

QALoad 05.07

---

Language Reference Commands



Technical support is available from our Customer Support Hotline or via our FrontLine Support Web site.

Customer Support Hotline:  
1-800-538-7822

FrontLine Support Web Site:  
<http://frontline.compuware.com>

This document and the product referenced in it are subject to the following legends:

Access is limited to authorized users. Use of this product is subject to the terms and conditions of the user's License Agreement with Compuware Corporation.

© 1998-2008 Compuware Corporation. All rights reserved. Unpublished - rights reserved under the Copyright Laws of the United States.

#### U.S. GOVERNMENT RIGHTS

Use, duplication, or disclosure by the U.S. Government is subject to restrictions as set forth in Compuware Corporation license agreement and as provided in DFARS 227.7202-1(a) and 227.7202-3(a) (1995), DFARS 252.227-7013(c)(1)(ii)(OCT 1988), FAR 12.212(a) (1995), FAR 52.227-19, or FAR 52.227-14 (ALT III), as applicable. Compuware Corporation.

This product contains confidential information and trade secrets of Compuware Corporation. Use, disclosure, or reproduction is prohibited without the prior express written permission of Compuware Corporation.

Compuware, ActiveAnalysis, ActiveData, Interval, QACenter, QADirector, QALoad, QARun, Reconcile, TestPartner, TrackRecord, and WebCheck are trademarks or registered trademarks of Compuware Corporation.

Acrobat® Reader copyright © 1987-2007 Adobe Systems Incorporated. All rights reserved. Adobe, Acrobat, and Acrobat Reader are trademarks of Adobe Systems Incorporated.

ICU License - ICU 1.8.1 and later COPYRIGHT AND PERMISSION NOTICE Copyright (c) 1995-2003 International Business Machines Corporation and others All rights reserved. Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, provided that the above copyright notice(s) and this permission notice appear in all copies of the Software and that both the above copyright notice(s) and this permission notice appear in supporting documentation. THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF THIRD PARTY RIGHTS. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR HOLDERS INCLUDED IN THIS NOTICE BE LIABLE FOR ANY CLAIM, OR ANY SPECIAL INDIRECT OR CONSEQUENTIAL DAMAGES, OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE. Except as contained in this notice, the name of a copyright holder shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization of the copyright holder.

All trademarks and registered trademarks mentioned herein are the property of their respective owners.

All other company or product names are trademarks of their respective owners.

US Patent Nos.: Not Applicable.

Doc. CWQLHX  
August 4, 2008

## Table Of Contents

QALoad Online Help .....	1
Language Reference Commands.....	2
Overview .....	2
.NET .....	2
Citrix.....	16
ODBC.....	45
Oracle Forms Server .....	89
QALoad .....	160
SAP.....	190
SSL.....	207
TestPartner .....	212
UNIFACE.....	216
Winsock .....	241
WWW .....	270
Index .....	347

## QALoad Online Help

# Language Reference Commands

## Overview

### List of QALoad Language Reference Commands

The QALoad Language Reference provides command reference information for general and middleware-specific commands. Select one of the middleware groups to display from the following list:

[.NET](#)

[Citrix](#)

[ODBC](#)

[Oracle Forms Server](#)

[QALoad](#)

[SAP](#)

[SSL](#)

[TestPartner](#)

[Uniface](#)

[Winsock](#)

[WWW](#)

## [.NET](#)

### [.NET Commands](#)

#### [BeginCheckpoint](#)

Marks the beginning of a checkpoint.

#### [Checkpoint Pair](#)

Inserts a checkpoints around the text you select.

#### [CLOSE\\_ALL\\_DATA\\_POOLS](#)

Closes all open local datapool files.

#### [CLOSE\\_DATA\\_POOL](#)

Closes the specified local datapool file.

#### [COUNTER\\_VALUE](#)

This command is used to update or increment the values of custom counters defined using the `DEFINE_COUNTER` command. As counter values are written to the timing file, they are time stamped with the elapsed time.

#### [DEFINE\\_COUNTER](#)

Use the `DEFINE_COUNTER` command to define custom counters. Custom counters are written and

managed on a per user basis. They will be saved to the timing file and can be graphed in Analyze. Counter data types can be either signed longs or floats. The counter type can be either cumulative or instance (which tells Analyze how to graph the counter.) Works in conjunction with the COUNTER\_VALUE command.

#### DO\_MSLEEP

Inserts a sleep for the number of seconds defined in the parameter.

#### DO\_SLEEP

Inserts a sleep for the number of seconds defined in the parameter.

#### EndCheckpoint

Indicates the end of a checkpoint, corresponding to a BeginCheckpoint command.

#### GET\_ABSOLUTE\_VUNUM

Gets the absolute virtual user number.

#### GET\_DATA

Requests that QALoad Conductor send the next datapool record to the script.

#### GET\_DATA\_FIELD

Accesses the fields from the data record that was just read using the READ\_DATA\_RECORD statement. Field numbering starts at 1.

#### GET\_RELATIVE\_VUNUM

Gets the relative virtual user number.

#### GET\_TOTAL\_TRANSACTIONS

Indicates the total number of transactions that will be performed. The value should be the same as the Transaction Count specified for the script from within the Conductor.

#### GET\_TRANSACTION\_NUMBER

Indicates the current transaction number that the Virtual User is performing. The value should be between zero and the Transaction Count specified for the script from within the Conductor.

#### OPEN\_DATA\_POOL

Opens the datapool file.

#### READ\_DATA\_RECORD

Reads a data record from a local datapool file.

#### RND\_DELAY

Delays the script for a random interval before proceeding.

#### RND\_DELAY\_RANGE

Delays the script for a random interval, within a specified range, before proceeding.

#### RR\_printf

Prints formatted output to the standard output stream.

#### SCRIPT\_MESSAGE

Inserts custom script messages into a timing file during test execution.

#### SLEEP

Pauses a script for the specified number of seconds. This command is not affected by the sleep factor

percentage specified in QALoad Conductor.

### **VARDATA**

Replaces a string with a datapool variable.

## **BeginCheckpoint**

Marks the beginning of a checkpoint.

You can turn enhanced checkpoints on or off from the QALoad Script Development Workbench's **Convert Options dialog box**. BeginCheckpoint is always used in conjunction with an **EndCheckpoint** command.

### **Syntax**

```
BeginCheckpoint ( char* CheckpointName );
```

### **Return Value**

### **Parameters**

Parameter	Description
CheckpointName	String containing a description of the checkpoint. This value cannot be longer than 127 characters.

### **Example**

```
BeginCheckpoint("Testing User-defined");  
DO_Http("GET http://compuweb.compuware.com/ HTTP/ 1.0\r\n\r\n");  
EndCheckpoint("Testing User-defined");
```

## **Checkpoint Pair**

Inserts a Begin Checkpoint item before the currently selected HTML Page and an End Checkpoint after the currently selected HTML Page.

Checkpoints are used to measure duration times for certain actions to be completed. You can move either the Begin or End checkpoint item to encompass several requests, if necessary. To move either item, highlight it and then click Move Up/Move Down in the form-view.

## **CLOSE\_ALL\_DATA\_POOLS**

Closes all open local datapool files.

All local datapool files should be closed at the end of the script using this statement.

### **Syntax**

```
CLOSE_ALL_DATA_POOLS ( );
```

### **Return Value**

### **Parameters**

None.



## Example

```

BeginCheckpoint();
RR_printf("Datapool Entry #1: %s", GET_DATA_FIELD 1);
DO_SLEEP(500);
EndCheckpoint(1);
CLOSE_ALL_DATA_POOLS ();
END_TRANSACTION( );

```

## CLOSE\_DATA\_POOL

Closes the specified local datapool file.

All local datapool files should be closed at the end of the script using these statements or the `CLOSE_ALL_DATA_POOLS` command.

### Syntax

```
CLOSE_DATA_POOL (int datapool ID);
```

### Return Value

### Parameters

Parameter	Description
Datapool ID	The local datapool file to close.

## Example

```

END_TRANSACTION();
CLOSE_DATA_POOL( SS_1 ); /* Default placement after */
/* END_TRANSACTION */

```

## COUNTER\_VALUE

Updates or increments the values of custom counters defined using the `DEFINE_COUNTER` command.

### Versions

Versions of `COUNTER_VALUE` are:


```
COUNTER_VALUE ( int Counter_ID, long Counter_Value );
```

```
COUNTER_VALUE ( int Counter_ID, float Counter_Value );
```

## DEFINE\_COUNTER

Defines custom counters.

Custom counters are written and managed on a per user basis. They are saved to the timing file and can be graphed in Analyze. Counter data types can be either signed longs or floats. The counter type can be either cumulative or instance, which tells Analyze how to graph the counter. Works in conjunction with the `COUNTER_VALUE` command.

 Note: If you call `DEFINE_COUNTER` more than once, with all of the same parameters, it returns the same counter ID.

## Language Reference Commands

### Syntax

```
int DEFINE_COUNTER ( char* Group_Name, char* Counter_Name, char* Units, CounterDataTypeEnum  
Data_Type, CounterCounterTypeEnum Counter_Type );
```

### Return Value

any value except -1 if successful

-1 if unsuccessful

### Parameters

Parameter	Description						
Group_Name	The name of the group this counter belongs to.						
Counter_Name	The name of the counter.						
Units	The counter units. Can be NULL if no units are needed for this counter.						
Data_Type	<i>CounterDataTypeEnum</i> Counter data type. Valid values are:  <table><thead><tr><th>Value</th><th>Description</th></tr></thead><tbody><tr><td>DATA_LONG</td><td>The counter values will be of type long.</td></tr><tr><td>DATA_FLOAT</td><td>The counter values will be of type float.</td></tr></tbody></table>	Value	Description	DATA_LONG	The counter values will be of type long.	DATA_FLOAT	The counter values will be of type float.
Value	Description						
DATA_LONG	The counter values will be of type long.						
DATA_FLOAT	The counter values will be of type float.						
Counter_Type	<i>CounterCounterTypeEnum</i> Counter type. Valid values are:  <table><thead><tr><th>Value</th><th>Description</th></tr></thead><tbody><tr><td>COUNTER_CUMULATIVE</td><td>The counter data is cumulative.</td></tr><tr><td>COUNTER_INSTANCE</td><td>The counter data is instance.</td></tr></tbody></table>	Value	Description	COUNTER_CUMULATIVE	The counter data is cumulative.	COUNTER_INSTANCE	The counter data is instance.
Value	Description						
COUNTER_CUMULATIVE	The counter data is cumulative.						
COUNTER_INSTANCE	The counter data is instance.						

### Example

```
// "CounterGroup", "Counter Name",  
// "Counter Units (Optional)" , Data Type, Counter Type.  
  
id1 = DEFINE_COUNTER( "Cumulative Group", "Cumulative long",  
0, DATA_LONG, COUNTER_CUMULATIVE);  
id2 = DEFINE_COUNTER( "Cumulative Group", "Cumulative float",  
0, DATA_FLOAT, COUNTER_CUMULATIVE);  
id3 = DEFINE_COUNTER( "Instance Group", "Instance long",  
0, DATA_LONG, COUNTER_INSTANCE);  
id4 = DEFINE_COUNTER( "Instance Group", "Instance float",  
0, DATA_FLOAT, COUNTER_INSTANCE);  
SYNCHRONIZE();  
BEGIN_TRANSACTION();
```

The following is an example of a command to call each time an error occurs:

```
void ErrorOneOccurred()  
{  
int errorCounterID;  
errorCounterID = DEFINE_COUNTER( "Some Error Group", "Error One", 0, DATA_LONG,  
COUNTER_CUMULATIVE );  
}
```

```
COUNTER_VALUE( errorCounterID, 1 );
}
```

## DO\_MSLEEP

Inserts a sleep for the number of seconds defined in the parameter.

The parameter passed to DO\_MSLEEP is first scaled by the sleep factor percentage specified in QALoad Conductor. During unit testing of the script, setting the sleep factor percentage to 0 (zero percent) causes DO\_MSLEEP not to sleep at all.

This command is ideal for unit testing where delays may not be wanted. Once the script is unit tested, the sleep factor percentage may be reset back to a suitable value, generally somewhere between 80% and 100%.

In addition, the sleep factor percentage can be set to Random in the QALoad Conductor. In this case, when a DO\_MSLEEP command is encountered, it sleeps for a random time frame ranging from 0 to the value specified.

### Syntax

```
DO_MSLEEP( int nMilliseconds );
```

### Return Value

### Parameters

Parameter	Description
nMilliseconds	Number of milliseconds to sleep.

### Example

This example shows how to pause a script for 5 seconds using the sleep function call. This example sleeps 5 seconds if the sleep factor percentage is set to 100 in the QALoad Conductor .

```
DO_MSLEEP( 5 ); /* Sleep 5 seconds */
```

## DO\_SLEEP

Inserts a sleep for the number of seconds defined in the parameter.

The parameter passed to DO\_SLEEP is first scaled by the sleep factor percentage specified in QALoad Conductor. During unit testing of the script, setting the sleep factor percentage to 0 (zero percent) causes DO\_SLEEP not to sleep at all.

This command is ideal for unit testing where delays may not be wanted. Once the script is unit tested, the sleep factor percentage may be reset back to a suitable value, generally somewhere between 80% and 100%.

In addition, the sleep factor percentage can be set to Random in the QALoad Conductor. In this case, when a DO\_SLEEP command is encountered, it sleeps for a random time frame ranging from 0 to the value specified.

### Syntax

```
DO_SLEEP( int nSeconds );
```

### Return Value

### Parameters

Parameter	Description
nSeconds	Number of seconds to sleep.

### Example

This example shows how to pause a script for 5 seconds using the sleep function call. This example sleeps 5 seconds if the sleep factor percentage is set to 100 in the QALoad Conductor .

```
DO_SLEEP( 5 ); /* Sleep 5 seconds */
```

### EndCheckpoint

Indicates the end of a checkpoint, corresponding to a BeginCheckpoint command.

BeginCheckpoint and EndCheckpoint correspond to QALoad's enhanced checkpoints. You can turn enhanced checkpoints on or off from the QALoad Script Development Workbench's [Convert Options dialog box](#). EndCheckpoint is always used in conjunction with a [BeginCheckpoint](#) command.

### Syntax

```
EndCheckpoint ( char* CheckpointName ) ;
```

### Return Value

### Parameters

Parameter	Description
CheckpointName	String containing a description of the checkpoint. This value cannot be longer than 127 characters.

### Example

```
BeginCheckpoint("Testing User-defined");
DO_Http("GET http://compuweb.compuware.com/ HTTP/ 1.0\r\n\r\n");
EndCheckpoint("Testing User-defined");
```

### GET\_ABSOLUTE\_VUNUM

Gets the absolute virtual user number. This value is used to identify a virtual user uniquely within an entire test.

### Syntax

```
int GET_ABSOLUTE_VUNUM ( );
```

### Return Value

int -- absolute virtual user number

### Parameters

None.

### Example

```
int vunum;
nunun = GET_ABSOLUTE_VUNUM();
RR_printf("I am vu %d", vunum);
```

## GET\_DATA

Requests that QALoad Conductor send the next datapool record to the script.

If you reach the end of the datapool file when this command is called, the script either exits with an END OF DATA status in QALoad Conductor, or rewinds to the beginning of the datapool file, depending on the status of the rewind option in QALoad Conductor.

### Syntax

```
GET_DATA ( );
```

### Return Value

### Parameters

None.

### Example

```
BEGIN_TRANSACTION( ); /*Beginning of transaction loop*/
GET_DATA ( );
...
RR__printf(VARDATA(1) );
```

## GET\_DATA\_FIELD

Accesses the fields from the data record that were just read using the READ\_DATA\_RECORD statement. Field numbering starts at one (1).

### Syntax

```
GET_DATA_FIELD (int datapool ID, int FieldNum);
```

### Return Value

### Parameters

Parameter	Description
Datapool ID	The datapool whose record should be used. This is necessary because you can have up to 32 local datapool files open at once.
FieldNum	Which field of the record to read. Field numbering starts at one (1).

### Example

```
BeginCheckpoint();
RR__printf("Datapool Entry #1: %s", GET_DATA_FIELD (1, 1) );
DO_SLEEP(500);
EndCheckpoint(1);
```

## GET\_RELATIVE\_VUNUM

Gets the relative virtual user number. This value is used to identify a virtual user uniquely within a player instance.

### Syntax

```
int GET_RELATIVE_VUNUM ( );
```

## Language Reference Commands

### Return Value

int -- relative virtual user number

### Parameters

None.

### Example

```
int vunum;  
nvvum = GET_RELATIVE_VUNUM();  
RR_printf("I am vu %d", vunum);
```

## GET\_TOTAL\_TRANSACTIONS

Indicates the total number of transactions that will be performed. The value should be the same as the Transaction Count specified for the script from within the Conductor.

### Syntax

```
int GET_TOTAL_TRANSACTIONS()
```

### Return Value

The total number of transactions as an Integer.

### Parameters

None

### Example

```
int x;  
x = GET_TOTAL_TRANSACTIONS();
```

## GET\_TRANSACTION\_NUMBER

Indicates the current transaction number that the Virtual User is performing. The value should be between zero and the Transaction Count specified for the script from within the Conductor.

### Syntax

```
int GET_TRANSACTION_NUMBER()
```

### Return Value

The current transaction number as an Integer.

### Parameters

None

### Example

```
int x;  
x = GET_TRANSACTION_NUMBER();
```

## OPEN\_DATA\_POOL

Opens the datapool file.

This command line is typically placed before the BEGIN\_TRANSACTION( ) statement.

## Syntax

```
OPEN_DATA_POOL (char* frame, int pNumber, int rewindflag);
```

## Return Value

## Parameters

Parameter	Description
frame	The name of the datapool file, including a drive and path.
pNumber	The ID that was given to the datapool when it was inserted into the script. This is used anytime the script reads a record or field from the datapool.
rewindFlag	TRUE if the datapool file should be rewound to the beginning after it reaches the end. FALSE if it should not rewind.

## Example

```
OPEN_DATA_POOL( "C:\\Program Files\\Compuware\\ QALoad \\Middlewares\\
    SQLServer\\Scripts\\junk.dat", SS_1, TRUE );

/* Default placement before BEGIN_TRANSACTION */
SYNCHRONIZE();
BEGIN_TRANSACTION();
```

## READ\_DATA\_RECORD

Reads a data record from a local datapool file.

This statement is typically placed after the BEGIN\_TRANSACTION statement, although it is possible to read more than one record from the file during a single transaction.

## Syntax

```
READ_DATA_RECORD( int datapool_ID );
```

## Return Value

## Parameters

Parameter	Description
Datapool_ID	Tells from which local datapool file to read the record.

## Example

```
BEGIN_TRANSACTION();
READ_DATA_RECORD( SS_1 ); /* Default placement - Start of */
/* Transaction loop */
```

## RND\_DELAY

Delays the script for a random interval before proceeding.

## Language Reference Commands

Each time the script executes the `RND_DELAY` command, the Player generates a random number. It uses a uniform distribution, between 0 and `n` seconds, where `n` is the parameter to the `RND_DELAY` command. The average delay time for multiple occurrences of this command is  $n/2$  seconds.

### Syntax

```
RND_DELAY ( int nSeconds );
```

### Return Value

### Parameters

Parameter	Description
<code>nSeconds</code>	Maximum number of seconds to delay before script execution proceeds.

## RND\_DELAY\_RANGE

Delays the script for a random interval, within a specified range, before proceeding.

Each time the script executes the `RND_DELAY_RANGE` command, the Player generates a random number. It uses a uniform distribution between `minTime` and `maxTime` seconds.

### Syntax

```
int RND_DELAY_RANGE (int minTime, int maxTime);
```

### Parameters

Parameter	Description
<code>minTime</code>	Minimum number of seconds to delay before script execution continues.
<code>maxTime</code>	Maximum number of seconds to delay before script execution continues.

### Example

In this example, the script pauses for a pseudo-random range between 2 and 10 seconds using the random delay range function.

```
RND_DELAY_RANGE(2, 10); /* Sleep between 2 and 10 seconds. */
```

## RR\_printf

Prints formatted output to the standard output stream.

`RR_printf` formats and prints a series of characters and values to the standard output stream, `stdout`. If arguments follow the format string, the format string must contain specifications that determine the output format for the arguments.

The format argument consists of ordinary characters, escape sequences, and, if arguments follow format, format specifications. The ordinary characters and escape sequences are copied to `stdout` in order of their appearance.

For example, the line:

```
RR_printf("Line one\n\t\tLine two\n");
```

produces the output:



Line one  
Line two

Format specifications always begin with a percent sign (%) and are read left to right. When `RR_printf` encounters the first format specification, if any, it converts the value of the first argument after format and outputs it accordingly. The second format specification causes the second argument to be converted and output, and so on. If there are more arguments than there are format specifications, the extra arguments are ignored. The results are undefined if there are not enough arguments for all the format specifications.

### Syntax

```
int RR_printf(const char * format [, argument]...);
```

### Return Value

The number of characters printed or a negative value if an error occurs.

### Parameters

Parameter	Description
format	Format control.
argument	Optional arguments.

### Example

```
/* This code segment shows examples of the usage of the RR_printf function to produce
formatted output for various datatypes. */

char ch='h', *string="computer";
int count=-9234;
double fp=251.7366;
wchar_t wch=L'w', *wstring=L"Unicode";

/*Display integers. */
RR_printf("Integer formats:\n" "\tDecimal: %d Justified: %.6d Unsigned: %u\n", count,
count, count, count);

RR_printf("Decimal %d as:\n\tHex: %Xh C hex: 0x%x Octal: %o\n", count, count, count,
count);

/* Display in different radices. */
RR_printf("Digits 10 equal:\n\tHex: %i Octal: %i Decimal: %i\n",0x10, 010, 10);

/* Display characters. */
RR_printf("Characters in field:\n%10c%5hc%5C%5lc\n", ch, ch, wch, wch);

/* Display strings. */
RR_printf("Strings in field:\n%25s\n%25.4hs\n\t%S%25.3ls\n", string, string, wstring,
wstring);

/* Display real numbers. */
RR_printf("Real numbers:\n\t%f%.2f%e%E\n", fp, fp, fp, fp);

/* Display pointer. */
RR_printf("\nAddress as:\t%p\n", &count);

/* Count characters printed. */
RR_printf("\nDisplay to here:\n");
RR_printf("1234567890123456\n78901234567890\n", &count);
RR_printf("\tNumber displayed: %d\n\n", count);
```

### Output

Integer formats:

## Language Reference Commands

Decimal: -9234  
Justified: -009234  
Unsigned: 4294958062

Decimal -9234 as:

Hex: FFFDBEEh  
C hex: 0xffffdbee  
Octal: 3777775756

Digits 10 equal:

Hex: 16  
Octal: 8  
Decimal: 10

Characters in field:

h h w w

Strings in field:

computer  
4hs  
Uni

Real numbers:

251.736600  
251.74 2.517366e+002

Address as:

0141FDC0

Display to here:

123456789012345678901234567890

Number displayed:

16

## SCRIPT\_MESSAGE

The **SCRIPT\_MESSAGE** command inserts custom script messages into a timing file during test execution. The command takes a group name and a message as parameters; the messages appear on the Error report in Analyze when they are used.

### Syntax

```
SCRIPT_MESSAGE ( char* group, char* msg );
```

### Parameters

Parameter	Description
group	Message group name.
msg	Message.

### Example

```
int rrobot_script( PLAYER_INFO *s_info )
```

```

{
    SET_ABORT_FUNCTION(abort_function);
    DEFINE_TRANS_TYPE( "CP01" );
    SYNCHRONIZE();

    BEGIN_TRANSACTION();
    SCRIPT_MESSAGE("My Group", "Message text here");
    END_TRANSACTION();
    REPORT(SUCCESS);
    EXIT();
    return(0);
}

```

## SLEEP

Pauses a script for the specified number of seconds.

This command is not affected by the sleep factor percentage specified in QALoad Conductor.

### Syntax

```
SLEEP ( int nSeconds );
```

### Return Value

### Parameters

Parameter	Description
nSeconds	The number of seconds to sleep before execution proceeds.

## VARDATA

Replaces a string with a datapool variable.

To insert data from the fields in a datapool, substitute VARDATA(n) expressions wherever you want to replace a string with variable data. Note that datapool field numbering starts at 1.

### Syntax

```
VARDATA(n)
```

### Return Value

### Parameters

Parameter	Description
n	The datapool field number. Field numbering starts at 1.

### Example

```
Do_TuxFMLData ( 8302, 0, VARDATA(1));
```

## Citrix

### Citrix Commands

#### BeginBlock

End of an if block of code.

#### CitrixInit

Initializes Citrix replay middleware resources.

#### CitrixUninit

Un-initializes the Citrix replay middleware resources. If the connection is still open, the function disconnects it.

#### CTX\_Error\_Handler

Outputs a fatal error message to the Conductor, which causes the virtual user to either fail or report a warning.

#### CtxClick

Clicks the specified button, using the specified modifier, at the current location.

#### CtxConnectICA

Connects to the Citrix server using an ICA file.

#### CtxConnectPubApp

Connects to a published application on a Citrix server or Citrix server farm.

#### CtxConnectServer

Connects to a Citrix server and possibly an application on the server.

#### CtxDisconnect

Disconnects from the Citrix server.

#### CtxDoubleClick

Double-clicks the mouse at the current location.

#### CtxFullBitmapExists

Checks to see if the current full screen bitmap matches the hash code passed into the BitmapHash argument.

#### CtxKeyDown

Inputs the keystroke specified by the key argument, which corresponds to the VK code.

#### CtxKeyUp

Inputs the keystroke specified by the key argument, which corresponds to the VK code.

#### CtxMouseDown

Presses the specified mouse button.

#### CtxMouseMove

Moves the mouse to the given coordinates with the given button and modifier.

#### CtxMouseUp

Releases the specified mouse button.

#### CtxPartialBitmapExists

Checks to see if the current partial screen bitmap matches the hash code passed into the BitmapHash argument.

**CtxPoint**

Moves the mouse to the specified location on the screen.

**CtxScreenEventExists**

Waits for the specified screen update to occur at the specified coordinates.

**CtxSetCitrixPort**

Sets the port for the Citrix client to use to connect to the server.

**CtxSetConnectTimeout**

Sets the number of seconds to wait for connections to the server to complete.

**CtxSetDisconnectTimeout**

Sets the number of seconds to wait for disconnections from the server to complete.

**CtxSetDomainLoginInfo**

Connects to the Citrix server with the specified user name, password, and domain.

**CtxSetEnableCounters**

Enables or disables custom counters for Citrix client-side statistics.

**CtxSetEnableWildcardMatching**

Enables or disables wildcard and substring name comparisons for matching Citrix window creation events.

**CtxSetGracefulDisconnect**

Specifies whether or not a logoff should be issued before issuing a disconnect.

**CtxWaitForFullBitmap**

Waits for a full screen bitmap to match the hash code passed into the BitmapHash argument.

**CtxWaitForPartialBitmap**

Waits for a partial screen bitmap to match the hash code passed into the BitmapHash argument.

**CtxSetWaitPointTimeout**

Sets the number of seconds to wait for a wait point.

**CtxSetWindowMatchTitle**

Sets the string to match the names of previously-created windows.

**CtxSetWindowRetries**

Sets the retry information for window verification.

**CtxSetWindowTimeout**

Sets the number of seconds to wait for windows to be activated and destroyed.

**CtxSetWindowVerification**

Enables or disables window verification for actions.

**CtxType**

Inputs the specified key strokes.

**CtxTypeChar**

Sends the specified ASCII character to the Citrix server.

**CtxTypeVK**

Sends the VK code that corresponds to a key typed by the user.

**CtxWaitForCaptionChange**

Waits for the specified window's caption to be changed.

**CtxWaitForScreenUpdate**

Waits for the specified screen update to occur at the specified coordinates.

## Language Reference Commands

### [CtxWaitForWindowActive](#)

Waits for the specified window to be activated (brought to the foreground).

### [CtxWaitForWindowCreate](#)

Waits for the specified window to be created.

### [CtxWaitForWindowDestroy](#)

Waits for the specified window to be destroyed.

### [CtxWaitForWindowLglIconChange](#)

Waits for the specified window's caption to be changed.

### [CtxWaitForWindowMinimize](#)

Waits for the specified window to be minimized.

### [CtxWaitForWindowMove](#)

Waits for the specified window to be moved to the specified coordinates.

### [CtxWaitForWindowResize](#)

Waits for the specified window to be resized to the specified dimensions.

### [CtxWaitForWindowSmIconChange](#)

Waits for the specified window's caption to be changed.

### [CtxWaitForWindowStyleChange](#)

Waits for the specified window's style to be changed as specified.

### [CtxWindowEventExists](#)

Checks to see if the specified window event has already occurred, and, if not, waits for the specified time for the event to occur.

### [EndBlock](#)

End of an else block of code.

## [BeginBlock](#)

End of an if block of code.

### [Syntax](#)

```
void BeginBlock();
```

### [Return Value](#)

None

### [Parameters](#)

None

### [Example](#)

```
// Window CWI_5 ("Citrix License Warning Notice") created 1087837373.062
if(CtxWindowEventExists(EVT_STR_CTXWINDOWCREATE, 3000, CWI_5))
BeginBlock();
CtxWaitForWindowCreate(CWI_5, 46);
EndBlock();
```

## CitrixInit

Initializes the Citrix replay middleware resources.

### Syntax

```
void CitrixInit (int flags);
```

### Return Value

None

### Parameters

Parameter	Description
flags	Reserved

### Example

```
CitrixInit(2);
```

## CitrixUninit

Un-initializes the Citrix replay middleware resources. If the connection is still open, this function disconnects it.

### Syntax

```
void CitrixUninit();
```

### Return Value

None

### Parameters

None

### Example

```
CitrixUninit();
```

## CTX\_Error\_Handler

Outputs a fatal error message to the Conductor, which causes the virtual user to either fail or report a warning.

### Syntax

```
void CTX_error_handler(PLAYERINFO *pInfo, char *msg);
```

### Return Value

### Parameters

Parameter	Description
-----------	-------------

## Language Reference Commands

pInfo	Pointer to the PLAYERINFO struct, <i>sinfo</i> .
msg	Message to be passed to the Conductor.

### Example

```
{
    char buffer[1024];
    sprintf(buffer, "App did not start. Stop script now!");
    CTX_error_handler(s_info, buffer);
}
```

### CtxClick

Clicks the specified button, using the specified modifier, at the current location.

### Syntax

```
void CtxClick(const CtxWI* windowInfo, long holdTime, CtxMouseButtonEnum button, CtxKeyModifierEnum mod);
```

### Return Value

### Parameters

Parameter	Description										
windowInfo	Pointer to a Citrix Window Information object containing window data.										
holdTime	Number of milliseconds to hold down the button.										
button	<p><i>CtxMouseButtonEnum</i></p> <p>A mouse button to use for this action</p> <table> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>NONE</td> <td>No keyboard modifier was specified</td> </tr> <tr> <td>L_BUTTON</td> <td>The left mouse button</td> </tr> <tr> <td>R_BUTTON</td> <td>The right mouse button</td> </tr> <tr> <td>M_BUTTON</td> <td>The middle mouse button</td> </tr> </tbody> </table>	Value	Description	NONE	No keyboard modifier was specified	L_BUTTON	The left mouse button	R_BUTTON	The right mouse button	M_BUTTON	The middle mouse button
Value	Description										
NONE	No keyboard modifier was specified										
L_BUTTON	The left mouse button										
R_BUTTON	The right mouse button										
M_BUTTON	The middle mouse button										
ModifierKeys	<p><i>CtxKeyModifierEnum</i></p> <p>The following modes are available:</p> <table> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>NONE</td> <td>No keyboard modifier was specified</td> </tr> <tr> <td>SHIFT</td> <td>Shift key</td> </tr> <tr> <td>CONTROL</td> <td>Control key</td> </tr> </tbody> </table>	Value	Description	NONE	No keyboard modifier was specified	SHIFT	Shift key	CONTROL	Control key		
Value	Description										
NONE	No keyboard modifier was specified										
SHIFT	Shift key										
CONTROL	Control key										



	ALT	Alt key
	EXTENDED	An extended key

### Example

```
CtxWI *CWI_7001c = new CtxWI(0x1001c, "Warning !!", 299, 139, 427, 351);
...
CtxClick(CWI_7001c, 109, L_BUTTON, NONE);
```

## CtxConnectICA

Connects to the Citrix server using an ICA file.

### Syntax

```
void CtxConnectICA (char* pszICAFile)
```

### Return Value

### Parameters

Parameter	Description
pszICAFile	ICA file name, excluding path.

### Example

```
/* Declare Variables */
const char *CitrixICAFilename = "Calculator2.ica";
BEGIN_TRANSACTION();
DO_SetTransactionStart();
CtxConnectICA(CitrixICAFilename);
```

## CtxConnectPubApp

Connects to a published application on a Citrix server or Citrix server farm.

### Syntax

```
void CtxConnectPubApp(char *pszPubAppName, char *pszCitrixServer)
```

### Return Value

### Parameters

Parameter	Description
pszPubAppName	Name of the published application.

<code>pszCitrixServer</code>	Name of the Citrix server.
------------------------------	----------------------------

### Example

```

/* Declare Variables */
const char *CitrixServer      = "dtw-labcitrix2";
const char *CitrixPubAppname = "Calc";
BEGIN_TRANSACTION();
DO_SetTransactionStart();
CtxConnectPubApp(CitrixPubAppname, CitrixServer);

```

## CtxConnectServer

Connects to a Citrix server and possibly an application on the server.

### Syntax

```
void CtxConnectServer (char *pszCitrixServer, char *pszApplication, char *pszWorkingDir)
```

### Return Value

### Parameters

Parameter	Description
<code>pszCitrixServer</code>	Name of the Citrix Server.
<code>pszApplication</code>	Name of the startup application.
<code>pszWorkingDir</code>	Working directory of the startup application.

### Example

```

/* Declare Variables */
const char *CitrixServer      = "qaccitrix";
const char *CitrixApplication = "calc.exe";
const char *CitrixAppWorkDir = "c:\\";
BEGIN_TRANSACTION();
DO_SetTransactionStart();
CtxConnectServer(CitrixServer, CitrixApplication, CitrixAppWorkDir);

```

## CtxDisconnect

Disconnects from the Citrix server.

### Syntax

```
void CtxDisconnect();
```

### Return Value

None

### Parameters

None

### Example

```
CtxDisconnect();
```

## CtxDoubleClick

Double-clicks the mouse at the current location. If Window Verification is enabled, ensure that the specified window is in the foreground.

### Syntax

```
void CtxDoubleClick(const CtxWI* windowInfo);
```

### Return Value

### Parameters

Parameter	Description
windowInfo	Pointer to a Citrix Window Information object containing window data.

### Example

```
CtxWI *CWI_7001c = new CtxWI(0x1001c, "Warning !!", 299, 139, 427, 351);
...
CtxDoubleClick(CWI_7001c);
```

## CtxFullBitmapExists

Checks to see if the current full screen bitmap matches the hash code passed into the BitmapHash argument and, if not, waits for the specified time for the bitmap to match.

### Versions

Versions of CtxFullBitmapExists are:

```
BOOL CtxFullBitmapExists(char *BitmapHash, char *BitmapTitle, long lTimeout = 0)
```

```
BOOL CtxFullBitmapExists(char *BitmapHash, char *BitmapTitle)
```

## CtxKeyDown

Inputs the key stroke specified by the key argument, which corresponds to the VK code. Ensure that *wi* is the foreground window.

### Syntax

```
void CtxKeyDown(const CtxWI *wi, int key);
```

### Return Value

### Parameters

Parameter	Description
wi	Pointer to a Citrix Window Information object containing window data.
key	Virtual Key code to type.

### Example

```
CtxWI *CWI_2006c = new CtxWI(0x40034, "blah", 303, 208, 418, 145);  
...  
CtxKeyDown(CWI_2006c, 107); // '+'  
DO_MSLEEP(93);  
CtxKeyUp(CWI_2006c, 107); // '+'
```

## CtxKeyUp

Inputs the key stroke specified by the key argument, which corresponds to the VK code. Ensure that wi is the foreground window.

### Syntax

```
void CtxKeyUp(const CtxWI* wi, int key);
```

### Return Value

### Parameters

Parameter	Description
wi	Pointer to a Citrix Window Information object containing window data.
key	Virtual Key code to type.

### Example

```
CtxWI *CWI_2006c = new CtxWI(0x40034, "blah", 303, 208, 418, 145);  
...  
CtxKeyDown(CWI_2006c, 103); // '7'  
DO_MSLEEP(93);  
CtxKeyUp(CWI_2006c, 103); // '7'
```

## CtxMouseDown

Presses the specified mouse button.

### Syntax

```
void CtxMouseDown(const CtxWI* windowInfo, CtxMouseButtonEnum button, CtxKeyModifierEnum mod, long Xpos, long Ypos);
```

## Return Value

## Parameters

Parameter	Description												
windowInfo	Pointer to a Citrix Window Information object containing window data.												
button	<p><i>CtxMouseButtonEnum</i></p> <p>A mouse button to use for this action</p> <table> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>NONE</td> <td>No mouse button was specified</td> </tr> <tr> <td>L_BUTTON</td> <td>The left mouse button</td> </tr> <tr> <td>R_BUTTON</td> <td>The right mouse button</td> </tr> <tr> <td>M_BUTTON</td> <td>The middle mouse button</td> </tr> </tbody> </table>	Value	Description	NONE	No mouse button was specified	L_BUTTON	The left mouse button	R_BUTTON	The right mouse button	M_BUTTON	The middle mouse button		
Value	Description												
NONE	No mouse button was specified												
L_BUTTON	The left mouse button												
R_BUTTON	The right mouse button												
M_BUTTON	The middle mouse button												
ModifierKeys	<p><i>CtxKeyModifierEnum</i></p> <p>The following modes are available</p> <table> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>NONE</td> <td>No keyboard modifier was specified</td> </tr> <tr> <td>SHIFT</td> <td>Shift key</td> </tr> <tr> <td>CONTROL</td> <td>Control key</td> </tr> <tr> <td>ALT</td> <td>Alt key</td> </tr> <tr> <td>EXTENDED</td> <td>An extended key</td> </tr> </tbody> </table>	Value	Description	NONE	No keyboard modifier was specified	SHIFT	Shift key	CONTROL	Control key	ALT	Alt key	EXTENDED	An extended key
Value	Description												
NONE	No keyboard modifier was specified												
SHIFT	Shift key												
CONTROL	Control key												
ALT	Alt key												
EXTENDED	An extended key												
Xpos	Move the mouse to this X coordinate.												
Ypos	Move the mouse to this Y coordinate.												

## Example

```

CtxWI *CWI_2006c = new CtxWI(0x40034, "blah", 303, 208, 418, 145);
...
CtxMouseDown(CWI_2006c, L_BUTTON, NONE, 274, 316);
DO_MSLEEP(109);
CtxMouseUp(CWI_2006c, L_BUTTON, NONE, 274, 316);

```

## CtxMouseMove

Move the mouse to the specified location on the screen.

### Syntax

```
void CtxMouseMove(long x, long y);
```

### Return Value

### Parameters

Parameter	Description
x	Move the mouse to this X coordinate.
y	Move the mouse to this Y coordinate.

### Example

```
CtxMouseMove(274, 316);
```

## CtxMouseUp

Releases the specified mouse button.

### Syntax

```
void CtxMouseUp(const CtxWI* windowInfo, CtxMouseButtonEnum button, CtxKeyModifierEnum mod, long Xpos, long Ypos);
```

### Return Value

### Parameters

Parameter	Description										
windowInfo	Pointer to a Citrix Window Information object containing window data.										
button	<p><i>CtxMouseButtonEnum</i></p> <p>A mouse button to use for this action</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>NONE</td> <td>No mouse button was specified</td> </tr> <tr> <td>L_BUTTON</td> <td>The left mouse button</td> </tr> <tr> <td>R_BUTTON</td> <td>The right mouse button</td> </tr> <tr> <td>M_BUTTON</td> <td>The middle mouse button</td> </tr> </tbody> </table>	Value	Description	NONE	No mouse button was specified	L_BUTTON	The left mouse button	R_BUTTON	The right mouse button	M_BUTTON	The middle mouse button
Value	Description										
NONE	No mouse button was specified										
L_BUTTON	The left mouse button										
R_BUTTON	The right mouse button										
M_BUTTON	The middle mouse button										
ModifierKeys	<p><i>CtxKeyModifierEnum</i></p> <p>The following modes are available</p>										

	Value	Description
	NONE	No keyboard modifier was specified
	SHIFT	Shift key
	CONTROL	Control key
	ALT	Alt key
	EXTENDED	An extended key
Xpos	Move the mouse to this X coordinate.	
Ypos	Move the mouse to this Y coordinate.	

### Example

```
CtxWI *CWI_2006c = new CtxWI(0x40034, "blah", 303, 208, 418, 145);
...
CtxMouseDown(CWI_2006c, L_BUTTON, NONE, 274, 316);
DO_MSLEEP(109);
CtxMouseUp(CWI_2006c, L_BUTTON, NONE, 274, 316);
```

### CtxPartialBitmapExists

Checks to see if the current partial screen bitmap matches the hash code passed into the BitmapHash argument and, if not, waits for the specified time for the bitmap to match.

#### Versions

Versions of CtxPartialBitmapExists are:

BOOL [CtxPartialBitmapExists](#)(char \*BitmapHash, char \*BitmapTitle, int x, int y, int width, int height, long lTimeout = 0)

BOOL [CtxPartialBitmapExists](#)(char \*BitmapHash, char \*BitmapTitle, int x, int y, int width, int height)

### CtxPoint

Moves the mouse to the specified location on the screen.

#### Syntax

```
void CtxPoint(long X, long Y);
```

#### Return Value

#### Parameters

Parameter	Description
x	X coordinate.

Y	Y coordinate.
---	---------------

**Example**

```
CtxPoint(509, 422);
```

**CtxScreenEventExists**

Checks to see if the specified screen event has already occurred and, if not, waits the specified time for the event to occur.

**Syntax**

```
BOOL CtxScreenEventExists(CitrixScreenEventTypeEnum EventType, int nmWait, const char* EventInfo);
```

**Return Value**

**Parameters**

Parameter	Description				
EventType	<p><i>CitrixScreenEventTypeEnum</i></p> <p>Citrix screen event. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>EVT_STR_CTXSCREENUPDATE</td> <td>Screen Update</td> </tr> </tbody> </table>	Value	Description	EVT_STR_CTXSCREENUPDATE	Screen Update
Value	Description				
EVT_STR_CTXSCREENUPDATE	Screen Update				
nmWait	Amount of time in milliseconds to wait for the event.				
EventInfo	Coordinates and size of target screen update in the format: x y width height.				

**Example**

```
CtxClick(CWI_2, 188, L_BUTTON, NONE); //1087322563.276
    if(CtxScreenEventExists(EVT_STR_CTXSCREENUPDATE,3000,"0 224 39 10"))
    BeginBlock();
        RR_printf("Screen Update Found Test1");
    EndBlock();
```

**CtxSetCitrixPort**

Sets the port for the Citrix client to use to connect to the server.

**Syntax**

```
void CtxSetCitrixPort (int port);
```

**Return Value**



## Parameters

Parameter	Description
port	The port number.

## Example

```
CtxSetCitrixPort (1494);
```

## CtxSetConnectTimeout

Sets the number of seconds to wait for connections to the server to complete.

## Syntax

```
void CtxSetConnectTimeout(int timeout);
```

## Return Value

## Parameters

Parameter	Description
timeout	Number of seconds to wait when attempting to connect.

## Example

```
//Use a timeout of 1 minute, 30 seconds for connect
CtxSetConnectTimeout(90);
```

## CtxSetDisconnectTimeout

Sets the number of seconds to wait for disconnections from the server to complete.

## Syntax

```
void CtxSetDisconnectTimeout(int timeout);
```

## Return Value

## Parameters

Parameter	Description
timeout	Number of seconds to wait when attempting to disconnect.

## Example

```
//Use a timeout of 1 minute, 30 seconds for disconnect
CtxSetDisconnectTimeout(90);
```

## CtxSetDomainLoginInfo

Specifies user name, password, and domain to use on connection to the Citrix server.

### Syntax

```
void CtxSetDomainLoginInfo (const char *username, const char *password, const char *domain);
```

### Return Value

### Parameters

Parameter	Description
username	The user name to use when connecting.
password	The password to use when connecting.
domain	The domain to use when connecting.

### Example

```
const char *CitrixUsername="citrix";
// QALoad "encrypts" the password in the script. The
// login functions also support regular strings.
const char *CitrixPassword    = "~encr~657E06726F697206";
const char *CitrixDomain      = "domain3";
...
CtxSetDomainLoginInfo (CitrixUsername, CitrixPassword, CitrixDomain);
```

## CtxSetEnableCounters

Enables or disables custom counters for Citrix client-side statistics.

### Syntax

```
void CtxSetEnableCounters (BOOL enable);
```

### Return Value

### Parameters

Parameter	Description
enable	TRUE or FALSE

### Example

```
CtxSetEnableCounters (TRUE);
```

## CtxSetEnableWildcardMatching

Enables or disables wildcard and substring name comparisons for matching Citrix window creation events.

### Syntax

```
void CtxSetEnableWildcardMatching (BOOL enable);
```

### Return Value

### Parameters

Parameter	Description
enable	TRUE or FALSE

### Example

```
CtxSetEnableWildcardMatching (TRUE); //Wildcards are enabled for this script
BEGIN_TRANSACTION();
```

See [CtxSetWindowMatchTitle](#) for another example of wildcards.

## CtxSetGracefulDisconnect

Specifies whether or not a logoff should be issued before issuing a disconnect. If this is set to false, the Citrix server may need to be properly configured to handle the lingering sessions.

### Syntax

```
void CtxSetGracefulDisconnect(BOOL enable)
```

### Return Value

N/A

### Parameters

Parameter	Description
enable	TRUE – a logoff will be issued before issuing a disconnect. BOOL – No logoff will be issued before issuing a disconnect

### Example

The following is an example of using `CtxSetGracefulDisconnect`

```
CtxSetGracefulDisconnect( TRUE );
```

## CtxSetOutputMode

Sets the output mode of the current script.

### Syntax

```
void CtxSetOutputMode(int iOutputMode)
```

Return Value

Parameters

Parameter	Description
iOutputMode	Output: OUTPUT_MODE_NORMAL OUTPUT_MODE_WINDOWLESS OUTPUT_MODE_RENDERLESS

Example

```
/* Declare Variables */
const int CitrixOutputMode = OUTPUT_MODE_NORMAL;
/* Citrix replay settings */
CtxSetOutputMode(CitrixOutputMode);
```

CtxSetWaitPointTimeout

Sets the number of seconds to wait for a wait point. This applies to all waitpoint timeouts other than window create and destroy waitpoint timeouts, which are set using CtxSetWindowTimeout.

Syntax

```
void CtxSetWaitPointTimeout (int timeout);
```

Return Value

Parameters

Parameter	Description
timeout	Number of seconds to wait for a waitpoint.

Example

```
CtxSetWaitPointTimeout (30);
```

CtxSetWindowMatchTitle

Sets the string to match the names of previously-created windows in the CtxWaitForWindowCreate method of the Citrix Window Information object.

This name is used for comparison if wildcards have been enabled by the CtxSetEnableWildcardMatching method call earlier in the script. You can use the CtxSetWindowMatchTitle function as many times as necessary in a script to change the window title match string after the window is created.

Syntax

```
void CtxSetWindowMatchTitle (CtxWI* windowInfo, char* strWindowMatchName);
```

## Return Value


## Parameters

Parameter	Description
windowInfo	Pointer to a Citrix Window Information object that contains window data.
strWindowMatchName	A character string of the name to match with wildcards.

## Example

```
CtxSetWindowMatchTitle(CWI_1, "*Microsoft Word"); //Sets the wildcard match name
```

```
CtxWaitForWindowCreate(CWI_1); //With the match name set above, finding
//any current window with a title ending in "Microsoft Word" will match
//and allow this function to return successfully.
```

 **Note:** The `CtxSetWindowMatchTitle` function can be used as many times as necessary in a script. The `CtxSetWindowTitle` function should appear each time the window title changes during capture after the window is created. When the window title contains variable content, such as transaction number or date and time, you can change the `CtxSetWindowTitle` command to `CtxSetWindowMatchTitle` and use wildcards for the variable content. To use this approach, you must enable the wildcard matching function using `CtxSetEnableWildcardMatching(TRUE)`.

## CtxSetWindowRetries

Sets the retry information for window verification.

If a window does not exist initially, the middleware waits for the number of milliseconds specified before retrying. The verification takes place for the number of times specified.

### Syntax

```
void CtxSetWindowRetries(int retries, int waittime);
```

## Return Value

## Parameters

Parameter	Description
retries	The number of times to retry verifying the window.
waittime	The number of milliseconds to wait between retries.

## Example

```
//Use 3 retries with a 3-second delay
CtxSetWindowRetries(3, 3000);
```

## CtxSetWindowTimeout

## Language Reference Commands

Set the number of seconds to wait for windows to be created and destroyed in the `CtxWaitForWindowCreate` and the `CtxWaitForWindowDestroy` waitpoint commands, respectively.

### Syntax

```
void CtxSetWindowTimeout (int timeout);
```

### Return Value

### Parameters

Parameter	Description
timeout	Number of seconds to wait for a window to be created.

### Example

```
CtxSetWindowTimeout (30);
```

## CtxSetWindowTitle

Sets the name of a previously-created window in the Citrix Window Information object.

### Syntax

```
void CtxSetWindowTitle(const CtxWI* windowInfo, const char *strWindowTitle);
```


### Return Value

### Parameters

Parameter	Description
windowInfo	Pointer to a Citrix Window Information object that contains window data.
strWindowTitle	Character string containing the new window title.

### Example

```
CtxWI *CWI_7 = new CtxWI(0x20122, "Untitled - Notepad", 72, 54, 481, 322);  
CtxWaitForWindowCreate(CWI_7, 500);  
// Update the window title after Notepad loads the file;  
// this is necessary so following script commands which reference window CWI_7  
// can properly match the window title.  
CtxSetWindowTitle(CWI_7, "SampleFile.txt - Notepad");
```

 **Note:** The `CtxSetWindowTitle` function should appear each time the window title changes during capture after the window is created. When the window title contains variable content, such as transaction number or date and time, you can change the `CtxSetWindowTitle` command to `CtxSetWindowMatchTitle` and use wildcards for the variable content. To use this approach, you must enable the wildcard matching function using `CtxSetEnableWildcardMatching(TRUE)`.

## CtxSetWindowVerification

Enables or disables window verification for actions.

### Syntax

```
void CtxSetWindowVerifiation (BOOL enable);
```

### Return Value

### Parameters

Parameter	Description
enable	TRUE or FALSE

### Example

```
CtxSetWindowVerification (TRUE);
```

## CtxType

Inputs the specified key strokes. If Window Verification is enabled, ensure that `wi` is the foreground window.

### Syntax

```
void CtxType(const CtxWI *wi, char *text);
```

### Return Value

### Parameters

Parameter	Description
wi	Pointer to a Citrix Window Information object containing window data.
text	ASCII text to type into the window.

### Example

```
CtxWI *CWI_40034 = new CtxWI(0x40034, "blah", 303, 208, 418, 145);
...
CtxType(CWI_40034, "HELLO");
```

## CtxTypeChar

Sends the specified ASCII character to the Citrix server.

Inputs the key stroke specified by the `key` argument, which corresponds to the character. Ensure that `wi` is the foreground window. This is equivalent to `CtxKeyDown(key)` and `CtxKeyUp(Key)`.

### Syntax

## Language Reference Commands

```
void CtxTypeChar(const CtxWI *wi, long vkey, CtxKeyModifierEnum mod);
```

### Return Value

### Parameters

Parameter	Description												
wi	Pointer to a Citrix Window Information object containing window data.												
key	Virtual Key code to type.												
mod	<p><i>CtxKeyModifierEnum</i></p> <p>The following modes are available:</p> <table><thead><tr><th>Value</th><th>Description</th></tr></thead><tbody><tr><td>NONE</td><td>No keyboard modifier was specified</td></tr><tr><td>SHIFT</td><td>Shift key</td></tr><tr><td>CONTROL</td><td>Control key</td></tr><tr><td>ALT</td><td>Alt key</td></tr><tr><td>EXTENDED</td><td>An extended key</td></tr></tbody></table>	Value	Description	NONE	No keyboard modifier was specified	SHIFT	Shift key	CONTROL	Control key	ALT	Alt key	EXTENDED	An extended key
Value	Description												
NONE	No keyboard modifier was specified												
SHIFT	Shift key												
CONTROL	Control key												
ALT	Alt key												
EXTENDED	An extended key												

### Example

```
CtxTypeChar(CWI_3001e, 'F', ALT); //Send ALT-F
```

## CtxTypeVK

Sends the VK code that corresponds to a key typed by the user.

Inputs the key stroke specified by the key argument, which corresponds to the VK code. Ensure that wi is the foreground window. This is equivalent to `CtxKeyDown(key)` and `CtxKeyUp(Key)`.

### Syntax

```
void CtxTypeVK(const CtxWI *wi, long vkey, CtxKeyModifierEnum mod);
```

### Return Value

### Parameters

Parameter	Description
wi	Pointer to a Citrix Window Information object containing window data.
key	Virtual Key code to type.



mod	<p><i>CtxKeyModifierEnum</i></p> <p>The following modes are available:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>NONE</td> <td>No keyboard modifier was specified</td> </tr> <tr> <td>SHIFT</td> <td>Shift key</td> </tr> <tr> <td>CONTROL</td> <td>Control key</td> </tr> <tr> <td>ALT</td> <td>Alt key</td> </tr> <tr> <td>EXTENDED</td> <td>An extended key</td> </tr> </tbody> </table>	Value	Description	NONE	No keyboard modifier was specified	SHIFT	Shift key	CONTROL	Control key	ALT	Alt key	EXTENDED	An extended key
Value	Description												
NONE	No keyboard modifier was specified												
SHIFT	Shift key												
CONTROL	Control key												
ALT	Alt key												
EXTENDED	An extended key												

### Example

```
CtxTypeVK(CWI_3001e, VK_RIGHT, EXTENDED); //Send the right arrow key
```

## CtxWaitForCaptionChange

Waits for the specified window's caption to be changed.

### Syntax

```
void CtxWaitForCaptionChange(const CtxWI *wi, const char *newcaption, long nmWait);
```

### Return Value

### Parameters

Parameter	Description
wi	Pointer to a Citrix Window Information object containing window data.
newcaption	String representing new window caption.
nmWait	Timeout offset, in milliseconds. Amount to increase or decrease the wait time specified by CtxSetWaitPointTimeout.

### Example

```
DO_MSLEEP (234);

// Wait for the title of the window that matches CWI_11 to change to "new title"
CtxWaitForCaptionChange (CWI_11, "new title", 2000);

DO_MSLEEP (125);
```

## CtxWaitForFullBitmap

Waits for a full screen bitmap to match the hash code passed into the BitmapHash argument.

### Versions

Versions of CtxWaitForFullBitmap are:

```
void CtxWaitForFullBitmap(char *BitmapHash, char *BitmapTitle, long lTimeoutOffset = 0)
```

```
void CtxWaitForFullBitmap(char *BitmapHash, char *BitmapTitle)
```

### CtxWaitForPartialBitmap

Waits for a partial screen bitmap to match the hash code passed into the BitmapHash argument.

### Versions

Versions of CtxWaitForPartialBitmap are:

```
void CtxWaitForPartialBitmap(char *BitmapHash, char *BitmapTitle, int x, int y, int width, int height, long lTimeoutOffset = 0)
```

```
void CtxWaitForPartialBitmap(char *BitmapHash, char *BitmapTitle, int x, int y, int width, int height)
```

### CtxWaitForScreenUpdate

Waits for the specified screen update to occur at the specified coordinates.

### Syntax

```
void CtxWaitForScreenUpdate(long x, long y, long w, long h, long nmWait);
```

### Return Value

### Parameters

Parameter	Description
x	X coordinate
y	Y coordinate
w	Width of the screen update
h	Height of the screen update
nmWait	Timeout offset, in milliseconds. Amount to increase or decrease the wait time specified by CtxSetWaitPointTimeout.

### Example

```
CtxWaitForScreenUpdate(154, 154, 253, 261, 500);
```

### CtxWaitForWindowActivate

Waits for the specified window to be activated (brought to the foreground).

### Syntax

```
void CtxWaitForWindowActivate(const CtxWI *wi, long nmWait);
```

## Return Value

## Parameters

Parameter	Description
wi	Pointer to a Citrix Window Information object containing window data.
nmWait	Timeout offset, in milliseconds. Amount to increase or decrease the wait time specified by CtxSetWaitPointTimeout.

## Example

```
CtxWI *CWI_40034 = new CtxWI(0x40034, "Please wait...", 303, 208, 418, 145);
...
CtxWaitForWindowActivate(CWI_40034, 500);
```

## CtxWaitForWindowCreate

Waits for the specified window to be created.

### Syntax

```
void CtxWaitForWindowCreate(const CtxWI *wi, long nmWait);
```

## Return Value

## Parameters

Parameter	Description
wi	Pointer to a Citrix Window Information object containing window data.
nmWait	Timeout offset, in milliseconds. Amount to increase or decrease the wait time specified by CtxSetWindowTimeout.

## Example

```
CtxWI *CWI_40034 = new CtxWI(0x40034, "Please wait...", 303, 208, 418, 145);
...
CtxWaitForWindowCreate(CWI_40034, 500);
```

## CtxWaitForWindowDestroy

Waits for the specified window to be destroyed.

### Syntax

```
void CtxWaitForWindowDestroy(const CtxWI *wi, long nmWait);
```

## Return Value

Parameters

Parameter	Description
wi	Pointer to a Citrix Window Information object containing window data.
nmWait	Timeout offset, in milliseconds. Amount to increase or decrease the wait time specified by CtxSetWindowTimeout.

Example

```
CtxWI *CWI_40034 = new CtxWI(0x40034, "Please wait...", 303, 208, 418, 145);
...
CtxWaitForWindowDestroy(CWI_40034, 500);
```

### CtxWaitForWindowLgIconChange

Waits for the specified window's large icon to be changed.

Syntax

```
void CtxWaitForWindowLgIconChange(const CtxWI *wi, const char *hash, long nmWait);
```

Return Value

Parameters

Parameter	Description
*wi	Pointer to a Citrix Window Information object containing window data.
*hash	Unique hash of icon bitmap.
nmWait	Timeout offset, in milliseconds. Amount to increase or decrease the wait time specified by CtxSetWaitPointTimeout.

Example

```
// Window CWI_13 ("Windows Task Manager") created 1101909450.125
CtxWaitForWindowCreate(CWI_13, 110);
CtxPoint(327, 2); //1101909452.531
CtxWaitForWindowLgIconChange(CWI_13, "c48b65c8b825324a5ff73638118fb8fc", 1218);
```

### CtxWaitForWindowMinimize

Waits for the specified window to be minimized.

Syntax

```
void CtxWaitForWindowMinimize(const CtxWI *wi, long nmWait);
```

Return Value

### Parameters

Parameter	Description
wi	Pointer to a Citrix Window Information object containing window data.
nmWait	Timeout offset, in milliseconds. Amount to increase or decrease the wait time specified by CtxSetWaitPointTimeout.

### Example

```
CtxWI *CWI_40034 = new CtxWI(0x40034, "Please wait...", 303, 208, 418, 145);
...
CtxWaitForWindowMinimize(CWI_40034, 500);
```

## CtxWaitForWindowMove

Waits for the specified window to be moved to the specified coordinates.

### Syntax

```
void CtxWaitForWindowMove(const CtxWI *wi, long x, long y, long nmWait);
```

### Return Value

### Parameters

Parameter	Description
wi	Pointer to a Citrix Window Information object containing window data
x	X coordinate
y	Y coordinate
nmWait	Timeout offset, in milliseconds. Amount to increase or decrease the wait time specified by CtxSetWaitPointTimeout.

### Example

```
CtxWI *CWI_40034 = new CtxWI(0x40034, "Please wait...", 303, 208, 418, 145);
...
CtxWaitForWindowMove(CWI_40034, 132, 297, 2000);
```

## CtxWaitForWindowResize

Waits for the specified window to be resized to the specified dimensions.

### Syntax

```
void CtxWaitForWindowResize(const CtxWI *wi, long w, long h, long nmWait);
```

Return Value

Parameters

Parameter	Description
wi	Pointer to a Citrix Window Information object containing window data.
w	X coordinate.
h	Y coordinate.
nmWait	Timeout offset, in milliseconds. Amount to increase or decrease the wait time specified by CtxSetWaitPointTimeout.

Example

```
CtxWI *CWI_40034 = new CtxWI(0x40034, "Please wait...", 303, 208, 418, 145);
...
CtxWaitForWindowResize(CWI_40034, 100, 200, 500);
```

CtxWaitForWindowSmIconChange

Waits for the specified window's small icon to be changed.

Syntax

```
void CtxWaitForWindowSmIconChange(const CtxWI *wi, const char *hash, long nmWait);
```

Return Value

Parameters

Parameter	Description
*wi	Pointer to a Citrix Window Information object containing window data.
*hash	Unique hash of icon bitmap.
nmWait	Timeout offset, in milliseconds. Amount to increase or decrease the wait time specified by CtxSetWaitPointTimeout.

Example

```
// Window CWI_13 ("Windows Task Manager") created 1101909450.125
CtxWaitForWindowCreate(CWI_13, 110);
CtxPoint(327, 2); //1101909452.531
CtxWaitForWindowSmIconChange(CWI_13, "924f75dd0db6ecb28d3e513053a8038e", 1391);
```

## CtxWaitForWindowStyleChange

Waits for the specified window's style to be changed as specified.

### Syntax

```
void CtxWaitForWindowStyleChange(const CtxWI *wi, long style, long extendedStyle, long nmWait);
```

### Return Value

### Parameters

Parameter	Description
wi	Pointer to a Citrix Window Information object containing window data.
style	Bit mask that corresponds to the window style.
extendedStyle	Bit mask that corresponds to the extended window style.
nmWait	Timeout offset, in milliseconds. Amount to increase or decrease the wait time specified by CtxSetWaitPointTimeout.

### Example

```
Point (155, 1);
DO_MSLEEP (515);
//Wait for the window that matches CWI_11 to maximize
CtxWaitForWindowStyleChange (CWI_11, 0x14ca0044, 0x50100, 500);
DO_MSLEEP (11047);
```

## CtxWindowEventExists

Checks to see if the specified screen event has already occurred and, if not, waits for the specified time for the event to occur.

### Syntax

```
BOOL CtxWindowEventExists(CitrixWindowEventTypeEnum EventType, int nmWait, const CtxWI *wi);
```

### Return Value

### Parameters

Parameter	Description		
EventType	<p><i>CitrixWindowEventTypeEnum</i></p> <p>Citrix window event. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> </tbody> </table>	Value	Description
Value	Description		

## Language Reference Commands

	EVT_STR_CTXWINDOWCREATE	WindowCreate
	EVT_STR_CTXWINDOWACTIVATE	WindowActivate
	EVT_STR_CTXWINDOWMOVE	WindowMove
	EVT_STR_CTXWINDOWDEACTIVATE	WindowDeactivate
	EVT_STR_CTXWINDOWDESTROY	WindowDestroy
	EVT_STR_CTXWINDOWSIZE	WindowResize
	EVT_STR_CTXWINDOWMINIMIZE	WindowMinimize
	EVT_STR_CTXWINDOWCAPTIONCHANGE	WindowCaptionChange
	EVT_STR_CTXWINDOWSMALLICONCHANGE	WindowSmallIconChange
	EVT_STR_CTXWINDOWLARGEICONCHANGE	WindowLargeIconChange
	EVT_STR_CTXWINDOWSTYLECHANGE	WindowStyleChange
nmWait	Amount of time in milliseconds to wait for the event.	
wi	Pointer to a Citrix Window Information object containing window data.	

### Example

```
// Window CWI_15 ("Open") destroyed 1087837404.827
if(CtxWindowEventExists(EVT_STR_CTXWINDOWCREATE,3000,CWI_16))
BeginBlock();

    CtxPoint(337, 265); //1087837404.905
    // Window CWI_16 ("11111111 - Microsoft Word") created 1087837404.905
    CtxWaitForWindowCreate(CWI_16, 31);
    // Window CWI_14 ("Document1 - Microsoft Word") destroyed 1087837404.905
    DO_MSLEEP(7547);
    CtxPoint(628, 9); //1087837414.592
    DO_MSLEEP(2141);
    CtxClick(CWI_16, 281, L_BUTTON, NONE); //1087837414.873
    DO_MSLEEP(234);
    // Window CWI_16 ("11111111 - Microsoft Word") destroyed 1087837415.108
    CtxPoint(113, 93); //1087837418.779
    // Window CWI_17 ("") created 1087837418.779
EndBlock();
```

### EndBlock

End of an else block of code.

### Syntax



```
void EndBlock();
```

#### Return Value

None

#### Parameters

None

#### Example

```
// Window CWI_5 ("Citrix License Warning Notice") created 1087837373.062
if(CtxWindowEventExists(EVT_STR_CTXWINDOWCREATE, 3000, CWI_5))
BeginBlock();
CtxWaitForWindowCreate(CWI_5, 46);
EndBlock();
```

## ODBC

### ODBC Commands

#### DO\_FreeODBC

Releases the memory used by QALoad's ODBC driver. It should only be called once at the end of a script.

#### DO\_initODBC

Initializes QALoad's internal ODBC variables. Must be called at the beginning of the script prior to any other calls.

#### DO\_LoadMem

Fills the memory location described in a corresponding DO\_SQLBindParameter call. The data, sData, is always represented as a string. DO\_LoadMem enables sending multiple pieces of data into the same bind call by loading memory that was added with a DO\_SQLBindParameter call.

#### DO\_SQLAllocConnect

The connection handle must be allocated before the actual connection can take place. It is important that each DO\_SQLAllocConnect call is matched up with a similar DO\_SQLFreeConnect, either inside of the transaction loop or outside of the transaction loop.

#### DO\_SQLAllocHandle

Allocates handles. Replaces DO\_SQLAllocStmt.

#### DO\_SQLAllocStmt

Allocates a statement handle and assigns it to a previously open connection.

#### DO\_SQLBindCol

Binds application buffers to a specific column of a statement. The columns are identified by number in the result set.

#### DO\_SQLBindParameter

Used to describe a memory location between the application and the database. This memory location is used to exchange data between the application and the database.

#### DO\_SQLCancel

Cancels the processing of the present SQL statement.

## Language Reference Commands

### [DO\\_SQLCloseCursor](#)

Closes a cursor associated with a handle and discards the results.

### [DO\\_SQLColAttribute](#)

Returns descriptor information for a column in a result set.

### [DO\\_SQLColumns](#)

Retrieves the column information of the selected tables.

### [DO\\_SQLConnect](#)

Performs a connection to the database.

### [DO\\_SQLCopyDesc](#)

If the values of the SourceDescHandle and TargetDescHandle parameters are associated with the same driver, the driver copies all descriptor fields. This is true even if the drivers are on different connections or environments. If the values of the parameters are not associated with the same driver, only ODBC-defined fields are copied.

### [DO\\_SQLDescribeCol](#)

Returns descriptor information to the statement handle.

### [DO\\_SQLDisconnect](#)

Closes the connection from the application to the database server.

### [DO\\_SQLDriverConnect](#)

Connects the application to the database.

### [DO\\_SQLEndTran](#)

Provides the mechanism for all open transactions or all open transactions on a particular connection to be resolved.

### [DO\\_SQLExecDirect](#)

Prepares and executes a SQL statement.

### [DO\\_SQLExecute](#)

Executes a prepared command using the current values of the parameter marker variables, if any parameter markers exist in the command.

### [DO\\_SQLFetch](#)

Retrieves a single row of data.

### [DO\\_SQLFreeConnect](#)

Performs the cleanup of connection handles for ODBC/DB2 within a QALoad script.

### [DO\\_SQLFreeHandle](#)

In ODBC, DO\_SQLFreeHandle handles statement and descriptor cleanup. In DB2, DO\_SQLFreeHandle handles the additional cleanup of connection handles. Each occurrence of DO\_SQLFreeHandle must have a corresponding DO\_SQLAllocHandle, either both within the transaction loop or both outside of the transaction loop.

### [DO\\_SQLFreeStmt](#)

Stops processing associated with a specific command\_index and:

### [DO\\_SQLGetCursorName](#)

Use on an open ODBC/DB2 statement to return a char \* containing the cursor active on a particular

statement.

#### [DO\\_SQLGetData](#)

Retrieves data for a single column in the form of a string.

#### [DO\\_SQLGetDescField](#)

Returns the value of a field of a descriptor record.

#### [DO\\_SQLGetDescRec](#)

Returns the settings or values from fields of a descriptor record set by [DO\\_SQLSetDescRec](#), including name, data type, and column or parameter data storage. Does not retrieve values for header fields.

#### [DO\\_SQLGetEnvAttr](#)

Gets a characteristic of an environment.

#### [DO\\_SQLGetTypeInfo](#)

Returns information about data types supported by the data source.

#### [DO\\_SQLNumResultCols](#)

Determines the number of columns being returned in a result set.

#### [DO\\_SQLParamData](#)

Used in conjunction with [DO\\_SQLPutData](#) to supply parameter data at statement execution time.

#### [DO\\_SQLPrepare](#)

Prepares an SQL statement and associates the results with the `command_index`. The command is not executed until the [DO\\_SQLExecute](#) command is called.

#### [DO\\_SQLRetrieveParamValue](#)

Retrieves a value of a `SQL_PARAM_INPUT_OUTPUT` or `SQL_PARAM_OUTPUT` parameter, following the execution of the corresponding SQL statement.

#### [DO\\_SQLRowCount](#)

Returns an integer indicating the number of rows affected by the last SQL statement associated with the specified `command_index`.

#### [DO\\_SQLSetConnectAttr](#)

Sets a characteristic of the connection.

#### [DO\\_SQLSetConnectOption](#)

Sets options on the connection handle.

#### [DO\\_SQLSetCursorName](#)

Associates a cursor name with an active `command_index`.

#### [DO\\_SQLSetDescField](#)

Sets a descriptor field. A call to [DO\\_SQLSetDescField](#) can set a field of any descriptor type that can be set.

#### [DO\\_SQLSetDescRec](#)

Sets multiple descriptor fields with a single call.

#### [DO\\_SQLSetEnvAttr](#)

Sets different aspects of the ODBC environment.

#### [DO\\_SQLSetPos](#)

## Language Reference Commands

Sets cursor locking and direction properties.

### [DO\\_SQLSetStmtAttr](#)

Sets statement attributes and, as a result, sets descriptor fields.

### [DO\\_SQLSetStmtOption](#)

Sets the boundaries of a specific statement handle.

### [DO\\_SQLSpecialColumns](#)

Retrieves information about columns within a specified table. `DO_SQLSpecialColumns` retrieves the following information:

### [DO\\_SQLStatistics](#)

Retrieves a list of statistics about a single table and the indexes associated with the table. The driver returns the information as a result set.

### [DO\\_SQLTables](#)

Returns the list of table names stored in a specific data source. The driver returns the information as a result set.

### [DO\\_SQLTransact](#)

Requests a commit or rollback operation for all update, insert, and delete transactions in progress on all command indexes associated with a connection. Can also request that a commit or rollback operation be performed for all connections by specifying a connection index of -1.

### [DO\\_substr](#)

Finds a value within a string.

### [GetBindColumnData](#)

Retrieves data from one of the rows that are returned by `DO_SQLFetch` calls, after a combination of `DO_SQLSetStmtAttr` and `DO_SQLBindCol` calls.

## Using descriptors

Descriptors are new to ODBC with release ODBC 3.x. They offer a way of tracking column metadata. Descriptors can be used for a number of different purposes, and can be shared by different statements. In most cases, an application doesn't require access to descriptors; however, in some cases accessing descriptors can simplify a number of operations.

There are four types of descriptors:

- ! Application Parameter Descriptor (APD)  
Contains either the input parameters set up by the application or the output columns following the execution of a CALL statement within SQL.
- ! Application Row Descriptor (ARD)  
Contains the row data as the row is presented to the application.
- ! Implementation Row Descriptor (IRD)  
Contains the row as it comes from the database.
- ! Implementation Parameter Descriptor (IPD)  
Contains the parameter elements after conversion heading to the database.

For more information on ODBC descriptors, refer to your ODBC 3.0 Programmer's Reference Volume and SDK Guide.

### Handling connection descriptors

It is important to note that QALoad processes descriptor handles in the same way it processes statement handles. Each connection handle is associated with a unique descriptor handle. Each time a descriptor is allocated during conversion, QALoad associates descriptors with connections the same way that ODBC does.

### DO\_FreeODBC

Releases the memory used by QALoad 's ODBC driver. It should only be called once at the end of a script.

#### Syntax

```
DO_FreeODBC( PLAYERINFO* sInfo );
```

#### Return Value

#### Parameters

Parameter	Description
sInfo	Structure used by each virtual user.

#### Example

```
END_TRANSACTION();
DO_FreeODBC( sInfo );
REPORT( SUCCESS );
EXIT();
```

### DO\_initODBC

Initializes QALoad 's internal ODBC variables. Must be called at the beginning of the script before any other calls.

#### Syntax

```
DO_initODBC( int nVersion, PLAYER_INFO* sInfo );
```

#### Return Value

#### Parameters

Parameter	Description
nVersion	This argument deals with the version of ODBC. ODBC uses different functions to allocate and free different structures to handle different properties of connections, statements, and the environment. In order to handle the behavior properly, QALoad detects and passes the version number into the script.
sInfo	This needs to be passed in order to properly initialize the Thread Local Storage.

#### Example

```
SET_ABORT_FUNCTION( abort_function );
DEFINE_TRANS_TYPE( "wilson.c" );
// Checkpoints have been included by the convert process
```

## Language Reference Commands

```
DefaultCheckpointsOn();  
DO_initODBC( 3, sInfo );
```

### DO\_LoadMem

Fills the memory location described in a corresponding DO\_SQLBindParameter call.

The data, sData, is always represented as a string. DO\_LoadMem enables sending multiple pieces of data into the same bind call by loading memory that was added with a DO\_SQLBindParameter call.

#### Syntax

```
DO_LoadMem( int nStmtIndex, int nParamNum, char* sData, int nBufLen );
```

#### Return Value

#### Parameters

Parameter	Description
nStmtIndex	Index into the table of statement handles.
nParamNum	Number of the parameter. This matches the value in DO_SQLBindCol.
sData	String representation of the data.
nBufLength	Length of the string.

#### Example

```
DO_SQLPrepare( S0, sql_statement );  
DO_SQLBindParameter( S0, 1, SQL_PARAM_OUTPUT, SQL_C_ULONG, SQL_INTEGER, 0, 0, 4, 4 );  
DO_SQLBindParameter( S0, 2, SQL_PARAM_OUTPUT, SQL_C_ULONG, SQL_INTEGER, 0, 0, 4, 4 );  
DO_SQLBindParameter( S0, 3, SQL_PARAM_OUTPUT, SQL_C_ULONG, SQL_INTEGER, 0, 0, 4, 4 );  
DO_SQLBindParameter( S0, 4, SQL_PARAM_OUTPUT, SQL_C_ULONG, SQL_INTEGER, 0, 0, 4, 4 );  
DO_SQLBindParameter( S0, 5, SQL_PARAM_OUTPUT, SQL_C_ULONG, SQL_INTEGER, 0, 0, 4, 4 );  
DO_LoadMem( S0, 1, "22", 4 );  
DO_LoadMem( S0, 2, "0", 4 );  
DO_LoadMem( S0, 3, "0", 4 );  
DO_LoadMem( S0, 4, "0", 4 );  
DO_LoadMem( S0, 5, "0", 4 );  
DO_SQLExecute( S0 );
```

### DO\_SQLAllocConnect

Allocates a connection handle.

The connection handle must be allocated before the actual connection can take place. It is important that each DO\_SQLAllocConnect call is matched up with a similar DO\_SQLFreeConnect, either inside the transaction loop or outside the transaction loop.

Use DO\_SQLAllocHandle in place of DO\_SQLAllocConnect if using ODBC version 3 or higher.

#### Syntax

```
DO_SQLAllocConnect( int HDBCIndex );
```

#### Return Value

## Parameters

Parameter	Description
ConnectionIndex	Points to a structure that ODBC uses to track different connection settings, statements within the connection, and descriptors allocated within the connection.

## Example

```
DO_SQLAllocConnect( C0 );
DO_SQLConnect( C0, "fhloadb2", "sa", "" );
DO_SQLDisconnect( C0 );
DO_SQLFreeConnect( C0 );
```

## DO\_SQLAllocHandle

Allocates handles. Replaces DO\_SQLAllocStmt.

Previous versions of ODBC used different statements to allocate different structures. ODBC 3.x uses a single handle allocation function instead, which is represented by DO\_SQLAllocHandle in QALoad .

## Syntax

```
DO_SQLAllocHandle ( ODBCSQLHandleTypeEnum handleType, int IncomingIndex, int OutgoingIndex)
```

## Return Value

## Parameters

Parameter	Description										
handleType	<p><i>ODBCSQLHandleTypeEnum</i></p> <p>The type of handle to be allocated. Each handle takes different arguments. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>SQL_HANDLE_ENV</td> <td>Environment handle</td> </tr> <tr> <td>SQL_HANDLE_DBC</td> <td>Connection handle</td> </tr> <tr> <td>SQL_HANDLE_STMT</td> <td>Statement handle</td> </tr> <tr> <td>SQL_HANDLE_DESC</td> <td>Descriptor handle</td> </tr> </tbody> </table>	Value	Description	SQL_HANDLE_ENV	Environment handle	SQL_HANDLE_DBC	Connection handle	SQL_HANDLE_STMT	Statement handle	SQL_HANDLE_DESC	Descriptor handle
Value	Description										
SQL_HANDLE_ENV	Environment handle										
SQL_HANDLE_DBC	Connection handle										
SQL_HANDLE_STMT	Statement handle										
SQL_HANDLE_DESC	Descriptor handle										
IncomingIndex	The structure that the outgoing handle will belong to. An environment handle is the incoming handle for a connection. A connection handle is the incoming handle for statements and for descriptors. When allocating the environment, pass in the following value for the incoming handle argument: <code>SQL_NULL_HANDLE</code> .										
OutgoingIndex	Points to the location of the structure that will store information for each of the different structures that ODBC uses.										

## Language Reference Commands

### Example

```
DO_SQLAllocHandle( SQL_HANDLE_STMT, C0, S0 );
DO_SQLBindCol( S0, 1, SQL_C_LONG, 4, 4 );
strcpy(sql_statement, /* >> 2 << */ "select MAX(keyval) from test_table");
DO_SQLExecDirect( S0, sql_statement );
DO_SQLFreeHandle( SQL_HANDLE_STMT, S0 );
```

### DO\_SQLAllocStmt

Allocates a statement handle and assigns it to a previously open connection.

#### Syntax

```
DO_SQLAllocStmt( int nConnectionIndex, int nStatementIndex );
```

#### Return Value

#### Parameters

Parameter	Description
nConnectionIndex	Index into the table of ODBC connection handles.
nStatementIndex	Index into the table of ODBC statement handles.

### Example

```
DO_SQLSetConnectOption( C0, SQL_ACCESS_MODE, 0 );
DO_SQLAllocStmt( C0, S0 );
DO_SQLSetStmtOption( S0, SQL_QUERY_TIMEOUT, 60 );
```

### DO\_SQLBindCol

Binds application buffers to a specific column of a statement. The columns are identified by number in the result set.

#### Syntax

```
DO_SQLBindCol( int StatementIndex, int ColumnNum, ODBCSQLCDataTypeEnum CDataType, long BufferLength, long pBufferLength );
```

#### Return Value

#### Parameters

Parameter	Description		
StatementIndex	Index into the table of ODBC statement handles.		
ColumnNum	Number of the result set column to bind.		
CDataType	<i>ODBCSQLCDataTypeEnum</i> C data type. Valid values are: <table border="0"><tr><td>Value</td><td>Description</td></tr></table>	Value	Description
Value	Description		



	SQL_C_BIT	Bit
	SQL_C_UTINYINT	Unsigned tiny integer
	SQL_C_STINYINT	Signed tiny integer
	SQL_C_TINYINT	Tiny integer
	SQL_C_SSHORT	Signed Short
	SQL_C_USHORT	Unsigned short
	SQL_C_SHORT	Short
	SQL_C_SLONG	Signed long
	SQL_C_ULONG	Unsigned long
	SQL_C_LONG	Long
	SQL_C_CHAR	Char
	SQL_C_BINARY	Binary
	SQL_C_FLOAT	Float
	SQL_C_DOUBLE	Double
	SQL_C_DATE	Date YYYY:MM:DD (for example: 1996:10:25)
	SQL_C_TIME	Time HH:MM:SS (for example: 17:28:01)
	SQL_C_TIMESTAMP	Timestamp YYYY:MM:DD:HH:MM:SS
BufferLength	The length of the buffer for the data that is being returned.	
PBufferLength	The length/indicator buffer to bind to the column.	

### Example

```

BEGIN_TRANSACTION();

DO_SQLAllocHandle( SQL_HANDLE_DBC, 0, C0 );
DO_SQLConnect( C0, "FHLOADDB2", "sa", "" );
DO_SQLAllocHandle( SQL_HANDLE_STMT, C0, S0 );
DO_SQLSetStmtAttr( S0, SQL_ATTR_ROW_ARRAY_SIZE, 5, SQL_IS_INTEGER ); // Changed from 5 to 0
DO_SQLSetStmtAttr( S0, SQL_ATTR_ROWS_FETCHED_PTR, 0, SQL_IS_POINTER );
DO_SQLSetStmtAttr( S0, SQL_ATTR_ROW_STATUS_PTR, 0, SQL_IS_POINTER );
DO_SQLBindCol( S0, 1, SQL_C_SLONG, 4, 0 );
DO_SQLBindCol( S0, 2, SQL_C_CHAR, 20, 0 );
DO_SQLBindParameter( S0, 1, SQL_PARAM_INPUT, SQL_C_SLONG, SQL_INTEGER, 10, 0, 4, 4 );

DO_LoadMem( S0, 1, "1", 4 );

strcpy(sql_statement, /* >> 0 << */
"SELECT KEYVAL, VARCHAR_COL FROM TEST_TABLE WHERE KEYVAL > {0}");
DO_substr(sql_statement, 1, "200" );
DO_SQLExecDirect( S0, sql_statement );

// Retrieve the data
DO_SQLFetch( 0 );

```

## Language Reference Commands

```
RR__printf( GetBindColumnData( 0, 1, 1 ) );
RR__printf( GetBindColumnData( 0, 2, 1 ) );
RR__printf( GetBindColumnData( 0, 1, 2 ) );
RR__printf( GetBindColumnData( 0, 2, 2 ) );
RR__printf( GetBindColumnData( 0, 1, 3 ) );
RR__printf( GetBindColumnData( 0, 2, 3 ) );
RR__printf( GetBindColumnData( 0, 1, 4 ) );
RR__printf( GetBindColumnData( 0, 2, 4 ) );
RR__printf( GetBindColumnData( 0, 1, 5 ) );
RR__printf( GetBindColumnData( 0, 2, 5 ) );
```

## DO\_SQLBindParameter

Used to describe a memory location between the application and the database. This memory location is used to exchange data between the application and the database.

Bind parameters are identified in a SQL statement with the question mark (?) character. Each ? character is a separate bind parameter, with the first bind parameter starting at 1.

### Syntax

```
DO_SQLBindParameter( int CommandIndex, unsigned short nParamNum,
ODBCSQLBindParameterParamTypeEnum ParamType, ODBCSQLBindParameterCDataTypeEnum CDataType,
ODBCSQLBindParameterSQLDataTypeEnum DataType, long ColumnDefinition, short Scale, SDWORD
InputString, int cbValueMax );
```

### Return Value

### Parameters

Parameter	Description								
CommandIndex	Index into the table of ODBC command handles.								
nParamNum	Bind parameter number. The first parameter is 1.								
ParamType	<p><i>ODBCSQLBindParameterParamTypeEnum</i></p> <p>Defines the direction of the parameter. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>SQL_PARAM_INPUT</td> <td>Parameter is input only.</td> </tr> <tr> <td>SQL_PARAM_INPUT_OUTPUT</td> <td>Parameter is output only.</td> </tr> <tr> <td>SQL_PARAM_OUTPUT</td> <td>Parameter is input and output.</td> </tr> </tbody> </table>	Value	Description	SQL_PARAM_INPUT	Parameter is input only.	SQL_PARAM_INPUT_OUTPUT	Parameter is output only.	SQL_PARAM_OUTPUT	Parameter is input and output.
Value	Description								
SQL_PARAM_INPUT	Parameter is input only.								
SQL_PARAM_INPUT_OUTPUT	Parameter is output only.								
SQL_PARAM_OUTPUT	Parameter is input and output.								
CDataType	<p><i>ODBCSQLBindParameterCDataTypeEnum</i></p> <p>C data type. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>SQL_C_BIT</td> <td>Bit</td> </tr> <tr> <td>SQL_C_UTINYINT</td> <td>Unsigned tiny integer</td> </tr> </tbody> </table>	Value	Description	SQL_C_BIT	Bit	SQL_C_UTINYINT	Unsigned tiny integer		
Value	Description								
SQL_C_BIT	Bit								
SQL_C_UTINYINT	Unsigned tiny integer								

	SQL_C_STINYINT	Signed tiny integer																						
	SQL_C_TINYINT	Tiny integer																						
	SQL_C_SSHORT	Signed Short																						
	SQL_C_USHORT	Unsigned short																						
	SQL_C_SHORT	Short																						
	SQL_C_SLONG	Signed long																						
	SQL_C_ULONG	Unsigned long																						
	SQL_C_LONG	Long																						
	SQL_C_CHAR	Char																						
	SQL_C_BINARY	Binary																						
	SQL_C_FLOAT	Float																						
	SQL_C_DOUBLE	Double																						
	SQL_C_NUMERIC	Numeric																						
	SQL_C_DATE	Date YYYY:MM:DD (for example: 1996:10:25)																						
	SQL_C_TIME	Time HH:MM:SS (for example: 17:28:01)																						
	SQL_C_TIMESTAMP	Timestamp YYYY:MM:DD:HH:MM:SS																						
Data Type	<p><i>ODBCSQLBindParameterSQLDataTypeEnum</i></p> <p>ODBC SQL data type. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>SQL_CHAR</td> <td>Char</td> </tr> <tr> <td>SQL_DECIMAL</td> <td>Decimal</td> </tr> <tr> <td>SQL_SMALLINT</td> <td>Small integer</td> </tr> <tr> <td>SQL_REAL</td> <td>Real</td> </tr> <tr> <td>SQL_VARCHAR</td> <td>Varchar</td> </tr> <tr> <td>SQL_TIME</td> <td>Time HH:MM:SS (for example: 17:28:01)</td> </tr> <tr> <td>SQL_LONGVARCHAR</td> <td>Long Varchar</td> </tr> <tr> <td>SQL_VARBINARY</td> <td>Var binary</td> </tr> <tr> <td>SQL_BIGINT</td> <td>Big integer</td> </tr> <tr> <td>SQL_BIT</td> <td>Bit</td> </tr> </tbody> </table>		Value	Description	SQL_CHAR	Char	SQL_DECIMAL	Decimal	SQL_SMALLINT	Small integer	SQL_REAL	Real	SQL_VARCHAR	Varchar	SQL_TIME	Time HH:MM:SS (for example: 17:28:01)	SQL_LONGVARCHAR	Long Varchar	SQL_VARBINARY	Var binary	SQL_BIGINT	Big integer	SQL_BIT	Bit
Value	Description																							
SQL_CHAR	Char																							
SQL_DECIMAL	Decimal																							
SQL_SMALLINT	Small integer																							
SQL_REAL	Real																							
SQL_VARCHAR	Varchar																							
SQL_TIME	Time HH:MM:SS (for example: 17:28:01)																							
SQL_LONGVARCHAR	Long Varchar																							
SQL_VARBINARY	Var binary																							
SQL_BIGINT	Big integer																							
SQL_BIT	Bit																							

	SQL_NUMERIC	Numeric
	SQL_INTEGER	Integer
	SQL_FLOAT	Float
	SQL_DOUBLE	Double
	SQL_BINARY	Binary
	SQL_LONGVARBINARY	Long variable binary
	SQL_TINYINT	Tiny integer
ColumnDefinition	Precision of the column. (The same as using the native ODBC call for the given C or SQL type.)	
Scale	Scale of the column. (The same as using the native ODBC call for the given C or SQL type.)	
InputString	A string that defines the input data to the bind call.	
cbValueMax	The length of the output variable being passed.	

### Example

```
DO_SQLAllocHandle( SQL_HANDLE_STMT, C0, S0 );
strcpy(sql_statement, "INSERT INTO dbo.TEST_TABLE (keyval, test_number, longvarchar_col)
VALUES (?, ?, ?)");
DO_SQLPrepare( S0, sql_statement );
DO_SQLBindParameter( S0, 1, SQL_PARAM_INPUT, SQL_C_LONG, SQL_INTEGER, 0, 0, 4, 0);
DO_SQLBindParameter( S0, 2, SQL_PARAM_INPUT, SQL_C_LONG, SQL_INTEGER, 0, 0, 4, 0);
DO_SQLBindParameter( S0, 3, SQL_PARAM_INPUT, SQL_C_CHAR, SQL_CHAR, 16, 0, 0,
SQL_DATA_AT_EXEC);
DO_LoadMem( S0, 1, "26293", 0 );
DO_LoadMem( S0, 2, "9", 0 );
DO_SQLExecute( S0 );
DO_SQLParamData( S0 );
DO_SQLPutData( S0, "AAA", -3 );
DO_SQLParamData( S0 );
DO_SQLEndTran( SQL_HANDLE_DBC, C0, SQL_COMMIT );
DO_SQLFreeHandle( SQL_HANDLE_STMT, S0 );
```

### DO\_SQLCancel

Cancels the processing of the present SQL statement.

This is rarely used within a script, although you could use it if only a subset of the rows are needed from a Select command.

#### Syntax

```
DO_SQLCancel( int StatementIndex );
```

#### Return Value

None

### Parameters

Parameter	Description
StatementIndex	Index into the table of ODBC statement handles.

### Example

```
DO_SQLCancel( S0 );
```

## DO\_SQLCloseCursor

Closes a cursor associated with a handle and discards the results.

This cleanup function interacts minimally with do\_odbc.

### Syntax

```
DO_SQLCloseCursor( int StatementIndex )
```

### Return Value

### Parameters

Parameter	Description
StatementIndex	Index into the table of ODBC statement handles.

### Example

```
DO_SQLFreeStmt( S0, SQL_DROP );
DO_SQLFreeStmt( S1, SQL_CLOSE );
DO_SQLSetStmtAttr( S1, SQL_ATTR_NOSCAN, SQL_NOSCAN_OFF, );
strcpy(sql_statement, /* >> 5 << */ "SELECT keyval, test_number, test_type FROM
dbo.test.table");
DO_SQLExecDirect( S1, sql_statement );
DO_SQLCloseCursor( S1);
DO_SQLFreeHandle(S1);
```

## DO\_SQLColAttribute

Returns descriptor information for a column in a result set.

In ODBC 3.x, this function replaces `SQLColAttributes`. `SQLColAttribute` returns descriptor information as a character string, a 32-bit descriptor-dependent value, or an integer value.

The `SQLColAttribute` replaces `SQLColAttributes` because it interacts with Descriptor information that was not present in prior versions of ODBC.

### Syntax

```
DO_SQLColAttribute( int StatementIndex, int ColumnNum, SQLUSMALLINT ColumnAttribute,
SQLSMALLINT BufferLen )
```

### Return Value

### Parameters

Parameter	Description
-----------	-------------

StatementIndex	Index into the table of ODBC statement handles.
ColumnNum	The column for the information.
ColumnAttribute	The attribute to be retrieved.
BufferLen	Amount of space for the information to be retrieved.

**Example**

```
DO_SQLAllocHandle( SQL_HANDLE_STMT, C0, S0);
DO_SQLBindParameter(S0, 1, SQL_PARAM_INPUT,
    SQL_C_ULONG, SQL_INTEGER,
    10, 0, "19", 4, 4 );
strcpy(sql_statement, /* >> 1 << */ "select
varchar_col, char_col, timestamp_col
from test_table where keyval < ?");
DO_SQLExecDirect( S0, sql_statement );
DO_SQLBindCol( S0, 1, SQL_C_CHAR, 50, 196658 );
DO_SQLBindCol( S0, 2, SQL_C_CHAR, 50, 50 );
DO_SQLBindCol( S0, 3, SQL_C_TIMESTAMP, 50, 2012741682 );
DO_SQLColAttribute( S0, 1, SQL_DESC_BASE_COLUMN_NAME, 50);
DO_SQLFreeHandle( SQL_HANDLE_STMT, S0 );
```

**DO\_SQLColumns**

Retrieves the column information of the selected tables.

DO\_SQLColumns is used to retrieve information from a series of columns within a table. Use DO\_SQLNumResultsCols to sort through the result set.

**Syntax**

```
DO_SQLColumns( int StatementIndex, UCHAR* QualifierName, UCHAR* TableOwner, UCHAR*
TableName, UCHAR* ColumnName );
```

**Return Value**

The following information is retrieved for each matching column:

Column Name	Data Type	Comments
TABLE_QUALIFIER	Varchar(128)	Table qualifier identifier; NULL if not applicable to the data source.
TABLE_OWNER	Varchar(128)	Table owner identifier; NULL if not applicable to the data source.
TABLE_NAME	Varchar(128)	Table identifier.
COLUMN_NAME	Varchar(128)	Column identifier.
DATA_TYPE	Smallint	ODBC SQL data type.
TYPE_NAME	Varchar(128)	Data source-dependent data type name; for example, CHAR, VARCHAR, MONEY, LONG VARBINARY, or CHAR ( ) for bit data.
PRECISION	Integer	Precision of the column on the data source.

LENGTH	Integer	Transfer size of the data. The length in bytes of data transferred on an SQLGetData or SQLFetch operation if SQL_C_DEFAULT is specified. For numeric data, this size may be different than the size of the data stored on the data source. This value is the same as the PRECISION column for character or binary data.
SCALE	Smallint	Scale of the column on the data source.
RADIX	Smallint	Either 10 or 2. If it is 10, the values in PRECISION and SCALE give the number of decimal digits allowed for the column. If it is 2, the values in PRECISION and SCALE give the number of bits allowed in the column.
NULLABLE	Smallint	SQL_NO_NULLS if the column does not accept NULL values.
REMARKS	Varchar(254)	A description of the column.

### Parameters

Parameter	Description
StatementIndex	Index into the table of ODBC statement handles.
QualifierName	Table qualifier identifier (accepts search patterns).
TableOwner	Name of the table owner (accepts search patterns).
TableName	Table name (accepts search patterns).
ColumnName	Column name to retrieve (accepts search patterns).

### Example

```
DO_SQLAllocStmt( C0, S1 );
DO_SQLColumns( S1, "", "", "qctest", "" );
```

### DO\_SQLConnect

Performs a connection to the database.

The authorization string, if required by the database, must be present, since many drivers prompt the user for a password at runtime if the password is not present. This presents a problem when playing back multiple virtual users, as it is impractical for the test operator to respond to each prompt individually.

The call is for completeness only. QALoad translates a SQLConnect command into a SQLDriverConnect command. This facilitates the automatic detection of the Authorization string (password).

### Syntax

```
DO_SQLConnect( int ConnectionIndex, UCHAR* DSN, UCHAR* UDI, UCHAR* AuthStr );
```

### Return Value

Parameters

Parameter	Description
ConnectionIndex	Index into the table of connections.
DSN	Data source name.
UID	User identifier.
AuthStr	Authorization string (password).

Example

```
DO_SQLAllocConnect( C0 );
DO_SQLConnect( C0, "fhloadb2", "sa", "" );
```

DO\_SQLCopyDesc

Copies the fields of the source descriptor handle to the target descriptor handle.

If the values of the SourceDescHandle and TargetDescHandle parameters are associated with the same driver, the driver copies all descriptor fields. This is true even if the drivers are on different connections or environments.

If the values of the parameters are not associated with the same driver, only ODBC-defined fields are copied.

At this time QALoad does not store descriptor information. QALoad relies on ODBC to handle the calls and the descriptor data for the application.

Syntax

```
DO_SQLCopyDesc( int SourceDescriptorHandleIndex, int TargetDescriptorHandle );
```

Return Value

Parameters

Parameter	Description
SourceDescriptorHandleIndex	The descriptor to copy over.
TargetDescriptorHandle	The descriptor receiving the copied information.

Example

```
DO_SQLAllocHandle( SQL_HANDLE_DESC, C0, D1 );
DO_SQLAllocHandle( SQL_HANDLE_DESC, C0, D2 );
DO_SQLSetDescField( D1, 0, SQL_DESC_COUNT, 2, -6 );
DO_SQLSetDescRec( D1, 1, 4, 0, 4, 10, 0, 42919801, 1242388, 1242384 );
DO_SQLSetDescRec( D1, 2, 4, 0, 4, 10, 0, 42922201, 1242388, 1242384 );
DO_SQLCopyDesc( D1, D2 );
DO_SQLGetDescRec( D2, 1, 4 );
DO_SQLFreeHandle( SQL_HANDLE_DESC, D2 );
DO_SQLFreeHandle( SQL_HANDLE_DESC, D1 );
```



## DO\_SQLDescribeCol

Returns descriptor information to the statement handle.

The information is returned as a set of pointers describing the column name, column precision, column scale, and SQL type of the column. This information can be used as metadata for generic data handling.

### Syntax

```
DO_SQLDescribeCol( int StatementIndex, int ColumnNumber, int BufferLength )
```

### Return Value

### Parameters

Parameter	Description
StatementIndex	The statement handle for the function call.
ColumnNumber	The number of the column in the table that SQLdescribeCol is retrieving information about. Column numbers start at 1 and advance from there.
BufferLength	The length of the buffer for the column name in bytes.

### Example

```
DO_SQLFreeStmt( S0, SQL_CLOSE );
DO_SQLSetStmtAttr( S0, SQL_ATTR_NOSCAN, SQL_NOSCAN_OFF, );
strcpy(sql_statement, /* >> 3 << */ "SELECT * FROM dbo.test.table");
DO_SQLExecDirect( S0, sql_statement );
pcol = DO_SQLNumResultCols( S0 );
DO_SQLDescribeCol( S0, 1, 129);
DO_SQLColAttribute( S0, 1, SQL_DESC_AUTO_UNIQUE_VALUE, 0);
DO_SQLColAttribute( S0, 1, SQL_DESC_FIXED_PREC_SCALE, 0);
DO_SQLColAttribute( S0, 1, SQL_DESC_UPDATABLE, 0);
DO_SQLDescribeCol( S0, 2, 129);
DO_SQLColAttribute( S0, 2, SQL_DESC_AUTO_UNIQUE_VALUE, 0);
DO_SQLColAttribute( S0, 2, SQL_DESC_FIXED_PREC_SCALE, 0);
DO_SQLColAttribute( S0, 2, SQL_DESC_UPDATABLE, 0);
DO_SQLDescribeCol( S0, 3, 129);
DO_SQLColAttribute( S0, 3, SQL_DESC_AUTO_UNIQUE_VALUE, 0);
DO_SQLColAttribute( S0, 3, SQL_DESC_FIXED_PREC_SCALE, 0);
DO_SQLColAttribute( S0, 3, SQL_DESC_UPDATABLE, 0);
```

## DO\_SQLDisconnect

Closes the connection from the application to the database server.

### Syntax

```
DO_SQLDisconnect( int ConnectionIndex );
```

### Return Value

### Parameters

Parameter	Description
ConnectionIndex	Index into the table of connections.

## Language Reference Commands

### Example

```
DO_SQLDisconnect( C0 );
```

### DO\_SQLDriverConnect

Connects the application to the database.

Normally, the format of the connection string can vary between databases and ODBC drivers, but generally includes, at a minimum, the dataset name (DSN), user ID (UID), and password (PWD). If a password is required for the connection, it is important to include it in DO\_SQLDriverConnect so the ODBC driver does not prompt the user at runtime for the connection string.

### Syntax

```
DO_SQLDriverConnect( int ConnectionIndex, UCHAR* ConnectionString );
```

### Return Value

### Parameters

Parameter	Description
ConnectionIndex	Index into the table of connections.
ConnectionString	Complete ODBC connection string (see description).

### Example

```
DO_SQLDriverConnect( C0, "DSN=Dan32;UID=dba;PWD=sql" );
```

### DO\_SQLEndTran

Provides the mechanism for all open transactions or all open transactions on a particular connection to be resolved.

### Syntax

```
DO_SQLEndTran( ODBCSQLTransactionHandleTypeEnum nHandleType, long nHandleIndex, ODBCSQLTransactTypeEnum nOperation );
```

### Return Value

### Parameters

Parameter	Description						
nHandleType	<i>ODBCSQLTransactionHandleTypeEnum</i> The type of Handle on which the transaction is being committed or rolled back. Valid values are: <table><thead><tr><th>Value</th><th>Description</th></tr></thead><tbody><tr><td>SQL_HANDLE_ENV</td><td>Environment handle</td></tr><tr><td>SQL_HANDLE_DBC</td><td>Connection handle</td></tr></tbody></table>	Value	Description	SQL_HANDLE_ENV	Environment handle	SQL_HANDLE_DBC	Connection handle
Value	Description						
SQL_HANDLE_ENV	Environment handle						
SQL_HANDLE_DBC	Connection handle						

nHandleIndex	Index into the table of statement or connection handles, or -666 which is used as a marker for the Environment handle.						
nOperation	<p><i>ODBCSQLTransactTypeEnum</i></p> <p>SQL transaction type option. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>SQL_COMMIT</td> <td>Commit transaction</td> </tr> <tr> <td>SQL_ROLLBACK</td> <td>Rollback transaction</td> </tr> </tbody> </table>	Value	Description	SQL_COMMIT	Commit transaction	SQL_ROLLBACK	Rollback transaction
Value	Description						
SQL_COMMIT	Commit transaction						
SQL_ROLLBACK	Rollback transaction						

### Example

The following example commits all of the transactions open on connection index 1:

```
DO_SQLExecDirect( S3, sql_statement );
DO_SQLEndTran( SQL_HANDLE_DBC, C1, SQL_COMMIT );
```

In order to resolve all transactions, the call to `DO_SQLEndTran` has the value -666 as the handle index. This is a marker for the Environment handle.

```
DO_SQLEndTran( SQL_HANDLE_ENV, -666, SQL_COMMIT );
```

### DO\_SQLExecDirect

Prepares and executes a SQL statement.

#### Syntax

```
DO_SQLExecDirect( int StatementIndex, UCHAR* SQLStatement );
```

#### Return Value

#### Parameters

Parameter	Description
StatementIndex	Index into the table of statement handles.
SQLStatement	SQL statement to be executed.

### Example

```
DO_SQLExecDirect( S0, "Select * from emp_tutorial" );
```

### DO\_SQLExecute

Executes a prepared command using the current values of the parameter marker variables if any parameter markers exist in the command.

#### Syntax

```
DO_SQLExecute( int StatementIndex );
```

Return Value

Parameters

Parameter	Description
StatementIndex	Index into the table of statement handles.

Example

```
DO_SQLPrepare( S0, sql_statement );
DO_LoadMem( S0, 1, "17", 4 ); \
DO_LoadMem( S0, 2, "1234", 4 );
DO_LoadMem( S0, 3, "1235", 4 );
DO_LoadMem( S0, 4, "1236", 4 );
DO_LoadMem( S0, 5, "1237", 4 );
DO_SQLExecute( S0 );
```

DO\_SQLFetch

Retrieves a single row of data.

Syntax

```
DO_SQLFetch( int StatementIndex )
```

Return Value

Parameters

Parameter	Description
StatementIndex	The index of the statement handle.

Example

```
DO_SQLAllocHandle( SQL_HANDLE_STMT, C0, S0 );
strcpy(sql_statement, /* >> 1 << */ "SELECT MAX(keyval) FROM TESTDB.TEST_TABLE");
DO_SQLExecDirect( S0, sql_statement );
while (DO_SQLFetch( S0 ) != SQL_NO_DATA_FOUND )
{
DO_SQLGetData( S0, 1, SQL_C_LONG, 4 );
strcpy(pReturnValue, GetFetchedData());
}
DO_SQLFreeHandle( SQL_HANDLE_STMT, S0 );
```

DO\_SQLFreeConnect

Performs the cleanup of connection handles for ODBC within a QALoad script.

The handle cleanup that was being performed in DO\_SQLDisconnect is now being performed in DO\_SQLFreeConnect or in DO\_SQLFreeHandle.

Syntax

```
DO_SQLFreeConnect( int ConnectionIndex );
```

Return Value

Parameters

Parameter	Description
ConnectionIndex	Points to a structure that ODBC uses to track different connection settings, statements within the connection, and descriptors allocated within the connection.

Example

```
DO_SQLAllocConnect( C0 );
DO_SQLConnect( C0, "fhloadb2", "sa", "" );
DO_SQLDisconnect( C0 );
DO_SQLFreeConnect( C0 );
```

DO\_SQLFreeHandle

In ODBC, DO\_SQLFreeHandle handles statement and descriptor cleanup.

Each occurrence of DO\_SQLFreeHandle must have a corresponding DO\_SQLAllocHandle, either within the transaction loop or outside of the transaction loop.

DO\_SQLFreeHandle replaces DO\_SQLFreeStmt. Like DO\_SQLAllocHandle, DO\_SQLFreeHandle takes different parameters than its predecessor. DO\_SQLFreeHandle is compatible with ODBC 3.x.

Syntax

```
DO_SQLFreeHandle( ODBCSQLHandleTypeEnum HandleType, int HandleIndex )
```

Return Value

Parameters

Parameter	Description										
HandleType	<p><i>ODBCSQLHandleTypeEnum</i></p> <p>The type of handle to be allocated. Each handle takes different arguments. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>SQL_HANDLE_ENV</td> <td>Environment handle</td> </tr> <tr> <td>SQL_HANDLE_DBC</td> <td>Connection handle</td> </tr> <tr> <td>SQL_HANDLE_STMT</td> <td>Statement handle</td> </tr> <tr> <td>SQL_HANDLE_DESC</td> <td>Descriptor handle</td> </tr> </tbody> </table>	Value	Description	SQL_HANDLE_ENV	Environment handle	SQL_HANDLE_DBC	Connection handle	SQL_HANDLE_STMT	Statement handle	SQL_HANDLE_DESC	Descriptor handle
Value	Description										
SQL_HANDLE_ENV	Environment handle										
SQL_HANDLE_DBC	Connection handle										
SQL_HANDLE_STMT	Statement handle										
SQL_HANDLE_DESC	Descriptor handle										
HandleIndex	The address of the structure that ODBC should release from memory.										

Example

```
DO_SQLAllocHandle( SQL_HANDLE_STMT, C0, S0 );
DO_SQLBindCol( S0, 1, SQL_C_LONG, 4, 4 );
```

## Language Reference Commands

```
strcpy(sql_statement, /* >> 2 << */ "select MAX(keyval) from test_table");  
DO_SQLExecDirect( S0, sql_statement );  
DO_SQLFreeHandle( SQL_HANDLE_STMT, S0 );
```

### DO\_SQLFreeStmt

Stops processing associated with a specific command\_index and:

- ! Closes any open cursors associated with the command\_index.
- ! Discards pending results.
- ! Frees all resources associated with command\_index.

Consult your ODBC reference manual for details regarding the option parameter.

#### Syntax

```
DO_SQLFreeStmt( int StatementIndex, ODBCSQLFreeStmtOptionEnum Option );
```

#### Return Value

#### Parameters

Parameter	Description										
StatementIndex	Index into the table of statement handles.										
Option	<i>ODBCSQLFreeStmtOptionEnum</i> SQLFreeStmt option. Valid values are: <table border="1"><thead><tr><th>Value</th><th>Description</th></tr></thead><tbody><tr><td>SQL_CLOSE</td><td>Close the statement handle</td></tr><tr><td>SQL_DROP</td><td>Drop the statement handle</td></tr><tr><td>SQL_UNBIND</td><td>Unbind the statement binds</td></tr><tr><td>SQL_RESET_PARAMS</td><td>Reset the statement parameters</td></tr></tbody></table>	Value	Description	SQL_CLOSE	Close the statement handle	SQL_DROP	Drop the statement handle	SQL_UNBIND	Unbind the statement binds	SQL_RESET_PARAMS	Reset the statement parameters
Value	Description										
SQL_CLOSE	Close the statement handle										
SQL_DROP	Drop the statement handle										
SQL_UNBIND	Unbind the statement binds										
SQL_RESET_PARAMS	Reset the statement parameters										

#### Example

```
DO_SQLFreeStmt( S0, SQL_DROP );
```

### DO\_SQLGetCursorName

Use on an open ODBC statement to return a char \* containing the cursor active on a particular statement.

This cursor can then be used in the execution of another query on another statement. Be aware that the pReturnValue must be freed by the script or a memory leak results.

#### Syntax

```
DO_SQLGetCursorName ( int StatementIndex, short nBufferLength);
```

#### Return Value

## Parameters

Parameter	Description
StatementIndex	Index into the table of statement handles.
nBufferLength	The length of the buffer in bytes.

## Example

In the following example, the pReturnValue is being placed in the sCursorName string immediately before the pReturnValue is freed.

```
char * DO_SQLGetCursor( <connection index>, <buffer length in bytes> );
```

An example on its correct use is as follows:

```
char sCursorName[19];
char *pReturnValue;
...
...
pReturnValue = DO_SQLGetCursorName( S1, 19 );
sprintf( sCursorName, "%s", pReturnValue );
free(pReturnValue);
strcpy(sql_statement, /* >> 3 << */ "UPDATE TESTDB.Test_Table set test_number = test_number
where current of ");
sprintf( sql_statement, "%s%s", sql_statement, sCursorName );
DO_SQLExecDirect( S2, sql_statement );
```

## DO\_SQLGetData

Retrieves data for a single column in the form of a string.

Call DO\_SQLGetData after one or more rows have been retrieved from the result set by DO\_SQLFetch. DO\_SQLGetData allows large pieces of data to be returned by retrieving the data in parts if the variable length data is too large for a single call.

### Syntax

```
DO_SQLGetData( int nStmtIndex, int nColNum, int nCType, long nBufLen )
```

### Return Value

DO\_SQLGetData can return the following values in the length/indicator buffer:

- ! Length of the data available to return
- ! SQL\_NO\_TOTAL
- ! SQL\_NULL\_DATA

## Parameters

Parameter	Description
nStmtIndex	The index of the statement handle.
nColNum	The column number being returned.
nCType	The datatype.
nBufLen	The length of the buffer the data is returned in.

## Language Reference Commands

### Example

```
strcpy(sql_statement, /* >> 1 << */ "SELECT MAX(keyval) FROM TESTDB.TEST_TABLE");
DO_SQLExecDirect( S0, sql_statement );
while (DO_SQLFetch( S0 ) != SQL_NO_DATA_FOUND )
{
pReturnValue = DO_SQLGetData( S0, 1, SQL_C_LONG, 4 );
free(pReturnValue);
}
```

### DO\_SQLGetDescField

Returns the value of a field of a descriptor record.

Use DO\_SQLGetDescField to return the value of a descriptor record field. DO\_SQLGetDescField can return the value of any field in any descriptor type. Make repeated calls to DO\_SQLGetDescField to return settings from multiple fields of one or multiple descriptors in arbitrary order. DO\_SQLGetDescField can also return driver-defined descriptor fields.

### Syntax

```
DO_SQLGetDescField( int DescriptorIndex, short RecordNumber, short FieldID, long
BufferLength, )
```

### Return Value

### Parameters

Parameter	Description
DescriptorIndex	Points to the descriptor structure in memory.
RecordNumber	The record number of the descriptor structure to be retrieved.
FieldID	The field of the descriptor record to be retrieved.
BufferLen	The length of a character string or SQL_NTS being returned. SQL_LEN_BINARY_ATTR ( macro) results if binary data is returned. SQL_IS_POINTER is Value, not binary or string data.

### Example

```
DO_SQLAllocHandle( SQL_HANDLE_DESC, C0, D0 );
strcpy(sql_statement, /* >> 1 << */ "UPDATE test_table SET integer_col = ? WHERE keyval =
?");
DO_SQLPrepare( S0, sql_statement );
DO_SQLSetDescRec( D0, 1, 4 );
DO_SQLSetDescRec( D0, 2, 4 );
DO_SQLGetDescField( D0, 1, SQL_DESC_CONCISE_TYPE, 261312 );
DO_SQLGetDescField( D0, 2, SQL_DESC_CONCISE_TYPE, 261312
```

### DO\_SQLGetDescRec

Returns the settings or values from fields of a descriptor record set by DO\_SQLSetDescRec.

These fields include name, data type, and column or parameter data storage. Does not retrieve values for header fields.



To prevent the return of a setting, set the corresponding parameter to a null pointer.

### Syntax

```
DO_SQLGetDescRec( int nDescIndex, SQLSMALLINT nRecordNumber, SQLSMALLINT nBufLen );
```

### Return Value

For a column or parameter, DO\_SQLGetDescRec can retrieve the value of the following fields:

SQL\_DESC\_NAME

SQL\_DESC\_TYPE

SQL\_DESC\_OCTET\_LENGTH

SQL\_DESC\_DATETIME\_INTERVAL\_CODE (types SQL\_DATETIME and SQL\_INTERVAL)

SQL\_DESC\_PRECISION

SQL\_DESC\_SCALE

SQL\_DESC\_NULLABLE

### Parameters

Parameter	Description
nDescIndex	Points to the location of the descriptor structure in memory.
nRecordNumber	The descriptor record with fields to be set.
nBufLen	Descriptor record buffer length.

### Example

```
DO_SQLSetDescRec( D1, 2, 4, 0, 4, 10, 0, 42922201, 1242388, 1242384 );
DO_SQLCopyDesc( D1, D2 );
DO_SQLGetDescRec( D2, 1, 4 );
DO_SQLFreeHandle( SQL_HANDLE_DESC, D2 );
DO_SQLFreeHandle( SQL_HANDLE_DESC, D1 );
```

## DO\_SQLGetEnvAttr

Gets a characteristic of an environment.

### Syntax

```
DO_SQLGetEnvAttr( SQLINTEGER nAttribute, SQLPOINTER strAttrValue, SQLINTEGER nBufferLength,
SQLINTEGER* nStringLength );
```

### Return Value

### Parameters

Parameter	Description
nAttribute	An environment attribute such as SQL_ATTR_CONNECTTYPE.
StrAttrValue	Current attribute value.
nBufferLength	Maximum size of attribute value.
nStringLength	Total number of bytes returned.

### Example

```
int rc = DO_SQLGetEnvAttr( SQL_ATTR_CONNECTTYPE, &connecttype, 0, NULL );
```

## DO\_SQLGetTypeInfo

Returns information about data types supported by the data source.

### Syntax

```
DO_SQLGetTypeInfo( int StatementIndex, ODBCSQLGetTypeSQLTypeEnum SQLType );
```

### Return Value

Data is returned as a result set with the following columns:

Column name	Data type
TYPE_NAME	Varchar(128)
DATA_TYPE	Smallint
PRECISION	Integer
LITERAL_PREFIX	Varchar(128)
LITERAL_SUFFIX	Varchar(128)
CREATE_PARAMS	Varchar(128)
NULLABLE	Smallint
CASE_SENSITIVE	Smallint
SEARCHABLE	Smallint
MONEY	Smallint
AUTO_INCREMENT	Smallint
LOCAL_TYPE_NAME	Varchar(128)

For details on the commands above, consult an ODBC reference manual.

### Parameters

Parameter	Description												
StatementIndex	Index into the table of statement handles.												
SQLType	<p><i>ODBCSQLGetTypeSQLTypeEnum</i>                      ODBC SQL data type. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>SQL_CHAR</td> <td>Char</td> </tr> <tr> <td>SQL_DECIMAL</td> <td>Decimal</td> </tr> <tr> <td>SQL_SMALLINT</td> <td>Small integer</td> </tr> <tr> <td>SQL_REAL</td> <td>Real</td> </tr> <tr> <td>SQL_VARCHAR</td> <td>Varchar</td> </tr> </tbody> </table>	Value	Description	SQL_CHAR	Char	SQL_DECIMAL	Decimal	SQL_SMALLINT	Small integer	SQL_REAL	Real	SQL_VARCHAR	Varchar
Value	Description												
SQL_CHAR	Char												
SQL_DECIMAL	Decimal												
SQL_SMALLINT	Small integer												
SQL_REAL	Real												
SQL_VARCHAR	Varchar												

SQL_TIME	Time HH:MM:SS (for example: 17:28:01)
SQL_LONGVARCHAR	Long Varchar
SQL_VARBINARY	Var binary
SQL_BIGINT	Big integer
SQL_BIT	Bit
SQL_NUMERIC	Numeric
SQL_INTEGER	Integer
SQL_FLOAT	Float
SQL_DOUBLE	Double
SQL_BINARY	Binary
SQL_LONGVARBINARY	Long variable binary
SQL_TINYINT	Tiny integer
SQL_ALL_TYPES	All SQL data types.

### Example

```
DO_SQLAllocStmt( C0, S0 );
DO_SQLGetTypeInfo( S0, SQL_ALL_TYPES );
DO_SQLSetStmtOption( S0, SQL_ROWSET_SIZE, 16 );
DO_checkpoint( 9, 1 );
DO_SQLFreeStmt( S0, SQL_DROP );
```

### DO\_SQLNumResultCols

Determines the number of columns being returned in a result set.

This function returns an integer indicating the number of columns in the result set. Knowing the number of columns in the result set allows the application to use `SQLDescribeCol` and `SQLColAttributes`.

#### Syntax

```
DO_SQLNumResultCols( int StatementIndex );
```

#### Return Value

#### Parameters

Parameter	Description
StatementIndex	Index into the table of statement handles.

### Example

```
int pcol = DO_SQLNumResultCols( S1 );
```

## DO\_SQLParamData

Used in conjunction with DO\_SQLPutData to supply parameter data at statement execution time.

### Syntax

```
int DO_SQLParamData( int nStatementIndex );
```

### Parameters

Parameter	Description
nStatementIndex	Index into the table of DB2 statement handles.

### Example

```
DO_SQLAllocHandle( SQL_HANDLE_STMT, C0, S0 );
strcpy(sql_statement, "INSERT INTO dbo.TEST_TABLE (keyval, test_number, longvarchar_col)
VALUES (?, ?, ?)");
DO_SQLPrepare( S0, sql_statement );
DO_SQLBindParameter( S0, 1, SQL_PARAM_INPUT, SQL_C_LONG, SQL_INTEGER, 0, 0, 4, 0);
DO_SQLBindParameter( S0, 2, SQL_PARAM_INPUT, SQL_C_LONG, SQL_INTEGER, 0, 0, 4, 0);
DO_SQLBindParameter( S0, 3, SQL_PARAM_INPUT, SQL_C_CHAR, SQL_CHAR, 16, 0, 0,
SQL_DATA_AT_EXEC);
DO_LoadMem( S0, 1, "26293", 0 );
DO_LoadMem( S0, 2, "9", 0 );
DO_SQLExecute( S0 );
DO_SQLParamData( S0 );
DO_SQLPutData( S0, "AAA", -3 );
DO_SQLParamData( S0 );
DO_SQLEndTran( SQL_HANDLE_DBC, C0, SQL_COMMIT );
DO_SQLFreeHandle( SQL_HANDLE_STMT, S0 );
```

## DO\_SQLPrepare

Prepares a SQL statement and associates the results with the command\_index. The command is not executed until the DO\_SQLExecute command is called.

### Syntax

```
DO_SQLPrepare( int StatementIndex, UCHAR* SQLString );
```

### Return Value

### Parameters

Parameter	Description
StatementIndex	Index into the table of statement handles.
SQLString	Text of the SQL statement to execute.

### Example

```
char *sql_statement = "SELECT name from emp_tut";
DO_SQLPrepare( S1, sql_statement );
DO_SQLExecute ( S1 );
```

## DO\_SQLPutData

Use to place data into the database at run time.

You can also use this method to place data that is too large for a single bind. This method allows multiple calls to SQLPutData().

### Syntax

```
DO_SQLPutData( int nStatementIndex, SQLPOINTER sData, long nIndLen);
```

### Return Value

### Parameters

Parameter	Description
nStatementIndex	Index to the table of statement handles.
sData	The actual data in string form.
nIndLen	The length of the data.

### Example

```
DO_SQLAllocHandle( SQL_HANDLE_STMT, C0, S0 );
strcpy(sql_statement, "INSERT INTO dbo.TEST_TABLE (keyval, test_number, longvarchar_col)
VALUES (?, ?, ?)");
DO_SQLPrepare( S0, sql_statement );
DO_SQLBindParameter( S0, 1, SQL_PARAM_INPUT, SQL_C_LONG, SQL_INTEGER, 0, 0, 4, 0);
DO_SQLBindParameter( S0, 2, SQL_PARAM_INPUT, SQL_C_LONG, SQL_INTEGER, 0, 0, 4, 0);
DO_SQLBindParameter( S0, 3, SQL_PARAM_INPUT, SQL_C_CHAR, SQL_CHAR, 16, 0, 0,
SQL_DATA_AT_EXEC);
DO_LoadMem( S0, 1, "26293", 0 );
DO_LoadMem( S0, 2, "9", 0 );
DO_SQLExecute( S0 );
DO_SQLParamData( S0 );
DO_SQLPutData( S0, "AAA", -3 );
DO_SQLParamData( S0 );
DO_SQLEndTran( SQL_HANDLE_DBC, C0, SQL_COMMIT );
DO_SQLFreeHandle( SQL_HANDLE_STMT, S0 );
```

## DO\_SQLRetrieveParam Value

Retrieves a value of a SQL\_PARAM\_INPUT\_OUTPUT or SQL\_PARAM\_OUTPUT parameter, following the execution of the corresponding SQL statement.

### Syntax

```
DO_SQLRetrieveParamValue( int nStmtIndex, short nParamNumber );
```

### Return Value

### Parameters

Parameter	Description
nStmtIndex	Index into the table of ODBC statement handles.

nParamNumber	Index of the parameter.
--------------	-------------------------

### Example

```
char* sRow1 = NULL;
char* sRow2 = NULL;
char* sRow3 = NULL;
char* sRow4 = NULL;
DO_SQLBindParameter( S0, 1, SQL_PARAM_INPUT, SQL_C_ULONG, SQL_INTEGER, 0, 0, 4, 4 );
DO_SQLBindParameter( S0, 2, SQL_PARAM_OUTPUT, SQL_C_ULONG, SQL_INTEGER, 0, 0, 4 );
DO_SQLBindParameter( S0, 3, SQL_PARAM_OUTPUT, SQL_C_ULONG, SQL_INTEGER, 0, 0, 4, 4 );
DO_SQLBindParameter( S0, 4, SQL_PARAM_OUTPUT, SQL_C_ULONG, SQL_INTEGER, 0, 0, 4, 4 );
DO_SQLBindParameter( S0, 5, SQL_PARAM_OUTPUT, SQL_C_ULONG, SQL_INTEGER, 0, 0, 4, 4 );
strcpy( sql_statement, "{call setup_rows (?,?,?,?) }" );
DO_SQLPrepare( S0, sql_statement );
DO_LoadMem( S0, 1, "17", 4 );
DO_LoadMem( S0, 2, "1234", 4 );
DO_LoadMem( S0, 3, "1235", 4 );
DO_LoadMem( S0, 4, "1236", 4 );
DO_LoadMem( S0, 5, "1237", 4 );
DO_SQLExecute( s0 );
sRow1 = DO_SQLRetrieveParamValue( S0, 2 );
sRow2 = DO_SQLRetrieveParamValue( S0, 3 );
sRow3 = DO_SQLRetrieveParamValue( S0, 4 );
sRow4 = DO_SQLRetrieveParamValue( S0, 5 );
```

### DO\_SQLRowCount

Returns an integer indicating the number of rows affected by the last SQL statement associated with the specified command\_index.

For inserts, updates, and deletes, the SQLRowCount value is available immediately after the command is executed. For Select commands, the value of this function depends on the capabilities of the specific ODBC driver used.

#### Syntax

```
DO_SQLRowCount( int nStatementIndex );
```

#### Return Value

#### Parameters

Parameter	Description
nStatementIndex	Index into the table of statement handles.

### Example

```
DO_SQLExecDirect( S1, sql_statement );
int pcrow = DO_SQLRowCount( S1 );
DO_SQLFreeStmt( S1, SQL_CLOSE );
```

### DO\_SQLSetConnectAttr

Sets a characteristic of the connection.

Connection attributes are characteristics of the connection. They can be set before or after connecting. Connection attributes become part of the connect handle structure.

### Syntax

```
DO_SQLSetConnectAttr( int nConnectionIndex, long nAttribute, void* nAttrValue, long nStrLength );
```

### Return Value

### Parameters

Parameter	Description
nConnectionIndex	Points to a structure that ODBC uses to track different connection settings, statements within the connection, and descriptors allocated within the connection.
nAttribute	For example: SQL_ATTR_AUTOCOMMIT is an attribute with set values SQL_TRUE or SQL_FALSE. Other connection attributes have different values. Note that QALoad does not allow SQL_ATTR_ENABLE_ASYNC to be true for ODBC. No asynchronous transactions will be handled.
nAttrValue	The value set for the attribute.
nStrLength	Can be a length pointer, or is ignored by ODBC.

### Example

```
DO_SQLAllocConnect( C0 );
DO_SQLConnect( C0, "fhloadb2", "sa", "" );
DO_SQLAllocHandle( SQL_HANDLE_DBC, 0, C1 );
DO_SQLSetConnectAttr( C1, SQL_ATTR_AUTOCOMMIT, "SQL_AUTOCOMMIT_OFF", SQL_NTS );
```

### DO\_SQLSetConnectOption

Sets options on the connection handle.

The following is a list of value option constants and the meanings of their respective value parameters.

Parameter	Value Type	Value Description
SQL_ACCESS_MODE	integer	Determines type of access this program uses.
SQL_AUTOCOMMIT	integer	0 = Autocommit off 1 = Autocommit on
SQL_LOGIN_TIMEOUT	integer	Number of seconds to wait for a login request to complete before returning to the application. The default is 15.
SQL_OPT_TRACE	integer	Integer value telling the Driver Manager whether or not to perform tracing. 0 = Tracing off (Default) 1 = Tracing on

## Language Reference Commands

SQL_OPT_TRACEFILE	string	Null-terminated character string containing the name of the trace file. If tracing is enabled, the Driver Manager writes to this file each time the application calls a function. If no trace file name is specified, the Driver Manager writes to SQL.LOG.
SQL_TRANSLATE_DLL	string	Null-terminated character string containing the name of a DLL containing the functions SQLClientToDataSource and SQLDataSourceToClient the driver loads and uses to perform tasks such as character set translation. This option may only be specified if the driver has connected to the data source.
SQL_TRANSLATE_OPTION	integer	32-bit flag value that is passed to the translate DLL. This option may only be specified if the driver has connected to the data source.
SQL_TXN_ISOLATION	integer	32-bit bitmask that sets the transaction isolation level for the current connection index. Refer to ODBC documentation for details on setting this parameter.

### Syntax

```
DO_SQLSetConnectOption( int ConnectionIndex, ODBCSQLSetConnectOptionEnum Option, UDWORD Value );
```

### Return Value

### Parameters

Parameter	Description								
ConnectionIndex	Index into a table of ODBC connection handles.								
Option	<p><i>ODBCSQLSetConnectOptionEnum</i></p> <p>One of the valid option constants. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>SQL_ACCESS_MODE</td> <td>Determines type of access this program uses</td> </tr> <tr> <td>SQL_AUTOCOMMIT</td> <td>0 = Autocommit off, 1 = Autocommit on</td> </tr> <tr> <td>SQL_LOGIN_TIMEOUT</td> <td>Number of seconds to wait for a login request to complete before returning to the application.</td> </tr> </tbody> </table>	Value	Description	SQL_ACCESS_MODE	Determines type of access this program uses	SQL_AUTOCOMMIT	0 = Autocommit off, 1 = Autocommit on	SQL_LOGIN_TIMEOUT	Number of seconds to wait for a login request to complete before returning to the application.
Value	Description								
SQL_ACCESS_MODE	Determines type of access this program uses								
SQL_AUTOCOMMIT	0 = Autocommit off, 1 = Autocommit on								
SQL_LOGIN_TIMEOUT	Number of seconds to wait for a login request to complete before returning to the application.								



		The default is 15
	SQL_OPT_TRACE	Integer value telling the Driver Manager whether or not to perform tracing. 0 = Tracing off (Default) 1 = Tracing on
	SQL_OPT_TRACEFILE	Null-terminated character string containing the name of the trace file. If tracing is enabled, the Driver Manager writes to this file each time the application calls a function. If no trace file name is specified, the Driver Manager writes to SQL.LOG
	SQL_TRANSLATE_DLL	Null-terminated character string containing the name of a DLL containing the functions SQLClientToDataSource and SQLDataSourceToClient the driver loads and uses to perform tasks such as character set translation. This option may only be specified if the driver has connected to the data source
	SQL_TRANSLATE_OPTION	32-bit flag value that is passed to the translate DLL. This option may only be specified if the driver has connected to the data source
	SQL_TXN_ISOLATION	32-bit bitmask that sets the transaction isolation level for the current connection index. Refer to ODBC documentation for details on setting this parameter
Value		Value associated with the option. Depending on the type of option used, it can either be NULL, an integer, or a pointer to a string.

### Example

```
DO_SQLAllocStmt( C0, S0 );
DO_SQLSetStmtOption( S0, 1229, 0 );
DO_SQLSetStmtOption( S0, SQL_CONCURRENCY, 1);
DO_SQLSetConnectOption( C0, SQL_AUTOCOMMIT, 0 );
DO_SQLSetConnectOption( C0, SQL_TXN_ISOLATION, 1 );
DO_SQLFreeStmt( S0, SQL_CLOSE );
DO_SQLFreeStmt( S0, SQL_UNBIND );
```

### DO\_SQLSetCursorName

Associates a cursor name with an active command\_index.

The only SQL statements that accept cursor names are UPDATE and DELETE.

#### Syntax

```
DO_SQLSetCursorName( int StatementIndex, UCHAR* CursorName );
```

#### Return Value

Parameters

Parameter	Description
StatementIndex	Index into the table of statement handles.
CursorName	Name of the cursor.

Example

```
DO_SQLSetCursorName( S1, "C1" );
.....
.....
DO_SQLPrepare( S1,"UPDATE EMPLOYEE SET date=? WHERE CURRENT OF C1" );
```

DO\_SQLSetDescField

Sets a descriptor field. A call to DO\_SQLSetDescField can set a field of any descriptor type that can be set. Call DO\_SQLSetDescField first when dealing with an explicitly allocated descriptor, as it allocates the rows of an explicitly allocated descriptor.

Syntax

```
DO_SQLSetDescField( int DescriptorHandle, short RecordNumber, short FieldID, SQLPOINTER Value, long BufferLen )
```

Return Value

None

Parameters

Parameter	Description
DescriptorHandle	Points to a structure used to describe rows of a result set, or a set of parameters to be bound to a statement.
RecordNumber	The record number of the descriptor.
FieldID	An attribute to set for the record.
Value	The value to set the FieldID to.
BufferLen	Length of the value coming in.

Example

```
DO_SQLSetDescField( D0, 0, SQL_DESC_COUNT, 2, -6 );
DO_SQLSetDescRec( D0, 1, SQL_INTEGER, 0, 4, 10, 0, "10", 4, 4 );
DO_SQLSetDescRec( D0, 2, SQL_INTEGER, 0, 4, 10, 0, "10", 4, 4 );
DO_SQLCopyDesc( D0, D1 );
DO_SQLFreeHandle( SQL_HANDLE_DESC, D1 );
DO_SQLGetDescRec( D2, 1, 0 );
DO_SQLFreeHandle( SQL_HANDLE_DESC, D2 );
DO_SQLFreeHandle( SQL_HANDLE_DESC, D1 );
```

DO\_SQLSetDescRec

Sets multiple descriptor fields with a single call.

Use `DO_SQLSetDescRec` to change fields affecting the binding of a column or parameter without calling `DO_SQLBindCol`, `DO_SQLBindParameter`, or `DO_SQLSetDescField`. `DO_SQLSetDescRec` can set fields on a descriptor not currently associated with a statement, sets more fields than `DO_SQLSetDescField`, can set fields on both an APD and an IPD in one call, and does not require a descriptor handle.

Because descriptors are associated with connections, a descriptor can carry over from one statement to the next and can be associated with different statements for continued bindings.

### Syntax

```
DO_SQLSetDescRec( int nDescIndex, short nRecordNumber, short nField, short nSubType, long nLength, short nPrecision, short nScale, char* pData, long pStrLen, long pIndicator )
```

### Return Value

### Parameters

Parameter	Description
<code>nDescIndex</code>	Points to the location of the descriptor structure in memory.
<code>nRecordNumber</code>	The descriptor record with fields to be set.
<code>nFieldId</code>	The C data type of the field to be set.
<code>nSubType</code>	Applicable only for interval data types and for date and time data types, which have subtypes.
<code>nLength</code>	The length, in bytes, of a character string or binary datatype.
<code>nPrecision</code>	The maximum number of digits used by the column or parameter.
<code>nScale</code>	Scales the maximum number of digits to the right of the decimal point.
<code>pData</code>	Points to parameter or column value.
<code>pStrLen</code>	Points to a variable that will contain the total length in bytes of a dynamic argument.
<code>pIndicator</code>	Points to an indicator variable that contains <code>SQL_NULL_DATA</code> if the column value is a <code>NULL</code> . Otherwise the variable is 0.

### Example

```
DO_SQLSetDescField( D0, 0, SQL_DESC_COUNT, 2, -6 );
DO_SQLSetDescRec( D0, 1, SQL_INTEGER, 0, 4, 10, 0, "10", 4, 4 );
DO_SQLSetDescRec( D0, 2, SQL_INTEGER, 0, 4, 10, 0, "10", 4, 4 );
DO_SQLCopyDesc( D0, D1 );
DO_SQLFreeHandle( SQL_HANDLE_DESC, D1 );
```

### DO\_SQLSetEnvAttr

Sets different aspects of the ODBC environment.

For ODBC 3.x, call this function immediately after calling `DO_SQLAllocHandle` to alert the environment handle as to which set of calls, ODBC 2.x or ODBC 3.x, the application will adhere.

## Language Reference Commands

DO\_SQLSetEnvAttr can only be called if a connection handle is not allocated on the environment. Environment attributes set by the application persist until DO\_SQLFreeHandle is called on the environment.

Environment connection elements are set automatically in DO\_initODBC.

### Syntax

```
DO_SQLSetEnvAttr( SQLINTEGER Attribute, void* AttributeValue, SQLINTEGER Indicator)
```

### Return Value

### Parameters

Parameter	Description
Attribute	The specific property the application is setting.
AttributeValue	The value of the specific property that the application is setting.
Indicator	Can be a length pointer, or is ignored by ODBC.

### Example

```
DO_SQLAllocHandle( SQL_HANDLE_ENV, 0, c0 );  
DO_SQLSetEnvAttr( SQL_ATTR_ODBC_VERSION, (SQLPOINTER)SQL_OV_ODBC2, -6 );  
DO_SQLAllocHandle( SQL_HANDLE_STMT, c0, s0 );
```

## DO\_SQLSetPos

Positions a cursor within a retrieved block of data.

### Syntax

```
DO_SQLSetPos( int StatementIndex, UWORD nRow, UWORD nRefresh, UWORD nLock );
```

### Return Value

### Parameters

Parameter	Description
StatementIndex	Index into the table of statement handles.
nRow	Absolute position of the cursor within the retrieved block of data. nRow must be a value from 1 to the number of rows in the rowset.
nRefresh	Specifies whether or not to refresh the buffer value for the row specified by nRow. If TRUE (1), the driver refreshes the buffer value. If FALSE (0), the driver does not change the buffer value.
nLock	Specifies whether or not to lock the row for subsequent update operation. If TRUE (1), the driver requests a lock for the row. If FALSE (0), the driver applies the form of concurrency control specified in a call to DO_SQLSetScrollOptions.

### Example

```
int iRow = 1;
DO_SQLSetPos( S1, iRow, FALSE, FALSE );
```

### DO\_SQLSetStmtAttr

Sets statement attributes and, as a result, sets descriptor fields.

When calling DO\_SQLSetStmtAttr to set fields, rather than DO\_SQLSetDescField, it is not necessary to obtain a descriptor handle for the function call.

When using DO\_SQLSetStmtAttr, calling it for a statement can affect other statements if the statement's Application Parameter Descriptor (APD) or Application Row Descriptor (ARD) is explicitly allocated and associated with other statements.

DO\_SQLSetStmtAttr modifies the APD or ARD and those modifications apply to all statements with which the descriptor is associated. To avoid this, disassociate the descriptor from the other statement using DO\_SQLSetStmtAttr to change the descriptor handle of SQL\_ATTR\_APP\_ROW\_DESC or SQL\_ATTR\_APP\_PARAM\_DESC. Then call DO\_SQLSetStmtAttr again.

When setting a statement attribute also sets a descriptor field, the field is set only for the descriptors currently associated with the statement identified by the StatementHandle parameter. Subsequent attribute settings are not affected. When DO\_SQLSetDescField sets a descriptor field that is also a statement attribute, it also sets the corresponding statement attribute.

### Syntax

```
DO_SQLSetStmtAttr( int nStmtIndex, long nAttribute, long nAttrValue, long nStrLength );
```

### Return Value

### Parameters

Parameter	Description
nStmtIndex	Points to a structure that ODBC uses to track different statement settings and descriptor settings within the same connection handle as the statement.
nAttribute	Attribute. For example: SQL_ATTR_APP_ROW_DESC. Note that even at the statement level, QALoad does not permit asynchronous transactions.
nAttrValue	The value set for the attribute.
nStrLength	Attribute length

### Example

```
DO_SQLAllocHandle( SQL_HANDLE_STMT, C0, S0 );
DO_SQLAllocHandle( SQL_HANDLE_DESC, C0, D0 );
DO_SQLSetStmtAttr( S0, SQL_ATTR_APP_PARAM_DESC, D0, SQL_IS_POINTER );
DO_SQLSetDescField( D0, 0, SQL_DESC_COUNT, 2, -6 );
```

### DO\_SQLSetStmtOption

Sets the boundaries of a specific statement handle.

Following is a list of value option constants and the meanings of their respective value parameters.

Parameter	Description
SQLBindType	<p>A 32-bit value that sets the binding orientation used when <code>DO_SQLExtendedFetch</code> is called on the associated C.</p> <p>Column-wise binding is selected by supplying the defined constant <code>SQL_BIND_BY_COLUMN</code> for the argument <code>vParam</code>.</p> <p>Row-wise binding is selected by supplying a value for <code>vParam</code> specifying the length of a structure or an instance of a buffer into which result columns will be bound.</p> <p>The length specified in <code>vParam</code> must include space for all of the bound columns and any padding of the structure or buffer. This ensures that when the address of a bound column is incremented with the specified length, the result points to the beginning of the same column in the next row. When using the size of operator with structures or unions in ANSI C, this behavior is guaranteed. Column-wise binding is the default binding orientation for <code>DO_SQLExtendedFetch</code>.</p>
SQLMaxLength	A value corresponding to the maximum amount of data that can be retrieved from a single column with a <code>LONG VARCHAR</code> or <code>LONG VARBINARY</code> data type.
SQLMaxRows	A value corresponding to the maximum number of rows to return to the application for a <code>SELECT</code> command. If <code>vParam</code> equals 0 (Default), the driver returns all rows.
SQLNoScan	A value. If <code>TRUE</code> (1), the driver does not scan SQL strings for escape clauses. Instead, the driver sends the command directly to the data source. If <code>FALSE</code> (Default, value 0), the driver scans for escape clauses.
SQLQueryTimeout	A value corresponding to the number of seconds to wait for an SQL statement to execute before returning to the application. If <code>vParam</code> equals 0 (Default), there is no time out.

### Syntax

```
DO_SQLSetStmtOption( int StatementIndex, ODBCSQLSetStmtOptionEnum nOption, UDWORD nParam );
```

### Return Value

### Parameters

Parameter	Description						
StatementIndex	Index into the table of statement handles.						
nOption	<p><i>ODBCSQLSetStmtOptionEnum</i></p> <p>One of the valid option constants. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td><code>SQL_QUERY_TIMEOUT</code></td> <td>An integer value corresponding to the number of seconds to wait for an SQL statement to execute before returning to the application. If <code>vParam</code> equals 0 (Default), there is no time out</td> </tr> <tr> <td><code>SQL_MAX_ROWS</code></td> <td>An integer value corresponding to the maximum</td> </tr> </tbody> </table>	Value	Description	<code>SQL_QUERY_TIMEOUT</code>	An integer value corresponding to the number of seconds to wait for an SQL statement to execute before returning to the application. If <code>vParam</code> equals 0 (Default), there is no time out	<code>SQL_MAX_ROWS</code>	An integer value corresponding to the maximum
Value	Description						
<code>SQL_QUERY_TIMEOUT</code>	An integer value corresponding to the number of seconds to wait for an SQL statement to execute before returning to the application. If <code>vParam</code> equals 0 (Default), there is no time out						
<code>SQL_MAX_ROWS</code>	An integer value corresponding to the maximum						

		number of rows to return to the application for a <b>SELECT</b> command. If vParam equals 0 (Default), the driver returns all rows
	SQL_NOSCAN	An integer value. If TRUE (1), the driver does not scan SQL strings for escape clauses. Instead, the driver sends the command directly to the data source. If FALSE (Default, value 0), the driver scans for escape clauses
	SQL_MAX_LENGTH	An integer value corresponding to the maximum amount of data that can be retrieved from a single column with a LONG VARCHAR or LONG VARBINARY data type
	SQL_ASYNC_ENABLE	A 32-bit integer value that specifies whether a function called with the specified hstmt is executed asynchronously@ SQL_ASYNC_ENABLE_OFF = Off (Default), SQL_ASYNC_ENABLE_ON = On
	SQL_BIND_TYPE	A 32-bit integer value that sets the binding orientation used when DO_SQLExtendedFetch is called on the associated C. Column-wise binding is selected by supplying the defined constant SQL_BIND_BY_COLUMN for the argument vParam. Row-wise binding is selected by supplying a value for vParam specifying the length of a structure or an instance of a buffer into which result columns will be bound
	SQL_CURSOR_TYPE	A 32-bit integer value that specifies the cursor type@ SQL_CURSOR_FORWARD_ONLY = The cursor only scrolls forward. SQL_CURSOR_STATIC = The data in the result set is static. SQL_CURSOR_KEYSET_DRIVEN = The driver saves and uses the keys for the number of rows specified in the SQL_KEYSET_SIZE statement option. SQL_CURSOR_DYNAMIC = The driver only saves and uses the keys for the rows in the rowset. The default value is SQL_CURSOR_FORWARD_ONLY. This option cannot be specified for an open cursor and can also be set through the crowKeyset argument in SQLSetScrollOptions
	SQL_CONCURRENCY	A 32-bit integer value that specifies the cursor concurrency@ SQL_CONCUR_READ_ONLY = Cursor is read-only. No updates are allowed. SQL_CONCUR_LOCK = Cursor uses the lowest level of locking sufficient to ensure that the row can be updated. SQL_CONCUR_ROWVER = Cursor uses optimistic concurrency control, comparing row versions, such as SQLBase ROWID or Sybase TIMESTAMP. SQL_CONCUR_VALUES = Cursor uses optimistic concurrency control, comparing values. The default value is

		<b>SQL_CONCUR_READ_ONLY</b>
	<b>SQL_KEYSET_SIZE</b>	A 32-bit integer value that specifies the number of rows in the keyset for a keyset-driven cursor. If the keyset size is 0 (the default), the cursor is fully keyset-driven. If the keyset size is greater than 0, the cursor is mixed (keyset-driven within the keyset and dynamic outside of the keyset). The default keyset size is 0
	<b>SQL_ROWSET_SIZE</b>	A 32-bit integer value that specifies the number of rows in the rowset. This is the number of rows returned by each call to <code>SQLExtendedFetch</code> . The default value is 1
	<b>SQL_SIMULATE_CURSOR</b>	A 32-bit integer value that specifies whether drivers that simulate positioned update and delete statements guarantee that such statements affect only one single row
	<b>SQL_RETRIEVE_DATA</b>	A 32-bit integer value@ <code>SQL_RD_ON</code> = <code>SQLExtendedFetch</code> retrieves data after it positions the cursor to the specified location. This is the default. <code>SQL_RD_OFF</code> = <code>SQLExtendedFetch</code> does not retrieve data after it positions the cursor
	<b>SQL_USE_BOOKMARKS</b>	A 32-bit integer value that specifies whether an application will use bookmarks with a cursor@ <code>SQL_UB_OFF</code> = Off (Default), <code>SQL_UB_ON</code> = On
nParam	The parameter value.	

### Example

```
DO_SQLAllocStmt( C0, S0 );
DO_SQLSetStmtOption( S0, SQL_QUERY_TIMEOUT, 60 );
DO_SQLSetStmtOption( S0, SQL_ASYNC_ENABLE, 1 );
```

### DO\_SQLSpecialColumns

Retrieves information about columns within a specified table.

`DO_SQLSpecialColumns` retrieves the following information:

- ! The optimal set of columns that uniquely identifies a row in the table.
- ! Columns that are automatically updated when any value in the row is updated by a transaction.
- ! The data is returned as a result set.

### Syntax

```
DO_SQLSpecialColumns( int StatementIndex, ODBCSQLSpecialColumnsColTypeEnum fColType, UCHAR*
szTableQualifier, UCHAR* szTableOwner, UCHAR* szTableName, ODBCSQLSpecialColumnsScopeEnum
fScope, ODBCSQLSpecialColumnsNullableEnum fNullable );
```

### Return Value



## Parameters

Parameter	Description								
StatementIndex	Index into the table of statement handles.								
fColType	<p><i>ODBCSQLSpecialColumnsColTypeEnum</i></p> <p>Type of column to return. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>SQL_BEST_ROWID</td> <td>Returns the optimal column or set of columns that, by retrieving values from the column or columns, allows any row in the specified table to be uniquely identified. A column can be either a pseudo column specifically designed for this purpose (as in ODBC ROWID or Ingres TID) or the column or columns of any unique index for the table.</td> </tr> <tr> <td>SQL_ROWVER</td> <td>Returns the column or columns in the specified table, if any, that are automatically updated by the data source when any value in the row is updated by any transaction (as in SQLBase ROWID or Sybase TIMESTAMP).</td> </tr> </tbody> </table>	Value	Description	SQL_BEST_ROWID	Returns the optimal column or set of columns that, by retrieving values from the column or columns, allows any row in the specified table to be uniquely identified. A column can be either a pseudo column specifically designed for this purpose (as in ODBC ROWID or Ingres TID) or the column or columns of any unique index for the table.	SQL_ROWVER	Returns the column or columns in the specified table, if any, that are automatically updated by the data source when any value in the row is updated by any transaction (as in SQLBase ROWID or Sybase TIMESTAMP).		
Value	Description								
SQL_BEST_ROWID	Returns the optimal column or set of columns that, by retrieving values from the column or columns, allows any row in the specified table to be uniquely identified. A column can be either a pseudo column specifically designed for this purpose (as in ODBC ROWID or Ingres TID) or the column or columns of any unique index for the table.								
SQL_ROWVER	Returns the column or columns in the specified table, if any, that are automatically updated by the data source when any value in the row is updated by any transaction (as in SQLBase ROWID or Sybase TIMESTAMP).								
SzTableQualifier	Qualifier name for the table.								
SzTableOwner	Owner name for the table.								
SzTableName	Table name.								
fScope	<p><i>ODBCSQLSpecialColumnsScopeEnum</i></p> <p>Minimum required scope of the ROWID. The returned ROWID may be of greater scope. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>SQL_SCOPE_CURROW</td> <td>The ROWID is guaranteed to be valid only while positioned on that row. A later reselect using ROWID may not return a row if the row was updated or deleted by another transaction</td> </tr> <tr> <td>SQL_SCOPE_TRANSACTION</td> <td>The ROWID is guaranteed to be valid for the duration of the current transaction</td> </tr> <tr> <td>SQL_SCOPE_SESSION</td> <td>The ROWID is guaranteed to be valid for the duration of the session (across transaction boundaries)</td> </tr> </tbody> </table>	Value	Description	SQL_SCOPE_CURROW	The ROWID is guaranteed to be valid only while positioned on that row. A later reselect using ROWID may not return a row if the row was updated or deleted by another transaction	SQL_SCOPE_TRANSACTION	The ROWID is guaranteed to be valid for the duration of the current transaction	SQL_SCOPE_SESSION	The ROWID is guaranteed to be valid for the duration of the session (across transaction boundaries)
Value	Description								
SQL_SCOPE_CURROW	The ROWID is guaranteed to be valid only while positioned on that row. A later reselect using ROWID may not return a row if the row was updated or deleted by another transaction								
SQL_SCOPE_TRANSACTION	The ROWID is guaranteed to be valid for the duration of the current transaction								
SQL_SCOPE_SESSION	The ROWID is guaranteed to be valid for the duration of the session (across transaction boundaries)								
fNullable	<p><i>ODBCSQLSpecialColumnsNullableEnum</i></p> <p>Determines whether to return special columns that have NULL values. Valid values are:</p>								

	Value	Description
	SQL_NO_NULLS	Exclude special columns that can have NULL values
	SQL_NULLABLE	Return special columns even if they can have NULL values

**Example**

```
DO_SQLSpecialColumns( S1, SQL_ROWVER, "", "", "qc_test", SQL_SCOPE_TRANSACTION, SQL_NULLABLE );
int pcol = DO_SQLNumResultCols( S1 );
```

**DO\_SQLStatistics**

Retrieves a list of statistics about a single table and the indexes associated with the table. The driver returns the information as a result set.

**Syntax**

```
DO_SQLStatistics( int StatementIndex, UCHAR* szTableQualifier, UCHAR* szTableOwner, UCHAR* szTableName, ODBCSQLStatisticsUniqueEnum fUnique, ODBCSQLStatisticsAccuracyEnum fAccuracy );
```

**Return Value**

**Parameter**

Parameter	Description						
StatementIndex	Index into the table of statement handles.						
SzTableQualifier	Qualifier name.						
SzTableOwner	Owner name.						
SzTableName	Table name.						
fUnique	<p><i>ODBCSQLStatisticsUniqueEnum</i></p> <p>Type of index. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>SQL_INDEX_UNIQUE</td> <td>Unique value index</td> </tr> <tr> <td>SQL_INDEX_ALL</td> <td>Non-unique value index</td> </tr> </tbody> </table>	Value	Description	SQL_INDEX_UNIQUE	Unique value index	SQL_INDEX_ALL	Non-unique value index
Value	Description						
SQL_INDEX_UNIQUE	Unique value index						
SQL_INDEX_ALL	Non-unique value index						
fAccuracy	<p><i>ODBCSQLStatisticsAccuracyEnum</i></p> <p>Importance of the CARDINALITY and PAGES columns in result set. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>SQL_ENSURE</td> <td>Requests that the driver unconditionally</td> </tr> </tbody> </table>	Value	Description	SQL_ENSURE	Requests that the driver unconditionally		
Value	Description						
SQL_ENSURE	Requests that the driver unconditionally						

	SQL_QUICK	retrieves the statistics  Requests that the driver retrieves results only if they are readily available from the server. In this case, the driver does not ensure the values are current
--	-----------	--

### Example

```
DO_SQLStatistics( S0, "", "", "qc_test", SQL_INDEX_ALL, SQL_QUICK );
```

## DO\_SQLTables

Returns the list of table names stored in a specific data source. The driver returns the information as a result set.

The `szTableQualifier`, `szTableOwner`, and `szTableName` parameters accept search patterns. Refer to ODBC documentation regarding the use of search patterns.

### Syntax

```
DO_SQLTables( int StatementIndex, UCHAR* szTableQualifier, UCHAR* szTableOwner, UCHAR* szTableName, UCHAR* szTableType );
```

### Return Value

### Parameters

Parameter	Description
StatementIndex	Index into the table of statement handles.
SzTableQualifier	Qualifier name.
SzTableOwner	Owner name.
SzTableName	Table name.
SzTableType	List of table types to match. If <code>szTableType</code> is not an empty string, it must contain a list of comma-separated, single quoted values for the types of interest (for example: <code>TABLE</code> or <code>VIEW</code> ). Valid table type identifiers may include <code>TABLE</code> , <code>VIEW</code> , <code>SYSTEM TABLE</code> , <code>ALIAS</code> , <code>SYNONYM</code> , or other data source-specific identifiers.

### Example

```
DO_SQLTables( S0, "", "", "", "'TABLE','VIEW','SYSTEM TABLE','ALIAS','SYNONYM' " );
```

## DO\_SQLTransact

Requests a commit or rollback operation for all update, insert, and delete transactions in progress on all command indexes associated with a connection.

Can also request that a commit or rollback operation be performed for all connections by specifying a connection index of -1.

## Language Reference Commands

### Syntax

```
DO_SQLTransact( int ConnectionIndex, ODBCSQLTransactTypeEnum fType );
```

### Return Value

### Parameters

Parameter	Description						
ConnectionIndex	Index into a table of ODBC connection handles or -1 to indicate the operation should be performed on all connections.						
fType	<i>ODBCSQLTransactTypeEnum</i> SQL transaction type option. Valid values are: <table border="1"><thead><tr><th>Value</th><th>Description</th></tr></thead><tbody><tr><td>SQL_COMMIT</td><td>Commit transaction</td></tr><tr><td>SQL_ROLLBACK</td><td>Rollback transaction</td></tr></tbody></table>	Value	Description	SQL_COMMIT	Commit transaction	SQL_ROLLBACK	Rollback transaction
Value	Description						
SQL_COMMIT	Commit transaction						
SQL_ROLLBACK	Rollback transaction						

### Example

```
DO_SQLFreeStmt( C1, SQL_DROP );  
DO_SQLTransact( S0, SQL_COMMIT );
```

## DO\_substr

Finds a value within a string.

### Syntax

```
DO_Substr( char* string, int placeholder, char* value );
```

### Return Value

### Parameters

Parameter	Description
String	The string to be searched.
Placeholder	Location in the string.
Value	The token to search for.

### Example

```
DO_SQLAllocStmt( C0, S0 );  
DO_SQLSetStmtOption( S0, SQL_QUERY_TIMEOUT, 60 );  
strcpy(sql_statement, "SELECT {1}, {2}, {3} FROM Customers");  
DO_substr(sql_statement, 1, "CustomerID" );  
DO_substr(sql_statement, 2, "CompanyName" );  
DO_substr(sql_statement, 3, "ContactName" );  
DO_SQLExecDirect( S0, sql_statement );  
DO_SQLFreeStmt( S0, SQL_CLOSE );
```

## GetBindColumnData

Retrieves data from one of the rows that are returned by `DO_SQLFetch` calls, after a combination of `DO_SQLSetStmtAttr` and `DO_SQLBindCol` calls.

### Syntax

```
GetBindColumnData (int nIndex, int nColumn, int nRow);
```

### Return Value

char\* containing the data or an error

### Parameters

Parameter	Description
nIndex	The statement index.
nColumn	The column of data to return.
nRow	The row of data to return.

### Example

```
DO_SQLFetch( S0 );
RR__printf( GetBindColumnData( S0, 1, 1 ) );
RR__printf( GetBindColumnData( S0, 2, 1 ) );
RR__printf( GetBindColumnData( S0, 1, 2 ) );
RR__printf( GetBindColumnData( S0, 2, 2 ) );
RR__printf( GetBindColumnData( S0, 1, 3 ) );
RR__printf( GetBindColumnData( S0, 2, 3 ) );
RR__printf( GetBindColumnData( S0, 1, 4 ) );
RR__printf( GetBindColumnData( S0, 2, 4 ) );
RR__printf( GetBindColumnData( S0, 1, 5 ) );
RR__printf( GetBindColumnData( S0, 2, 5 ) );
```

## Oracle Forms Server

### Oracle Forms Server Commands

#### ofsActivateListItem

Adds the `Tlist_Activated` property to the current message. `Tlist_Activated` property indicates user selection of an item in a List control.

#### ofsActivateTreeItem

Adds the `Event_Activated` property of a Tree control to the current message. `Event_Activated` property indicates user selection of an item in a Tree control.

#### ofsActivateWindow

Adds the `Window_Activate` property (with `Enabled` attribute) to the current message.

#### ofsClickButton

Adds the `Pressed` property of a Button control to the current message.

#### ofsClickTextFieldItem

Adds the `Pressed` property associated with a Text Field control to the current message.

[ofsClosePopList](#)

Adds the List\_Closed property of a PopList control to the current message.

[ofsCloseWindow](#)

Adds the Window\_Close property (with Enabled attribute) to the current message.

[ofsCollapseTreeItem](#)

Adds the Event-Collapsed property of a Tree control to the current message.

[ofsColorAdd](#)

Adds the Color\_Add property to the current message.

[ofsConnectToSocket](#)

Establishes a socket-mode connection to the Oracle Forms Server.

[ofsDeActivateWindow](#)

Adds the Window\_Activate property (with Disabled attribute) to the current message.

[ofsDefineTreeNode](#)

Adds the Node\_ID property of a Tree control to the current message. Node\_ID property defines the relative position of the tree item, counting nested tree items.

[ofsDefineTreeNodeOffset](#)

Adds the Node\_Offset property of a Tree control to the current message. Node\_Offset defines the relative position of the tree item, excluding nested tree items.

[ofsDelconifyWindow](#)

Adds the Window\_Iconified property (with Disabled attribute) to the current message.

[ofsDeSelectItem](#)

Adds the Value property (with Disabled attribute) to the current message.

[ofsDeSelectTreeEvent](#)

Adds the Event\_DeSelect property of a Tree control to the current message. This statement indicates the application is moving from an internal processing event that is associated with a tree item.

[ofsEdit](#)

Adds the Value property to the current message. The property is associated with a Text Field control.

[ofsExpandTreeItem](#)

Adds the Event\_Expanded property of a Tree control to the current message. The Event\_Expanded property indicates a Tree control item being expanded.

[ofsFindLOVValue](#)

Adds the LOV\_Find\_Value property of a List of Values control to the current message. The statement indicates the user is searching for an item in a List of Values control.

[ofsFocus](#)

Adds the Focus property (with Enabled attribute) to the current message.

[ofsGetServerData](#)

Returns the Forms data from the server reply. In Servlet mode and Secure Servlet mode, also returns the HTTP headers.

**ofsHideWindow**

Adds the Visible property (with Disabled attribute) to the current message.

**ofsHTTPDisconnect**

Closes the current HTTP connection to the Forms Listener servlet.

**ofsHTTPSetHdrProperty**

Establishes the HTTP headers to use for connecting to the Forms servlet and listener servlet.

**ofsHTTPSetListenerServletParms**

Sets the Forms Listener Servlet parameters prior to connection.

**ofsHTTPConnectToFormsServlet**

Opens an HTTP connection to the Forms servlet responsible for initiating a Forms applet instance.

**ofsHTTPConnectToListenerServlet**

Opens an HTTP connection to the Forms Listener servlet responsible for starting an instance of the Forms run time process.

**ofsHTTPInitialFormsConnect**

Opens an HTTP connection to the Forms Listener servlet and posts the initial Forms handshake information.

**ofsIconifyWindow**

Adds the Window\_Iconified property (with Enabled attribute) to the current message.

**ofsIndexKey**

Adds the Index\_Key property to the current message.

**ofsIndexSKey**

Adds the Index\_SKey property to the current message.

**ofsInitSessionCmdLine**

Adds the INITIAL\_CMDLINE property to the current message.

**ofsInitSessionTimeZone**

Adds the Time\_Zone property to the current message.

**ofsListItemValue**

Adds the List\_Item property of a PopList or a TList control to the current message.

**ofsLoadValue**

Loads the values of a byte array or a string array associated with a GUI control.

**ofsLOVRequestRow**

Adds the LOV\_REQUEST\_ROW property to the current message.

**ofsLOVSelection**

Adds the LOV\_SELECTION property to the current message.

**ofsMenuParamDlgOK**

Adds the MENUPARAM\_DLGOK property to the current message. This statement defines the text in the menu param dialog control.

**ofsOpenWindow**

## Language Reference Commands

Adds the Window\_Open property (with Disabled attribute) to the current message.

### [ofsRemoveFocus](#)

Adds the Focus property (with Disabled attribute) to the current message.

### [ofsSetCursorPosition](#)

Adds the Cursor\_Position property of a Text Field control to the current message.

### [ofsSetErrorDialogTitle](#)

Adds the DISPLAYERRORDIALOG\_TITLE property to the current message.

### [ofsSetFontName](#)

Adds the Font\_Name property to the current message.

### [ofsScroll](#)

Adds the Block\_Scroller property to the current message.

### [ofsScrollSize](#)

Adds the Block\_Scroller\_Size property to the current message.

### [ofsSelectItem](#)

Adds the Value property (with Enabled attribute) to the current Message.

### [ofsSelectMenuItem](#)

Adds the Menu\_Event property to the current message.

### [ofsSelectTreeEvent](#)

Adds the Selected\_Event property of a Tree Control to the current message.

### [ofsSendRecv](#)

Sends the client request as Forms messages to the Forms server, gets the server response, and reads the responses as Forms messages.

### [ofsServerSideDisconnect](#)

Disconnects QALoad's socket connection to the server-side code. The server-side code intercepts the messages between QALoad and the Forms Listener servlet.

### [ofsSetColorDepth](#)

Adds the Color\_Depth property to the current message.

### [ofsSetDisplaySize](#)

Adds the Display\_Size property to the current message.

### [ofsSetExpectedServerMsg](#)

Enables the script to continue if a known error or warning message is received from the server.

### [ofsSetFontName](#)

Adds the Font\_Name property to the current message.

### [ofsSetFontSize](#)

Adds the Font\_Size property to the current message.

### [ofsSetFontStyle](#)

Adds the Font\_Style property to the current message.



**ofsSetFontWeight**

Adds the Font\_Weight property to the current message.

**ofsSetICXTicket**

Sets the value of the ICX ticket for the current Oracle Applications login. The statement is used only in a Universal OFS-WWW session, as a replacement for the OracleAppsLogin() statement.

**ofsSetInitialVersion**

Adds the Initial\_Version property to the current message.

**ofsSetJavaContainerArgName**

Adds the JAVACONTAINER\_ARG\_NAME property to the current message.

**ofsSetJavaContainerArgValue**

Adds the JAVACONTAINER\_ARG\_VALUE property to the current message.

**ofsSetJavaContainerEvent**

Adds the JAVACONTAINER\_ARG\_EVENT property to the current message.

**ofsSetLogonDatabase**

Adds the LOGON\_DATABASE property to the current message.

**ofsSetLogonPassWord**

Adds the LOGON\_PASSWORD property to the current message.

**ofsSetLogonUserName**

Adds the LOGON\_USERNAME property to the current message.

**ofsSetNoRequiredVAList**

Adds the Required\_VA\_List property (with Disabled attribute) to the current message.

**ofsSetPropertyBoolean**

Adds the generic boolean property (with Enabled attribute) to the current message.

**ofsSetPropertyByte**

Adds the generic byte property to the current message.

**ofsSetPropertyByteArray**

Adds the generic byte array property to the current message.

**ofsSetPropertyCharacter**

Adds the generic Character property to the current message.

**ofsSetPropertyDate**

Adds the generic Date property to the current message.

**ofsSetPropertyFloat**

Adds the generic Float property to the current message.

**ofsSetPropertyInteger**

Adds the generic Integer property to the current message.

**ofsSetPropertyPoint**

Adds the generic Point property to the current message.

## Language Reference Commands

### [ofsSetPropertyRectangle](#)

Adds the generic Rectangle property to the current message.

### [ofsSetPropertyString](#)

Adds the generic String property to the current message.

### [ofsSetPropertyStringArray](#)

Adds the generic String array property to the current message.

### [ofsSetPropertyVoid](#)

Adds the generic Void property to the current message.

### [ofsSetRequiredVAList](#)

Adds the Required\_VA\_List property (with Enabled attribute) to the current message.

### [ofsSetRunOptions](#)

Sets the runtime values for CONNECT TYPE, HEARTBEAT, LOGGING (to replay capture file) and CHECK SERVER MESSAGES.

### [ofsSetScaleInfo](#)

Adds the Scale property to the current message.

### [ofsSetScreenResolution](#)

Adds the Screen Resolution property to the current message.

### [ofsSetSelection](#)

Adds the Selection property of a Text Field control to the current message.

### [ofsSetServletMode](#)

Creates a socket connection to the server-side code which communicates with the Forms Listener Servlet.

### [ofsSetServerFailedMsg](#)

Enables QALoad to fail playback based on the user-entered string and filter parameters.

### [ofsSetValue](#)

Adds a generic Value property to the current message.

### [ofsSetWindowLocation](#)

Adds the Location property of a Window control to the current message.

### [ofsSetWindowSize](#)

Adds the Size property of a Window control to the current message.

### [ofsShowWindow](#)

Adds the Visible property (with Enabled attribute) to the current message.

### [ofsSocketDisconnect](#)

Closes the connection of a socket-mode playback.

### [ofsStartSubMessage](#)

Adds a sub-message to the current message.

### [ofsTabControlTopPage](#)

Adds the TabControl\_Top\_Page property to the current message.

### [ofsUnsetPropertyBoolean](#)

Adds a generic Boolean property (with Disabled attribute) to the current message.

### ofsWindowCreated

Check if the specified window was created during the last transaction with the server (ofsSendRecv).

### ofsActivateListItem

Adds the TList\_Activated property to the current message.

Tlist\_Activated property indicates user selection of an item in a List control.

#### Syntax

```
void ofsActivateListItem(const char *sHandlerName, int ControlID, OFSActionTypeEnum
ActionType, int PropertyID, const char *sValue );
```

#### Return Value

#### Parameters

Parameter	Description						
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.						
ControlID	Captured ID of the GUI control for the current message.						
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						
sValue	The positional value of the activated List item.						

#### Example

```
//In the example below, the List item is defined,
//and then selected using the statement
//ofsActivateListItem. The value 7 indicates
//that the item is the 7th List item.

ofsListItemValue( "TLIST", 118, OFS_ENDMSG, 131, "7" ); /*Item value =      Material
      Transactions*/

ofsSendRecv(1 );
:
:

ofsActivateListItem( "TLIST", 118, OFS_ENDMSG, 341, "7" );
ofsSendRecv(1 );
```

## ofsActivateTreeItem

Adds the Event\_Activated property of a Tree control to the current message.

Event\_Activated property indicates user selection of an item in a Tree control. The selected item is associated with internal processing events.

### Syntax

```
void ofsActivateTreeItem(const char *sHandlerName, int ControlID, OFSActionTypeEnum
ActionType, int PropertyID, const char *sValue);
```

### Return Value

### Parameters

Parameter	Description						
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.						
ControlID	Captured ID of the GUI control for the current message.						
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						
Value	The positional value of the activated Tree item.						

### Example

```
//The statement ofsActivateTreeItem is
//similar to ofsActivateListItem
//but internal processing events occur
//when it is executed. A Tree item is a
//List Item that is associated with an event.
//In this example, item 4 (named "Sample Event1")
//in Tree Control ID 118 is selected.

ofsListItemValue( "TLIST", 118, OFS_ENDMSG, 131, "4" ); /*Item value = Sample Event1*/
ofsSendRecv(1 );

.
.
.

ofsActivateTreeItem( "Test Tree", 118, OFS_ENDMSG, 491, "4" );
```

## ofsActivateWindow

Adds the Window\_Activate property (with Enabled attribute) to the current message.

The Window\_Activate (with Enabled attribute) property indicates the opening of a new window.

### Syntax

```
void ofsActivateWindow( const char *sHandlerName, int ControlID, OFSActionTypeEnum
ActionType, int PropertyID);
```

### Return Value

### Parameters

Parameter	Description						
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.						
ControlID	Captured ID of the GUI control for the current message.						
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						

### Example

```
//This example indicates the window "Oracle
//Applications" being displayed as the top window,
//then the window is activated for use.

ofsShowWindow( "Oracle Applications", 32, OFS_ENDMSG, 173 );
ofsActivateWindow( "Oracle Applications", 32, OFS_ENDMSG, 247 );
ofsFocus( "TEXTFIELD", 75, OFS_ENDMSG, 174 );
ofsSendRecv(2 );
```

## ofsClickButton

Adds the Pressed property of a Button control to the current message. This statement indicates a button click activity.

### Syntax

```
void ofsClickButton(const char *sHandlerName, int ControlID, OFSActionTypeEnum ActionType,
int PropertyID);
```

### Return Value

## Parameters

Parameter	Description						
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.						
ControlID	Captured ID of the GUI control for the current message.						
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						

## Example

```
//In this example, control ID 52 represents the button that is clicked.
ofsClickButton( "BUTTON", 52, OFS_ENDMSG, 325 );
ofsSendRecv(1 );
```

## ofsClickTextFieldItem

Adds the Pressed property associated with a Text Field control to the current message.

This statement indicates an activity in which focusing on a Text Field item enables the user to click a button that triggers internal processing events.

## Syntax

```
void ofsClickTextFieldItem(const char *sHandlerName, int ControlID, OFSActionTypeEnum
ActionType, int PropertyID);
```

## Return Value

## Parameters

Parameter	Description
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.
ControlID	Captured ID of the GUI control for the current message.
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p>

	Value	Description
	OFS_ADD	Add the property to the current message.
	OFS_ENDMSG	Add the property to the current message and end the current message.
PropertyID	Oracle-designated ID for the property being added.	

### Example

```
//In this example, the location of Text Field
//control 274 is defined using ofsSetSelection.

//The Browse button embedded in Text Field control
//274 is clicked. The click, simulated by
//ofsClickTextFieldItem, deactivated the currently
//opened window "Find Material Transactions"
//(control 179) and also triggered Custom Control
//1367 to act as the top window.

ofsSetSelection( "TEXTFIELD", 274, OFS_ENDMSG, 195, 0, 0);
ofsClickTextFieldItem( "TEXTFIELD", 274, OFS_ENDMSG, 325 );
ofsSendRecv(1 );
ofsSendRecv(1 );
ofsDeActivateWindow( "Find Material Transactions ", 179, OFS_ENDMSG, 247 );
ofsSendRecv(1 );

ofsSetPropertyInteger( "CUSTOMCONTROL", 1367, OFS_ADD, 2601, "91" );
ofsSetPropertyInteger( "CUSTOMCONTROL", 1367, OFS_ADD, 2600, "0" );
ofsSetPropertyInteger( "CUSTOMCONTROL", 1367, OFS_ADD, 2600, "0" );
ofsSetPropertyString( "CUSTOMCONTROL", 1367, OFS_ENDMSG, 2600, "xxx" );
ofsSendRecv(1 );
```

### ofsClosePopList

Adds the List\_Closed property of a PopList control to the current message.

The List\_Closed property indicates a PopList control is closed.

#### Syntax

```
void ofsClosePopList(const char *sHandlerName, int ControlID, OFSActionTypeEnum ActionType,
int PropertyID);
```

#### Return Value

#### Parameters

Parameter	Description
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.
ControlID	Captured ID of the GUI control for the current message.
ActionType	<i>OFSActionTypeEnum</i> This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special

	processing. Valid values are:						
	<table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						

**Example**

```
//In this example, control ID 52 represents
//the PopList control that is closed.
ofsClosePopList ( "POPLIST", 52, OFS_ENDMSG, 332 );
```

**ofsCloseWindow**

Adds the Window\_Close property (with Enabled attribute) to the current message.

The Window\_Close property indicates the act of closing a window.

**Syntax**

```
void ofsCloseWindow(const char *sHandlerName, int ControlID, OFSActionTypeEnum ActionType,
int PropertyID);
```

**Return Value**

**Parameters**

Parameter	Description						
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.						
ControlID	Captured ID of the GUI control for the current message.						
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						



## Example

```
//In this example, control ID 179 (named
//"Find Material Transactions") represents
//the window that is closed.

ofsCloseWindow( "Find Material Transactions ", 179, OFS_ENDMSG, 216 );
```

## ofsCollapseTreeItem

Adds the Event-Collapsed property of a Tree control to the current message.

The Event\_Collapsed property indicates a Tree control item being collapsed.

### Syntax

```
void ofsCollapseTreeItem(const char *sHandlerName, int ControlID, OFSActionTypeEnum
ActionType, int PropertyID, const char *Value);
```

### Parameters

Parameter	Description						
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.						
ControlID	Captured ID of the GUI control for the current message.						
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						
Value	The relative position of the Tree control item.						

## Example

```
//In this example, item 4 (named "FORD") in Tree control ID 73 is collapsed.

ofsStartSubMessage( "TREE", 73, OFS_STARTSUBMSG, 180, "0" );
ofsSetPropertyPoint( "TREE", 73, OFS_ADD, 185, 19, 50);
ofsSetPropertyByte( "TREE", 73, OFS_ENDMSG, 186, "16" );
ofsRemoveFocus( "TEXTFIELD", 69, OFS_ENDMSG, 174 );
ofsFocus( "TREE", 73, OFS_ENDMSG, 174 );
ofsCollapseTreeItem( "TREE", 73, OFS_ENDMSG, 490, "4" ); /*Item value = FORD*/
ofsSendRecv(1 );
```

## ofsColorAdd

Adds the Color\_Add property to the current message.

## Language Reference Commands

The `Color_Add` property is applied to the initial Forms environment.

### Syntax

```
void ofsColorAdd(const char *sHandlerName, int ControlID, OFSActionTypeEnum ActionType, int PropertyID, const char *Value);
```

### Return Value

### Parameters

Parameter	Description						
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.						
ControlID	Captured ID of the GUI control for the current message.						
ActionType	<i>OFSActionTypeEnum</i> This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are: <table border="1"><thead><tr><th>Value</th><th>Description</th></tr></thead><tbody><tr><td>OFS_ADD</td><td>Add the property to the current message.</td></tr><tr><td>OFS_ENDMSG</td><td>Add the property to the current message and end the current message.</td></tr></tbody></table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						
Value	The color being applied to the Forms application environment.						

### Example

```
//The initial set of Forms statements describes the
//initial Forms environment. The description is matched
//on the server side. In this example, a color is
//defined as part of the Forms environment.

ofsSetInitialVersion( "RUNFORM",1, OFS_ADD, 268, "90290" );
ofsSetScreenResolution( "RUNFORM", 1, OFS_ADD, 263, 96, 96);
:
ofsColorAdd( "RUNFORM", 1, OFS_ADD, 284, "16776960" );
:
ofsSetRequiredVAList( "RUNFORM", 1, OFS_ADD, 291 );
:
ofsFocus( "BUTTON", 58, OFS_ENDMSG, 174 );
ofsSendRecv(1 );
```

### ofsConnectToSocket

Establishes a socket-mode connection to the Oracle Forms Server.

## Syntax

```
void ofsConnectToSocket(const char *Hostname, int Port);
```

## Return Value

## Parameters

Parameter	Description
Hostname	Host name or IP address of the Oracle Forms Server.
Port	Port number used to connect to the Forms server.

## Example

```
//In socket-mode, QALoad uses the IP address
//or host name of the server machine and the
//Form Server Port to execute a socket connection
//with the server.
```

```
ofsConnectToSocket("10.10.0.167", 9002 );
```

## ofsDeActivateWindow

Adds the Window\_Activate property, with Disabled attribute, to the current message.

The Window\_Activate property, with Disabled attribute, indicates the ending of a currently opened window.

## Syntax

```
void ofsDeActivateWindow(const char *sHandlerName, int ControlID, OFSActionTypeEnum
ActionType, int PropertyID);
```

## Return Value

## Parameters

Parameter	Description						
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.						
ControlID	Captured ID of the GUI control for the current message.						
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						

PropertyID	Oracle-designated ID for the property being added.
------------	--

**Example**

```
//This example shows the window "WINDOW_DATABASETTEST"
//being terminated prior to the ending of the HTTP session.

ofsDeActivateWindow( "WINDOW_DATABASETTEST", 24, OFS_ENDMSG, 247 );
ofsFocus( "BUTTON", 52, OFS_ENDMSG, 174 );
ofsSendRecv(1 );
ofsHTTPDisconnect();
```

**ofsDefineTreeNode**

Adds the Node\_ID property of a Tree control to the current message.

Node\_ID property defines the relative position of the tree item, counting nested tree items.

**Syntax**

```
void ofsDefineTreeNode(const char *sHandlerName, int ControlID, OFSActionTypeEnum
ActionType, int PropertyID, const char *Value);
```

**Parameters**

Parameter	Description						
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.						
ControlID	Captured ID of the GUI control for the current message.						
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						
Value	The relative position of the tree item, counting nested tree items.						

**Example**

```
//In this example, the relative positions of items
//6 and 12 in Tree control ID 73 are defined.

ofsStartSubMessage( "TREE", 73, OFS_STARTSUBMSG, 505, "0" );
ofsDefineTreeNode( "TREE", 73, OFS_ADD, 500, "6" ); /*Item value = BLAKE*/
ofsDefineTreeNodeOffset( "TREE", 73, OFS_ENDMSG, 503, "2" );
ofsStartSubMessage( "TREE", 73, OFS_STARTSUBMSG, 505, "0" );
ofsDefineTreeNode( "TREE", 73, OFS_ADD, 500, "6" ); /*Item value = BLAKE*/
ofsDefineTreeNodeOffset( "TREE", 73, OFS_ENDMSG, 503, "3" );
ofsStartSubMessage( "TREE", 73, OFS_STARTSUBMSG, 505, "0" );
```

```
ofsDefineTreeNode( "TREE", 73, OFS_ADD, 500, "12" ); /*Item value = CLARK*/
ofsDefineTreeNodeOffset( "TREE", 73, OFS_ENDMSG, 503, "0" );
ofsSendRecv(1 );
```

## ofsDefineTreeNodeOffset

Adds the Node\_Offset property of a Tree control to the current message.

Node\_Offset defines the relative position of the tree item, excluding nested tree items.

### Syntax

```
void ofsDefineTreeNodeOffset(const char *sHandlerName, int ControlID, OFSActionTypeEnum
ActionType, int PropertyID, const char *Value);
```

### Return Value

### Parameters

Parameter	Description						
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.						
ControlID	Captured ID of the GUI control for the current message.						
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						
Value	The relative position of the tree item, counting nested tree items.						

### Example

```
//In this example, the relative positions of
//items 6 and 12 in Tree control ID 73 are defined.

ofsStartSubMessage( "TREE", 73, OFS_STARTSUBMSG, 505, "0" );
ofsDefineTreeNode( "TREE", 73, OFS_ADD, 500, "6" ); /*Item value = BLAKE*/
ofsDefineTreeNodeOffset( "TREE", 73, OFS_ENDMSG, 503, "2" );
ofsStartSubMessage( "TREE", 73, OFS_STARTSUBMSG, 505, "0" );
ofsDefineTreeNode( "TREE", 73, OFS_ADD, 500, "6" ); /*Item value = BLAKE*/
ofsDefineTreeNodeOffset( "TREE", 73, OFS_ENDMSG, 503, "3" );
ofsStartSubMessage( "TREE", 73, OFS_STARTSUBMSG, 505, "0" );
ofsDefineTreeNode( "TREE", 73, OFS_ADD, 500, "12" ); /*Item value = CLARK*/
ofsDefineTreeNodeOffset( "TREE", 73, OFS_ENDMSG, 503, "0" );
ofsSendRecv(1 );
```

## ofsDeIconifyWindow

Adds the Window\_Iconified property,with Disabled attribute, to the current message.

This statement indicates a window being sized up from its icon representation.

### Syntax

```
void ofsDeIconifyWindow(const char *sHandlerName, int ControlID, OFSActionTypeEnum
ActionType, int PropertyID);
```

### Return Value

### Parameters

Parameter	Description						
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.						
ControlID	Captured ID of the GUI control for the current message.						
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						

### Example

```
//In this example, window control ID 118 is
//being sized up from its icon representation.

ofsDeIconifyWindow ( "FORMWINDOW", 118, OFS_ENDMSG, 243 );
```

## ofsDeSelectItem

Adds the Value property,with Disabled attribute, to the current Message.

The Value property is applied to a Radio button, Checkbox, List Box or Combo Box control. This statement indicates the mouse moving away from a previously selected item that is associated with a Radio button, Checkbox, List Box or a Combo Box.

### Syntax

```
void ofsDeSelectItem( const char *sHandlerName, int ControlID, OFSActionTypeEnum ActionType,
int PropertyID);
```

### Return Value

## Parameters

Parameter	Description						
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.						
ControlID	Captured ID of the GUI control for the current message.						
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						

## Example

```
//In this example, the mouse is deselecting Checkbox
//control ID 60 and selecting Radiobutton control ID 63.

ofsDeselectItem( "CHECKBOX", 60, OFS_ENDMSG, 131 );
ofsSendRecv(1 );

ofsRemoveFocus( "CHECKBOX", 60, OFS_ENDMSG, 174 );
ofsFocus( "RADIOBUTTON", 63, OFS_ENDMSG, 174 );
ofsSendRecv(1 );

ofsSelectItem( "RADIOBUTTON", 63, OFS_ENDMSG, 131 );
ofsSendRecv(1 );
```

## ofsDeselectTreeEvent

Adds the Event\_DeSelect property of a Tree control to the current message.

This statement indicates the application is moving from an internal processing event that is associated with a tree item.

## Syntax

```
void ofsDeselectTreeEvent( const char *sHandlerName, int ControlID, OFSActionTypeEnum
ActionType, int PropertyID, const char *Value);
```

## Return Value

## Parameters

Parameter	Description
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.

ControlID	Captured ID of the GUI control for the current message.						
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						
Value	The relative position of the tree control item.						

**Example**

```
//In this example, user activity is moving
//away from Tree control ID 73.
ofsDeselectTreeEvent ( "TREE", 73, OFS_ENDMSG, 492, "1" );
```

**ofsEdit**

Adds the Value property to the current message.

The property is associated with a Text Field control. This statement indicates the act of entering values into a text field.

**Syntax**

```
void ofsEdit( const char *sHandlerName, int ControlID, int ActionType, int PropertyID, const char *Value);
```

**Return Value**

**Parameters**

Parameter	Description
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.
ControlID	Captured ID of the GUI control for the current message.
ActionType	<p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.</p> <p>OFS_ADD: Add the property to the current message.  OFS_ENDMSG: Add property to the current message and end the current message.</p>



PropertyID	Oracle-designated ID for the property being added.
Value	The value entered in the text field.

### Example

```
//In this example, the user enters "MFG"
//into Text Field control 75. The other
//statements are describing the location
//of the TextField control, the position
//of the cursor within the Text Field control,
//and recognizing the entry as a keyed entry.

ofsEdit( "TEXTFIELD", 75, OFS_ADD, 131, "MFG" );
ofsSetSelection( "TEXTFIELD", 75, OFS_ADD, 195, 3, 3);
ofsSetCursorPosition( "TEXTFIELD", 75, OFS_ENDMSG, 193, "3" );
ofsIndexSKey( "TEXTFIELD", 75, OFS_ENDMSG, 176, 9, 0);
ofsSendRecv(1 );
```

### ofsExpandTreeItem

Adds the Event\_Expanded property of a Tree control to the current message.

The Event\_Expanded property indicates a Tree control item being expanded.

#### Syntax

```
void ofsExpandTreeItem( const char *sHandlerName, int ControlID, OFSActionTypeEnum
ActionType, int PropertyID, const char *Value);
```

#### Return Value

#### Parameters

Parameter	Description						
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.						
ControlID	Captured ID of the GUI control for the current message.						
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						
Value	The relative position of the tree item, counting nested tree items.						

**Example**

```
//In this example, the item in Tree control
//ID 73 (named "CLARK") is expanded.

ofsStartSubMessage( "TREE", 73, OFS_STARTSUBMSG, 180, "0" );
ofsSetPropertyPoint( "TREE", 73, OFS_ADD, 185, 12, 220);
ofsSetPropertyByte( "TREE", 73, OFS_ENDMSG, 186, "16" );
ofsExpandTreeItem( "TREE", 73, OFS_ENDMSG, 489, "12" ); /*Item value = CLARK*/
ofsSendRecv(1 );
```

**ofsFindLOVValue**

Adds the LOV\_Find\_Value property of a List of Values control to the current message.

The statement indicates the user is searching for an item in a List of Values control. The search typically returns an item ID when a valid item is found for the given search string.

**Syntax**

```
void ofsFindLOVValue( const char *sHandlerName, int ControlID, OFSActionTypeEnum ActionType,
int PropertyID, const char *Value);
```

**Return Value**

**Parameters**

Parameter	Description						
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.						
ControlID	Captured ID of the GUI control for the current message.						
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						
Value	The name used to search the List of Values.						

**Example**

```
//In this example, the user is using
//"CGI" string to search inside LOV
//control 85 (named "LISTVALUESDIALOG").

ofsFindLOVValue ( "LISTVALUESDIALOG", 85, OFS_ENDMSG, 454, "CGI" );
```

## ofsFocus

Adds the Focus property (with Enabled attribute) to the current message.

The Focus property typically indicates the mouse hovering on a GUI control.

### Syntax

```
void ofsFocus(const char *sHandlerName, int ControlID, int ActionType, int PropertyID);
```

### Return Value

### Parameters

Parameter	Description
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.
ControlID	Captured ID of the GUI control for the current message.
ActionType	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
PropertyID	Oracle-designated ID for the property being added.

### Example

```
//In this example, control ID 78 (a button)
//is the object of Focus. The button is
//subsequently clicked.

ofsFocus( "BUTTON", 78, OFS_ENDMSG, 174 );
ofsSendRecv(1 );
ofsClickButton( "BUTTON", 78, OFS_ENDMSG, 325 );
ofsSendRecv(1 );
```

## ofsGetServerData

Returns the Forms data from the server reply. In Servlet mode and Secure Servlet mode, also returns the HTTP headers.

The statement is manually added to the script in conjunction with [DO\\_ExtractString](#), which extracts a substring from the returned data. The extracted value is passed to subsequent script statements.

The combination of [DO\\_ExtractString](#) and [ofsGetServerData](#) statements enables you to obtain and use dynamic Forms data, based on the server response. These statements replace the functionality provided by the OFS Java script statement [GetControlValue](#).

### Syntax

```
const char *ofsGetServerData();
```

### Return Value

Returns the Forms data from the server reply. In Servlet mode and Secure Servlet mode, also returns the HTTP headers.

Parameters

None

Example

The example below executes RR\_printf and DO\_ExtractString statements after the ofsSendRecv statement. Both statements use the ofsGetServerData statement as a parameter. After printing the result value, the memory allocated by DO\_ExtractString() is freed, and the pointer is set to NULL.

**Caution:** The value returned by the ofsGetServerData command should not be freed. Calling free on this pointer results in a memory error in the script.

```

.....
/* Declare Variables */
char *szResult = NULL;
...
BEGIN_TRANSACTION();
...
...
ofsSendRecv(1); //ClientSeqNo=1|CapTime=1090942125.437|1090942125.437
DO_ExtractString( ofsGetServerData(), /* returns character string containing Forms data */
1,
"P|S|284|java.lang.Integer|0|", /*left filter param*/
"P|S|284|java.lang.Integer|0|657930", /*right filter param*/
&szResult /* Value contains the dynamic value to be used in subsequent statements */
);
RR_printf("item: %s", szResult);
free(szResult);
szResult = NULL;

```

ofsHideWindow

Adds the Visible property, with Disabled attribute, to the current message.

The property is associated with a Window control. The statement indicates a window being hidden from view.

Syntax

```
void ofsHideWindow(const char *sHandlerName, int ControlID, OFSActionTypeEnum ActionType, int PropertyID);
```

Return Value

Parameters

Parameter	Description		
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.		
ControlID	Captured ID of the GUI control for the current message.		
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="0" style="width: 100%;"> <tr> <td style="width: 50%;">Value</td> <td style="width: 50%;">Description</td> </tr> </table>	Value	Description
Value	Description		

	OFS_ADD	Add the property to the current message.
	OFS_ENDMSG	Add the property to the current message and end the current message.
PropertyID	Oracle-designated ID for the property being added.	

### Example

```
//In this example, window control ID 118
//is being hidden from view.
ofsHideWindow( "FORMWINDOW", 118, OFS_ENDMSG, 173 );
```

## ofsHTTPConnectToFormsServlet

Opens an HTTP connection to the Forms servlet responsible for initiating a Forms applet instance.

### Syntax

```
void ofsHTTPConnectToFormsServlet(const char *sformsServletURL);
```

### Return Value

### Parameters

Parameter	Description
sformsServletURL	The URL location of the Forms Servlet.

### Example

```
ofsHTTPConnectToFormsServlet( "http://ntsap45b:7779/forms90/f90servlet?ifcmd=startsession"
);
```

## ofsHTTPConnectToListenerServlet

Opens an HTTP connection to the Forms Listener servlet responsible for starting an instance of the Forms run time process.

### Syntax

```
void ofsHTTPConnectToListenerServlet(const char *sformsServletURL);
```

### Return Value

### Parameters

Parameter	Description
sformsServletURL	The URL location of the Forms Listener servlet.

### Example

```
ofsHTTPConnectToListenerServlet( "http://ntsap45b:7779/forms90/l90servlet");
```

## ofsHTTPDisconnect

Closes the current HTTP connection to the Forms Listener Servlet.

### Syntax

```
void ofsHTTPDisconnect();
```

### Return Value

### Parameters

None

### Example

```
ofsHTTPDisconnect();
```

## ofsHTTPInitialFormsConnect

Opens an HTTP connection to the Forms Listener servlet and posts the initial Forms handshake information.

### Syntax

```
void ofsHTTPInitialFormsConnect();
```

### Return Value

### Parameters

None

### Example

```
ofsHTTPInitialFormsConnect();
```

## ofsHTTPSetHdrProperty

Establishes the HTTP headers to use for connecting to the Forms servlet and listener servlet. Headers that can be set with this function are: Cookie, User-Agent, Host, Accept, and Connection.

### Syntax

```
void ofsHTTPSetHdrProperty(const char *sName, const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sName	The HTTP header name.
sValue	The HTTP header value.

### Example

```
ofsHTTPSetHdrProperty("User-Agent", "Java1.3.1.9" );  
ofsHTTPSetHdrProperty("Host", "ntsap45b.prodti.compuware.com:4445" );
```

```
ofsHTTPSetHdrProperty("Accept", "text/html, image/gif, image/jpeg, *; q=.2, "
"/*; q=.2" );
ofsHTTPSetHdrProperty("Connection", "Keep-alive" );
```

### ofsHTTPSetListenerServletParms

Sets the Forms Listener Servlet parameters prior to connection.

#### Syntax

```
void ofsHTTPSetListenerServletParms(const char *sListenerServlet);
```

#### Return Value

#### Parameters

Parameter	Description
sListenerServlet	Servlet parameters to use for this session.

#### Example

```
ofsHTTPSetListenerServletParms( "?ifcmd=getinfo&ifhost=C104444D01&ifip="
"192.168.234.1" );
```

### ofsIconifyWindow

Adds the Window\_Iconified property, with Enabled attribute, to the current message. This statement indicates a window being sized down to its icon representation.

#### Syntax

```
void ofsIconifyWindow( const char *sHandlerName, int ControlID, OFSActionTypeEnum
ActionType, int PropertyID);
```

#### Return Value

#### Parameters

Parameter	Description				
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.				
ControlID	Captured ID of the GUI control for the current message.				
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="0"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.
Value	Description				
OFS_ADD	Add the property to the current message.				

	OFS_ENDMSG	Add the property to the current message and end the current message.
PropertyID	Oracle-designated ID for the property being added.	

**Example**

```
//In this example, window control ID 118 is
//being sized down to an icon.
ofsIconifyWindow ("FORMWINDOW", 118, OFS_ENDMSG, 243);
```

**ofsIndexKey**

Adds the Index\_Key property to the current message.

The Index\_Key property typically indicates a keyed entry in a TextField control, such as a user ID entry.

**Syntax**

```
void ofsIndexKey(const char *sHandlerName, int iControlId, int iAction, int iPropertyID, int iCoordinateX, int iCoordinateY);
```

**Return Value**

**Parameters**

Parameter	Description
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
ControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
iCoordianteX	X coordinate of the keyed entry.
iCoordinateY	Y coordinate of the keyed entry.

**Example**

```
//In this example, the user enters "M" into Text Field control 75.
//The other statements are describing the location of the TextField control,
//the position of the cursor within the Text Field control,
//and recognizing the entry as a keyed entry.
ofsEdit( "TEXTFIELD", 75, OFS_ADD, 131, "M" );
ofsSetSelection( "TEXTFIELD", 75, OFS_ADD, 195, 1, 1);
ofsSetCursorPosition( "TEXTFIELD", 75, OFS_ENDMSG, 193, "1" );
ofsIndexKey( "TEXTFIELD", 75, OFS_ENDMSG, 175, 97, 0);
ofsSendRecv(1 );
```



## ofsIndexSKey

Adds the Index\_SKey property to the current message.

The Index\_SKey property is typically associated with a keyed entry in a TextField control, such as a user ID entry.

### Syntax

```
void ofsIndexSKey(const char *sHandlerName, int iControlID, int iAction, int iPropertyID,
int iCoordinateX, int iCoordinateY);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
iCoordinateX	X coordinate of the keyed entry.
iCoordinateY	Y coordinate of the keyed entry.

### Example

```
//In this example, the user enters "MFG" into Text Field control 75.
//The other statements are describing the location of the TextField control,
//the position of the cursor within the Text Field control,
//and recognizing the entry as a keyed entry.

ofsEdit( "TEXTFIELD", 75, OFS_ADD, 131, "MFG" );
ofsSetSelection( "TEXTFIELD", 75, OFS_ADD, 195, 3, 3);
ofsSetCursorPosition( "TEXTFIELD", 75, OFS_ENDMSG, 193, "3" );
ofsIndexSKey( "TEXTFIELD", 75, OFS_ENDMSG, 176, 9, 0);
ofsSendRecv(1);
```

## ofsInitSessionCmdLine

Adds the INITIAL CMDLINE property to the current message. The INITIAL CMDLINE property is applied to the initial Forms environment.

### Syntax

```
void ofsInitSessionCmdLine(const char *sClassName, int iHandlerID, int iAction, int
iPropertyID, const char *sCmdLineInfo);
```

## Return Value

## Parameters

Parameter	Description
sClassName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.
iHandlerID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sCmdLineInfo	Value of the Initial CmdLine property.

## Example

```
ofsInitSessionCmdLine("RUNFORM", 1, OFS_ADD, 265,
    "server module=/oracle/appl/vis11iappl/fnd/11.5.0/forms/US/FNDSCSGN userid=APPLS"
    "YSPUB/PUB@vis11i fndnam=APPS");
```

## ofsInitSessionTimeZone

Adds the Time\_Zone property to the current message. The Time\_Zone property is applied to the initial Forms environment.

## Syntax

```
void ofsInitSessionTimeZone(const char *sClassName, int iHandlerID, int iAction, int iPropertyID, const char *sTimeZone);
```

## Return Value

## Parameters

Parameter	Description
sClassName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.
iHandlerID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.

iPropertyID	Oracle-designated ID for the property being added.
sTimeZone	The time zone to use for this session. The time zone is specified by the application.

### Example

```
ofsInitSessionTimeZone ( "RUNFORM", 1, OFS_ENDMSG, 530, "America/New_York" );
```

## ofsListItemValue

Adds the List\_Item property of a PopList or a TList control to the current message.

This statement defines an item in a PopList or a TList control.

### Syntax

```
void ofsListItemValue(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	Relative position of the item in the PopList or TList control.

### Example

```
//In this example, item 6 is defined in Poplist control ID 66.  
//Item 6 is labeled "Cindy Wang."  
ofsListItemValue( "POPLIST", 66, OFS_ENDMSG, 131, "6" ); /* Item value = Cindy Wang*/
```

## ofsLoadValue

Loads the values of a byte array or a string array associated with a GUI control.

This statement only applies when the size of the byte array or string array > 0.

### Syntax

```
void ofsLoadValue(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const char *sValue);
```

## Return Value

## Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	Value of the item in the byte array or string array associated with a GUI control.

## Example

```
//In this example, value 7 is being added to the list of values in the array.
ofsLoadValue( "RUNFORM", 1, OFS_ENDMSG, 1, "7");
```

## ofsLOVRequestRow

Adds the LOV\_REQUEST\_ROW property to the current message. This statement defines an item in a List of Values control.

## Syntax

```
void ofsLOVRequestRow(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, int iPosX, int iPosY);
```

## Return Value

## Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current

	message.
iPropertyID	Oracle-designated ID for the property being added.
iPosX	X coordinate of the item in the LOV control. This corresponds to the row in the list of values.
iPosY	Y coordinate of the item in the LOV control.

### Example

```
//In this example, the position of an item in LOV control 85 is defined.
ofsLOVRequestRow( "LISTVALUESDIALOG", 85, OFS_ENDMSG, 451, 5, 1);
```

### ofsLOVSelection

Adds the LOV\_SELECTION property to the current message. This statement indicates an item being selected from a List of Values.

### Syntax

```
void ofsLOVSelection(const char *sHandlerName, int iControlID, int iAction, int iPropertyID,
const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	Relative position of the selected item in the List of Values control.

### Example

```
//In this example, item 1 from LOV control ID 264 is selected
ofsActivateWindow( "NAVIGATOR", 28, OFS_ENDMSG, 247 );
ofsLOVSelection( "LISTVALUESDIALOG", 264, OFS_ENDMSG, 450, "1" );
ofsSendRecv(1);
```

## ofsMenuParamDlgOK

Adds the `MENUPARAM_DLGOK` property to the current message. This statement defines the text in the menu param dialog control.

### Syntax

```
void ofsMenuParamDlgOK(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	The text value of the menu param dialog.

### Example

```
//In this example, dialog control ID 12 has a text title of "testButton".
OfsMenuParamDlgOK( "menu1", 12, OFS_ENDMSG, 16, "testbutton");
```

## ofsOpenWindow

Adds the `Window_Close` property (with `Disabled` attribute) to the current message. The statement indicates the act of opening a window.

### Syntax

```
void ofsOpenWindow(const char *sHandlerName, int ControlID, OFSActionTypeEnum ActionType, int PropertyID);
```

### Return Value

### Parameters

Parameter	Description
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.
ControlID	Captured ID of the GUI control for the current message.

ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						

**Example**

```
//In this example, control ID 52 (named
//"Sample Window") represents the window
//that is opened.
ofsOpenWindow ( "Sample Window", 52, OFS_ENDMSG, 216 );
```

**ofsRemoveFocus**

Adds the Focus property,with Disabled attribute, to the current message.

The RemoveFocus property typically indicates the mouse moving away from a GUI control.

**Syntax**

```
void ofsRemoveFocus(const char *sHandlerName, int ControlID, OFSActionTypeEnum ActionType,
int PropertyID);
```

**Return Value**

**Parameters**

Parameter	Description						
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.						
ControlID	Captured ID of the GUI control for the current message.						
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						

PropertyID	Oracle-designated ID for the property being added.
------------	--

### Example

```
//In this example, Focus is moved from control
//ID 77 (a Text Field) to control ID 78 (a button).
ofsRemoveFocus( "TEXTFIELD", 77, OFS_ENDMSG, 174 );
ofsFocus( "BUTTON", 78, OFS_ENDMSG, 174 );
ofsSendRecv(1 );
```

### ofsScroll

Adds the Block\_Scroller property to the current message. This statement indicates a scrolling activity.

#### Syntax

```
void ofsScroll(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const
char *sValue);
```

#### Return Value

#### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	The value associated with the scroll bar

### Example

```
ofsScroll( "RUNFORM", 1, OFS_ADD, 250, "2");
```

### ofsScrollSize

Adds the Block\_Scroller\_Size property to the current message. This statement indicates the block scroller size.

#### Syntax

```
ofsScrollSize(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const
char *sValue);
```

#### Return Value



## Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	The value associated with the scroll bar

## Example

```
ofsScrollSize( "RUNFORM", 1, OFS_ADD, 256, "12");
```

## ofsSelectItem

Adds the Value property (with Enabled attribute) to the current Message.

The Value property is applied to a Radio button, Checkbox, List Box or Combo Box control. This statement indicates an item associated with a Radio button, Checkbox, List Box or a Combo Box is being selected.

## Syntax

```
void ofsSelectItem(const char *sHandlerName, int ControlID, OFSActionTypeEnum ActionType, int PropertyID);
```

## Return Value

## Parameters

Parameter	Description				
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.				
ControlID	Captured ID of the GUI control for the current message.				
ActionType	<i>OFSActionTypeEnum</i>  This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:  <table border="0"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.
Value	Description				
OFS_ADD	Add the property to the current message.				

	OFS_ENDMSG	Add the property to the current message and end the current message.
PropertyID	Oracle-designated ID for the property being added.	

**Example**

```
//In this example, the mouse is deselecting Checkbox
//control ID 60 and selecting Radiobutton control ID 63.

ofsDeselectItem( "CHECKBOX", 60, OFS_ENDMSG, 131 );
ofsSendRecv(1 );

ofsRemoveFocus( "CHECKBOX", 60, OFS_ENDMSG, 174 );
ofsFocus( "RADIOBUTTON", 63, OFS_ENDMSG, 174 );
ofsSendRecv(1 );

ofsSelectItem( "RADIOBUTTON", 63, OFS_ENDMSG, 131 );
ofsSendRecv(1 );
```

**ofsSelectMenuItem**

Adds the Menu\_Event property to the current message. This statement indicates an item being selected from the Forms Event Menu.

**Syntax**

```
void ofsSelectMenuItem(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const char *sValue);
```

**Return Value**

**Parameters**

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
ControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
PropertyID	Oracle-designated ID for the property being added.
sValue	Value associated with the menu item.

**Example**

```
//In this example, a menu item valued 3 is selected. The menu item
//is associated with control ID 1 (Runform).

ofsSelectMenuItem( "RUNFORM", 1 , OFS_ADD, 477, "3");
```

## ofsSelectTreeEvent

Adds the Selected\_Event property of a Tree Control to the current message.

This statement indicates a Tree item being selected. The selected item is associated with an internal processing event.

### Syntax

```
void ofsSelectTreeEvent(const char *sHandlerName, int iControlID, int iAction, int
iPropertyID, const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
ControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
PropertyID	Oracle-designated ID for the property being added.
sValue	Relative position of the selected Tree item.

### Example

```
//In this example, the user selects item 2 of Tree control ID 15.
//Item 2 has an internal processing event.
ofsSelectTreeEvent( "TREE", 15, OFS_ADD, 488, 2);
```

## ofsSendRecv

Sends the client request as Forms messages to the Forms server, gets the server response, and reads the responses as Forms messages.

### Syntax

```
void ofsSendRecv(int iResponseCode);
```

### Return Value

### Parameters

Parameter	Description
iResponseCode	The response code associated with the client request's terminal message. (1=add, 2=update, 3=close).

### Example

```
//In this example, the messages sent to the server include a Text Field
//location attribute and a Window size attribute.

ofsSetSelection( "TEXTFIELD", 75, ofs_ENDMSG, 195, 0, 0);
ofsSetWindowSize( "FORMWINDOW", 6, ofs_ENDMSG, 137, 1024, 768);
ofsSendRecv(1 );
```

### ofsServerSideDisconnect

Disconnects QALoad's socket connection to the server-side code.

The server-side code intercepts the messages between QALoad and the Forms Listener servlet.

#### Syntax

```
void ofsServerSideDisconnect();
```

#### Return Value

#### Parameters

None

#### Example

```
ofsServerSideDisconnect();
```

### ofsSetColorDepth

Adds the Color\_Depth property to the current message.

The Color\_Depth property is applied to the initial Forms environment.

#### Syntax

```
void ofsSetColorDepth(const char *sClassName, int iHandlerID, int iAction, int iPropertyID,
const char *sColorDepth);
```

#### Return Value

#### Parameters

Parameter	Description
sClassName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iHandlerID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  ofs_ADD: Add the property to the current message. ofs_ENDMSG: Add property to the current message and end the current message.

iPropertyID	Oracle-designated ID for the property being added.
sColorDepth	Value associated with the color depth.

### Example

```
ofsSetColorDepth( "RUNFORM", 1, OFS_ADD, 266, "256" );
```

## ofsSetCursorPosition

Adds the Cursor\_Position property of a Text Field control to the current message.

The Cursor\_Position property indicates the relative position of the cursor in the Text Field control at the time of user entry.

### Syntax

```
void ofsSetCursorPosition(const char *sHandlerName, int iControlId, int iAction, int iPropertyID, const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	Relative position of the cursor in the Text Field control at the time of user entry.

### Example

```
//In this example, the cursor is positioned on the 7th character.  
ofsSetCursorPosition( "TEXTFIELD", 77, OFS_ENDMSG, 193, "7" );
```

## ofsSetDisplaySize

Adds the Display\_Size property to the current message.

The Display\_Size property is applied to the initial Forms environment.

## Language Reference Commands

### Syntax

```
void ofsSetDisplaySize(const char *sClassName, int iHandlerID, int iAction, int iPropertyID, int iCoordinateX, int iCoordinateY);
```

### Return Value

### Parameters

Parameter	Description
sClassName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iHandlerID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
iCoordinateX	X coordinate of the canvas display.
iCoordinateY	Y coordinate of the canvas display.

### Example

```
ofsSetDisplaySize( "RUNFORM", 1, OFS_ADD, 264, 1024, 768);
```

## ofsSetErrorDialogTitle

Adds the DISPLAYERRORDIALOG\_TITLE property to the current message. This statement defines the text title associated with the Display Error Dialog control.

### Syntax

```
void ofsSetErrorDialogTitle(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.

	OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	Text title associated with the Error Dialog control.

### Example

```
//In this example, the text title of error dialog control ID 12 is defined as "TestErr1".
ofsSetErrorDialogTitle( "ERRDLG1", 12, OFS_ADD, 129, "TestErr1");
```

### ofsSetExpectedServerMsg

Enables the script to continue if a known error or warning message is received from the server.

It is positioned before the ofsSendRecv statement, which checks the server reply messages. If error message checking is enabled and the server message contains "FRM-", "ORA-" or "APP-", ofsSendRecv throws an exception unless it is preceded by ofsSetExpectedServerMsg.

This is a keyword search. You can broaden the search to include more than one specific transaction by modifying the Expected Server Message parameter to look for part of a string.

### Syntax

```
void ofsSetExpectedServerMsg(const char *ExpectedServerMessage);
```

### Return Value

### Parameters

Parameter	Description
ExpectedServerMessage	The expected server message.

### Example

```
//Before sending the request to the server with the statement ofsSendRecv,
//QALoad stores the expected message from the server reply,
//so that Playback would ignore the server message and continue execution.
.
.
.
ofsSelectMenuItem( "WINDOW_START_APP", 11, OFS_ENDMSG, 477, "MENU_77" );
ofsSetExpectedServerMsg("FRM-41003: This function cannot be performed here.");
ofsSendRecv(1 );
```

### ofsSetFontName

Adds the Font\_Name property to the current message.

The Font\_Name property is applied to the initial Forms environment.

### Syntax

```
void ofsSetFontName(const char *sClassName, int iHandlerID, int iAction, int iPropertyID,
const char *sFontName);
```

## Return Value

## Parameters

Parameter	Description
sClassName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iHandlerID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sFontName	Name of the font to use.

## Example

```
ofsSetFontName( "RUNFORM", 1, OFS_ADD, 383, "Dialog" );
```

## ofsSetFont Size

Adds the Font\_Name property to the current message.

The Font\_Name property is applied to the initial Forms environment.

## Syntax

```
void ofsSetFontName(const char *sClassName, int iHandlerID, int iAction, int iPropertyID, const char *sFontName);
```

## Return Value

## Parameters

Parameter	Description
sClassName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iHandlerID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.



iPropertyID	Oracle-designated ID for the property being added.
sFontName	The size of the font to use.

### Example

```
ofsSetFontSize( "RUNFORM", 1, OFS_ADD, 377, "900" );
```

## ofsSetFontStyle

Adds the Font\_Style property to the current message.

The Font\_Style property is applied to the initial Forms environment.

### Syntax

```
void ofsSetFontStyle(const char *sHandlerName, int iControlId, int iAction, int iPropertyID,
const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sClassName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iHandlerID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sFontName	The style of the font to use.

### Example

```
ofsSetFontStyle( "RUNFORM", 1, OFS_ADD, 378, "0" );
```

## ofsSetFontWeight

Adds the Font\_Weight property to the current message.

The Font\_Weight property is applied to the initial Forms environment.

### Syntax

```
void ofsSetFontWeight(const char *sHandlerName, int iControlId, int iAction, int
iPropertyID, const char *sValue);
```

### Return Value

## Parameters

Parameter	Description
sClassName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iHandlerID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sFontName	The font weight to use.

## Example

```
ofsSetFontWeight( "RUNFORM", 1, OFS_ADD, 379, "0" );
```

## ofsSetICXTicket

Sets the value of the ICX ticket for the current Oracle Applications login.

The statement is used only in a Universal OFS-WWW session, as a replacement for the OracleAppsLogin statement. The statement is manually added to the script, along with the WWW statement DO\_GetUniqueString. For more information, see OFS and WWW Universal Sessions in OFS Advanced Scripting Techniques.

 **Note:** The memory buffer allocated by ofsSetICXTicket needs to be explicitly freed.

## Syntax

```
ofsSetICXTicket( char **cookieValue);
```

## Return Value

## Parameters

Parameter	Description
cookieValue	Address to a string where the cookie value is stored.

## Example

```
...
/* Declare Variables */
...
char *p;
char ICX_Ticket[100];
char *pTicket;
...
...
```

```

BEGIN_TRANSACTION();

...
...

// This statement should be added after the rquest line that returns the ICX ticket
p = DO_GetUniqueString( "icx_ticket=", "" );
strcpy( ICX_Ticket, p );
pTicket=ICX_Ticket;

// Verify the ICX ticket value
RR_printf("ICX_Ticket=\"%s\"\n", ICX_Ticket);

// The ofsSetICXTicket statement passes the ICX ticket value to the
ofsInitiSessionCmdLine statement
ofsSetICXTicket(&pTicket);

// Free the memory allocated by DO_GetUniqueString and ofsSetICXTicket before the end of
the transaction.
free(p);
p=NULL;
free(pTicket);
pTicket=NULL;

END_TRANSACTION()

```

## ofsSetInitialVersion

Adds the Initial\_Version property to the current message.

The Initial\_Version property is applied to the initial Forms environment.

### Syntax

```
void ofsSetInitialVersion(const char *sClassName, int iHandlerID, OFSActionTypeEnum iAction,
int iPropertyID, OFSFormsVersionEnum sFormsVersion);
```

### Return Value

### Parameters

Parameter	Description						
sClassName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.						
iHandlerID	Captured ID of the GUI control for the current message.						
iAction	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
iPropertyID	Oracle-designated ID for the property being added.						

sFormsVersion	The Forms Version of the captured application, represented as an integer string.
---------------	--

### Example

```
ofsSetInitialVersion( "RUNFORM", 1, OFS_ADD, 268, "101200" );
```

## ofsSetJavaContainerArgName

Adds the JAVACONTAINER\_ARG\_NAME property to the current message.

This statement defines the name assigned to an item in a JavaContainer control.

### Syntax

```
void ofsSetJavaContainerArgName(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sClassName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iHandlerID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	Name assigned to a JavaContainer control item.

### Example

```
ofsSetJavaContainerArgName("Test_App", 15, OFS_ADD, 400, "TestBeanItem");
```

## ofsSetJavaContainerArgValue

Adds the JAVACONTAINER\_ARG\_VALUE property to the current message.

This statement defines the value entered by the user in a JavaContainer control item.

### Syntax

```
void ofsSetJavaContainerArgValue(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const char *sValue);
```

## Return Value

## Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	The value entered by the user in a JavaContainer control item.

## Example

```
ofsSetJavaContainerArgValue("Test_App", 15, OFS_ADD, 401, "BeanEntry1");
```

## ofsSetJavaContainerEvent

Adds the JAVACONTAINER\_ARG\_EVENT property to the current message.

This statement defines the name assigned to a JavaContainer control.

## Syntax

```
void ofsSetJavaContainerEvent(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const char *sValue);
```

## Return Value

## Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.

iPropertyID	Oracle-designated ID for the property being added.
sValue	Name assigned to the JavaContainer control.

**Example**

```
ofsSetJavaContainerEvent("Test_App", 15, OFS_ADD, 399, "TestEvent1");
```

**ofsSetLogonDatabase**

Adds the LOGON\_DATABASE property to the current message. This statement defines the connect string entry in the Forms Logon dialog.

**Syntax**

```
void ofsSetLogonDatabase(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const char *sValue);
```

**Return Value**

**Parameters**

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	The logon database for this session.

**Example**

```
ofsSetLogonDatabase( "Logon", 34, OFS_ENDMSG, 435, "iasdb" );
```

**ofsSetLogonPassWord**

Adds the LOGON\_PASSWORD property to the current message. This statement defines the password entry in the Forms Logon dialog.

**Syntax**

```
void ofsSetLogonPassWord(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const char *sValue);
```

**Parameters**

Parameter	Description
-----------	-------------

sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	The password for this session.

### Example

```
ofsSetLogonPassWord( "Logon", 34, OFS_ADD, 434, "tiger" );
```

### ofsSetLogonUserName

Adds the LOGON\_USERNAME property to the current message.

This statement defines the user name entry in the Forms Logon dialog.

### Syntax

```
void ofsSetLogonUserName(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	The user name to use for this session.

### Example

```
ofsSetLogonUserName( "Logon", 34, OFS_ADD, 433, "scott" );
```

## ofsSetNoRequiredVAList

Adds the Required\_VA\_List property (with Disabled attribute) to the current message.

The Required\_VA\_List property is applied to the initial Forms environment.

### Syntax

```
void ofsSetNoRequiredVAList(const char *sHandlerName, int ControlID, OFSActionTypeEnum
ActionType, int PropertyID);
```

### Return Value

### Parameters

Parameter	Description						
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.						
ControlID	Captured ID of the GUI control for the current message.						
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						

### Example

```
//The initial set of Forms statements describes
//the initial Forms environment. The description
//is matched on the server side.

ofsSetInitialVersion( "RUNFORM", 1, OFS_ADD, 268, "60818" );
ofsSetScreenResolution( "RUNFORM", 1, OFS_ADD, 263, 96, 96);

.
.
.

ofsSetNoRequiredVAList( "RUNFORM", 1, OFS_ADD, 291 );

.
.
.

ofsInitSessionTimeZone( "RUNFORM", 1, OFS_ENDMSG, 527, "EST" );
ofsSendRecv(1 );
```

## ofsSetPropertyBoolean

Adds the generic boolean property (with Enabled attribute) to the current message.



Use this statement when the boolean property is not known to QALoad.

### Syntax

```
void ofsSetPropertyBoolean(const char *sHandlerName, int iControlID, int iAction, int iPropertyID);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.

### Example

```
//In this example, property 381 is of Boolean type, and is associated with Tree control ID 73.
```

```
ofsSetPropertyBoolean("TREE", 73, OFS_ENDMSG, 381);
```

## ofsSetPropertyByte

Adds the generic byte property to the current message.

This statement is used when the byte property is not known to QALoad.

### Syntax

```
void ofsSetPropertyByte(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special

	processing. OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	Value associated with the byte property.

### Example

```
//In this example, property 186 is of type Byte, and is associated with Tree control ID 73.
ofsSetPropertyByte( "TREE", 73, OFS_ENDMSG, 186, "16" );
```

## ofsSetPropertyByteArray

Adds the generic byte array property to the current message.

This statement is used when the byte array property is not known to QALoad.

### Syntax

```
void ofsSetPropertyByteArray(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	Size of the byte array.

### Example

```
//In this example, property 382 is of Byte Array type, and is associated with Tree control ID 73.
ofsSetPropertyByteArray( "TREE", 73, OFS_ENDMSG, 382, "0" );
```

## ofsSetPropertyCharacter

Adds the generic Character property to the current message.

This statement is used when the Character property is not known to QALoad.

### Syntax

```
void ofsSetPropertyCharacter(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	Value associated with the Character property.

### Example

//In this example, property 383 is of Character type, and is associated with Tree control ID 73.

```
ofsSetPropertyCharacter("TREE", 73, OFS_ADD, 383, "20");
```

## ofsSetPropertyDate

Adds the generic Date property to the current message.

This statement is used when the Date property is not known to QALoad.

### Syntax

```
void ofsSetPropertyDate(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.

iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	Value associated with the Date property.

### Example

```
//In this example, property 383 is of Date type, and is associated with Tree control ID 73.
ofsSetPropertyDate( "TREE", 73, OFS_ADD, 383, "2000-02-22");
```

## ofsSetPropertyFloat

Adds the generic Float property to the current message.

This statement is used when the Float property is not known to QALoad.

### Syntax

```
void ofsSetPropertyFloat(const char *sHandlerName, int iControlID, int iAction, int
iPropertyID, const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	Value associated with the Float property.

### Example

```
//In this example, property 383 is of Float type, and is associated with Tree Control ID 73.
ofsSetPropertyFloat( "TREE", 73, OFS_ADD, 383, "2000.0222");
```

## ofsSetPropertyInteger

Adds the generic Integer property to the current message.

This statement is used when the Integer property is not known to QALoad.

### Syntax

```
void ofsSetPropertyInteger(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	Value associated with the Integer property.

### Example

//In this example, property 383 is of Integer type, and is associated with Tree control ID 73.

```
ofsSetPropertyInteger( "TREE", 73, OFS_ADD, 383, "20");
```

## ofsSetPropertyPoint

Adds the generic Point property to the current message.

This statement is used when the Point property is not known to QALoad.

### Syntax

```
void ofsSetPropertyPoint(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, int iCoordinateX, int iCoordinateY);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.

iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
iCoordinateX	X coordinate value of the Point property.
iCoordinateY	Y coordinate value of the Point property.

### Example

```
//In this example, property 185 is of Point type, and is associated with Tree control ID 73.
ofsSetPropertyPoint( "TREE", 73, OFS_ADD, 185, 30, 50);
```

### ofsSetPropertyRectangle

Adds the generic Rectangle property to the current message.

This statement is used when the Rectangle property is not known to QALoad.

### Syntax

```
void ofsSetPropertyRectangle(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, int iXval, int iYval, int iWval, int iHval);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
iXval	X value of the rectangle.
iYval	Y value of the rectangle.
iWval	Width of the rectangle.

iHval	Height value of the rectangle.
-------	--------------------------------

### Example

```
//In this example, property 155 is of type Rectangle, and is associated with Control ID 73
//(named "Button").
ofsSetPropertyRectangle( "BUTTON", 73, OFS_ADD, 155, 0, 0, 106, 29);
```

## ofsSetPropertyString

Adds the generic **String** property to the current message.

This statement is used when the **String** property is not known to QALoad.

### Syntax

```
void ofsSetPropertyString(const char *sHandlerName, int iControlID, int iAction, int
iPropertyID, const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	Value associated with the <b>String</b> property.

### Example

```
//In this example, property 520 is of String type, and is associated with control ID 1
(RunForm).
ofsSetPropertyString( "RUNFORM", 1, OFS_ENDMSG, 530, "America/New_York" );
```

## ofsSetPropertyStringArray

Adds the generic **String** array property to the current message.

This statement is used when the **String** array property is not known to QALoad.

Syntax

```
void ofsSetPropertyStringArray(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const char *sValue);
```

Return Value

Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	Size of the String array.

Example

```
//In this example, property 382 with size 0 is of type String Array.  
//The property is associated with Tree control ID 73.  
ofsSetPropertyStringArray( "TREE", 73, OFS_ENDMSG, 382, "0" );
```

ofsSetPropertyVoid

Adds the generic Void property to the current message.

This statement is used when the Void property is not known to QALoad.

Syntax

```
void ofsSetPropertyVoid(const char *sHandlerName, int iControlID, int iAction, int iPropertyID);
```

Return Value

Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special



	<p>processing.</p> <p>OFS_ADD: Add the property to the current message.</p> <p>OFS_ENDMSG: Add property to the current message and end the current message.</p>
iPropertyID	Oracle-designated ID for the property being added.

### Example

```
//In this example, property 382 is of Void type and is associated with Tree control ID 73.
ofsSetPropertyVoid( "TREE", 73, OFS_ENDMSG, 382 );
```

## ofsSetRequiredVAList

Adds the Required\_VA\_List property (with Enabled attribute) to the current message.

The Required\_VA\_List property is applied to the initial Forms environment.

### Syntax

```
void ofsSetRequiredVAList(const char *HandlerName, int ControlID, OFSActionTypeEnum
ActionType, int PropertyID);
```

### Return Value

### Parameters

Parameter	Description						
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.						
ControlID	Captured ID of the GUI control for the current message.						
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						

### Example

```
//The initial set of Forms statements describes
//the initial Forms environment. The description
//is matched on the server side.
```

## Language Reference Commands

```
ofsSetInitialVersion( "RUNFORM", 1, OFS_ADD, 268, "90290" );
ofsSetScreenResolution( "RUNFORM", 1, OFS_ADD, 263, 96, 96);
.
.
.
ofsSetRequiredVAList( "RUNFORM", 1, OFS_ADD, 291 );
.
.
.
ofsFocus( "BUTTON", 58, OFS_ENDMSG, 174 );
ofsSendRecv(1 );
```

## ofsSetRunOptions

Sets the runtime values for `Connect_Type`, `Heartbeat`, and `Check_Server_Messages`.

### Syntax

```
void ofsSetRunOptions( OFSFormsVersionEnum sFormsVersion, OFSConnectionTypeEnum
iConnectType, int iHeartbeatInterval, OFSMessageCheckingEnum iCheckServerMsgs);
```

### Return Value

### Parameters

Parameter	Description														
<code>sFormsVersion</code>	<p><i>OFSFormsVersionEnum</i></p> <p>Version of Oracle Forms in use. Valid values are:</p> <table><thead><tr><th>Value</th><th>Description</th></tr></thead><tbody><tr><td><code>FORMS_10g_SERVLET</code></td><td>Oracle Application Server 10g</td></tr><tr><td><code>FORMS_9i_SERVLET</code></td><td>Oracle Application Server 9i</td></tr><tr><td><code>FORMS_6i_SERVLET</code></td><td>Oracle Forms 6i Servlet Mode</td></tr><tr><td><code>FORMS_6i_11i_SERVLET</code></td><td>Oracle Forms 6i in 11i Environment</td></tr><tr><td><code>FORMS_6i_SOCKET</code></td><td>Oracle Forms 6i Socket Mode</td></tr><tr><td><code>FORMS_60_SOCKET</code></td><td>Oracle Forms 6.0</td></tr></tbody></table>	Value	Description	<code>FORMS_10g_SERVLET</code>	Oracle Application Server 10g	<code>FORMS_9i_SERVLET</code>	Oracle Application Server 9i	<code>FORMS_6i_SERVLET</code>	Oracle Forms 6i Servlet Mode	<code>FORMS_6i_11i_SERVLET</code>	Oracle Forms 6i in 11i Environment	<code>FORMS_6i_SOCKET</code>	Oracle Forms 6i Socket Mode	<code>FORMS_60_SOCKET</code>	Oracle Forms 6.0
Value	Description														
<code>FORMS_10g_SERVLET</code>	Oracle Application Server 10g														
<code>FORMS_9i_SERVLET</code>	Oracle Application Server 9i														
<code>FORMS_6i_SERVLET</code>	Oracle Forms 6i Servlet Mode														
<code>FORMS_6i_11i_SERVLET</code>	Oracle Forms 6i in 11i Environment														
<code>FORMS_6i_SOCKET</code>	Oracle Forms 6i Socket Mode														
<code>FORMS_60_SOCKET</code>	Oracle Forms 6.0														
<code>iConnectType</code>	<p><i>OFSConnectionTypeEnum</i></p> <p>This flag indicates the type of connection to establish with the server. Valid values are:</p> <table><thead><tr><th>Value</th><th>Description</th></tr></thead><tbody><tr><td><code>OFS_SOCKET</code></td><td>Socket connection</td></tr><tr><td><code>OFS_HTTP</code></td><td>HTTP connection</td></tr></tbody></table>	Value	Description	<code>OFS_SOCKET</code>	Socket connection	<code>OFS_HTTP</code>	HTTP connection								
Value	Description														
<code>OFS_SOCKET</code>	Socket connection														
<code>OFS_HTTP</code>	HTTP connection														

	OFS_HTTPS	Secure (SSL) connection						
iHeartbeatInterval	Heartbeat interval (minutes).							
iCheckServerMsgs	<p><i>OFSMessageCheckingEnum</i></p> <p>This flag indicates whether QALoad checks server messages. If server message checking is enabled, the script fails if the server sends a message ("FRM-", "ORA-", "APP-") unless the message is set as an expected message (see <code>ofsSetExpectedServerMsg()</code>). In addition, <code>ofsSetServerFailedMsg()</code> overrides the expected message if the message matches the failed message. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_DONTCHECKMSGS</td> <td>Disable error message checking for server messages.</td> </tr> <tr> <td>OFS_CHECKMSGs</td> <td>Enable error message checking for server messages.</td> </tr> </tbody> </table>		Value	Description	OFS_DONTCHECKMSGS	Disable error message checking for server messages.	OFS_CHECKMSGs	Enable error message checking for server messages.
Value	Description							
OFS_DONTCHECKMSGS	Disable error message checking for server messages.							
OFS_CHECKMSGs	Enable error message checking for server messages.							

### Example

```
ofsSetRunOptions( "6i", OFS_SOCKET, 4, OFS_CHECKMSGs );
```

### ofsSetScaleInfo

Adds the Scale property to the current message.

The Scale property is applied to the initial Forms environment.

### Syntax

```
void ofsSetScaleInfo(const char *sClassName, int iHandlerID, int iAction, int iPropertyID, int iCoordinateX, int iCoordinateY);
```

### Return Value

### Parameters

Parameter	Description
sClassName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.
iHandlerID	Captured ID of the GUI control for the current message.
iAction	<p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.</p> <p>OFS_ADD: Add the property to the current message.  OFS_ENDMSG: Add property to the current message and end the current message.</p>
iPropertyID	Oracle-designated ID for the property being added.

iCoordinateX	X coordinate associated with scale property.
iCoordinateY	Y coordinate associated with scale property.

**Example**

```
ofsSetScaleInfo( "RUNFORM", 1, OFS_ADD, 267, 11, 18);
```

**ofsSetScreenResolution**

Adds the Screen Resolution property to the current message.

The Screen Resolution property is applied to the initial Forms environment.

**Syntax**

```
void ofsSetScreenResolution(const char *sClassName, int iHandlerID, int iAction, int iPropertyID, int iCoordinateX, int iCoordinateY);
```

**Return Value**

**Parameters**

Parameter	Description
sClassName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.
iHandlerID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
iCoordinateX	X coordinate associated with the property.
iCoordinateY	Y coordinate associated with the property.

**Example**

```
ofsSetScreenResolution( "RUNFORM", 1, OFS_ADD, 263, 96, 96);
```

**ofsSetSelection**

Adds the Selection property of a Text Field control to the current message.

This statement indicates the selected Text Field location during user entry.

**Syntax**

```
void ofsSetSelection(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, int iCoordinateX, int iCoordinateY);
```

## Return Value

## Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
iCoordinateX	X coordinate of the text field entry.
iCoordinateY	Y coordinate of the text field entry.

## Example

```
ofsSetSelection( "TEXTFIELD", 75, OFS_ADD, 195, 0, 0);
ofsSetCursorPosition( "TEXTFIELD", 75, OFS_ENDMSG, 193, "0" );
ofsSetWindowLocation( "Oracle Applications", 32, OFS_ENDMSG, 135, 231, 218);
ofsShowWindow( "Oracle Applications", 32, OFS_ENDMSG, 173 );
ofsActivateWindow( "Oracle Applications", 32, OFS_ENDMSG, 247 );
ofsFocus( "TEXTFIELD", 75, OFS_ENDMSG, 174 );
ofsSendRecv(2 );
```

## ofsSetServerFailedMsg

Enables QALoad to fail playback based on the user-entered string and filter parameters.

This statement overrides the effects of the ofsSetExpectedMsg statement, which enables QALoad to continue playback if FRM-, ORA- or APP- server messages are encountered.

## Syntax

```
void ofsSetServerFailedMsg(const char *sMsgString, OFSServerMessageComparisonTypeEnum iMsgOption);
```

## Return Value

## Parameters

Parameter	Description
sMsgString	String to compare against server message.
iMsgOption	<i>OFSServerMessageComparisonTypeEnum</i>  This flag indicates the string comparison method to use for comparing a

	string against a server message. Valid values are:	
	Value	Description
	OFS_KEYWORD	Search for string anywhere in server message.
	OFS_PREFIX	Compare string against beginning of the message.
	OFS_SUFFIX	Compare string against end of the message.
	OFS_ENTIRE_MSG	Compare string against entire message.

### Example

```
ofsSetServerFailedMsg( "FRM-4041", OFS_KEYWORD );
:
ofsSetExpectedMsg("FRM-4041").;
ofsSendRecv(1);
```

### ofsSetServletMode

Creates a socket connection to the server-side code which communicates with the Forms Listener Servlet. The server-side code intercepts messages between QALoad and the servlet during a server-side connection.

#### Syntax

```
void ofsSetServletMode(int iConnectMode, const char *sServletName);
```

#### Return Value

#### Parameters

Parameter	Description
iConnectMode	Connection mode.
sServletName	The listener servlet name.

### Example

```
ofsSetServletMode(OFS_HTTP, "http://ntsap45b:7779/forms90/190servlet" );
```

### ofsSetWindowLocation

Adds the Location property of a Window control to the current message.

This statement defines the window location in the canvas.

#### Syntax

```
void ofsSetWindowLocation(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, int iPosX, int iPosY);
```

#### Return Value

## Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
iPosX	X coordinate of the window control.
iPosY	Y coordinate of the window control.

## Example

```
ofsSetWindowLocation( "FORMWINDOW", 6, OFS_ENDMSG, 135, 0, 0);
ofsSetWindowSize( "FORMWINDOW", 6, OFS_ENDMSG, 137, 650, 500);
ofsSetWindowSize( "FORMWINDOW", 6, OFS_ENDMSG, 137, 650, 500);
ofsSendRecv(1 );
```

## ofsSetValue

Adds a generic Value property to the current message.

## Syntax

```
void ofsSetValue(const char *sHandlerName, int iControlID, int iAction, int iPropertyID,
const char *sValue);
```

## Return Value

## Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the class name of the control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.

sValue	Value associated with the property.
--------	-------------------------------------

**Example**

```
//In this example, a value of "30" is being associated with control ID 1 "RUNFORM"
ofsSetValue( "RUNFORM", 1, OFS_ADD, 131, "30");
```

**ofsSetWindowSize**

Adds the Size property of a Window control to the current message. This statement indicates a window being resized.

**Syntax**

```
void ofsSetWindowSize(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, int iPosX, int iPosY);
```

**Return Value**

**Parameters**

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing.  OFS_ADD: Add the property to the current message. OFS_ENDMSG: Add property to the current message and end the current message.
iPropertyID	Oracle-designated ID for the property being added.
iPosX	Width of the window control.
iPosY	Length of the window control.

**Example**

```
ofsSetWindowSize( "FORMWINDOW", 6, OFS_ENDMSG, 137, 650, 500);
ofsSendRecv(1 );
```

**ofsShowWindow**

Adds the Visible property (with Enabled attribute) to the current message.

The property is associated with a Window control. The statement indicates a window being displayed in front of all other windows.

**Syntax**

```
void ofsShowWindow(const char *sHandlerName, int ControlID, OFSActionTypeEnum ActionType, int PropertyID);
```



## Return Value

## Parameters

Parameter	Description						
HandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.						
ControlID	Captured ID of the GUI control for the current message.						
ActionType	<p><i>OFSActionTypeEnum</i></p> <p>This flag indicates if the property is only to be added to the current message or if it also ends the current message. The end of a message requires special processing. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OFS_ADD</td> <td>Add the property to the current message.</td> </tr> <tr> <td>OFS_ENDMSG</td> <td>Add the property to the current message and end the current message.</td> </tr> </tbody> </table>	Value	Description	OFS_ADD	Add the property to the current message.	OFS_ENDMSG	Add the property to the current message and end the current message.
Value	Description						
OFS_ADD	Add the property to the current message.						
OFS_ENDMSG	Add the property to the current message and end the current message.						
PropertyID	Oracle-designated ID for the property being added.						

## Example

```
//In this example, window control ID 118 is
//being displayed in front of all other windows.
ofsShowWindow( "FORMWINDOW", 118, OFS_ENDMSG, 173 );
```

## ofsSocketDisconnect

Closes the connection of a socket-mode playback.

### Syntax

```
void ofsSocketDisconnect();
```

### Return Value

### Parameters

None

### Example

```
ofsSocketDisconnect();
```

## ofsStartSubMessage

Adds a sub-message to the current message. A sub-message is a message nested inside another message.

## Language Reference Commands

### Syntax

```
void ofsStartSubMessage(const char *sHandlerName, int iHandlerID, int iAction, int iPropertyID, const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.
iHandlerID	Captured ID of the GUI control for the current message.
iAction	Action type. Adds the property of the succeeding nested message to the current message.
iPropertyID	Oracle-designated ID for the property being added.
sValue	Value associated with the parent message.

### Example

```
ofsStartSubMessage( "TREE", 73, OFS_STARTSUBMSG, 505, "0" );
ofsDefineTreeNode( "TREE", 73, OFS_ADD, 500, "6" ); /*Item value = BLAKE*/
ofsDefineTreeNodeOffset( "TREE", 73, OFS_ENDMSG, 503, "2" );
ofsStartSubMessage( "TREE", 73, OFS_STARTSUBMSG, 505, "0" );
ofsDefineTreeNode( "TREE", 73, OFS_ADD, 500, "6" ); /*Item value = BLAKE*/
ofsDefineTreeNodeOffset( "TREE", 73, OFS_ENDMSG, 503, "3" );
ofsStartSubMessage( "TREE", 73, OFS_STARTSUBMSG, 505, "0" );
ofsDefineTreeNode( "TREE", 73, OFS_ADD, 500, "12" ); /*Item value = CLARK*/
ofsDefineTreeNodeOffset( "TREE", 73, OFS_ENDMSG, 503, "0" );

ofsSendRecv(1 );
```

## ofsTabControlTopPage

Adds the TabControl\_Top\_Page property to the current message.

### Syntax

```
void ofsTabControlTopPage(const char *sHandlerName, int iControlID, int iAction, int iPropertyID, const char *sValue);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	Action type. Adds the property of the succeeding nested message to the current message.

iPropertyID	Oracle-designated ID for the property being added.
sValue	Value associated with the Tab Control.

### Example

```
ofsTabControlTopPage( "RUNFORM", 1, OFS_ENDMSG, 411, "30");
```

## ofsUnSetPropertyBoolean

Adds a generic Boolean property (with Disabled attribute) to the current message.

This statement is used when the property is not known to QALoad.

### Syntax

```
void ofsUnSetPropertyBoolean(const char *sHandlerName, int iControlID, int iAction, int iPropertyID);
```

### Return Value

### Parameters

Parameter	Description
sHandlerName	Captured name of the control ID for the current message. When the control name is not available, the Class name of the Control ID is shown.
iControlID	Captured ID of the GUI control for the current message.
iAction	Action type. Adds the property of the succeeding nested message to the current message.
iPropertyID	Oracle-designated ID for the property being added.

### Example

```
//In this example, property 382 is of Boolean type,  
//and is associated with control ID 1 (Runform).  
ofsUnSetPropertyBoolean( "RUNFORM", 1, OFS_ADD, 382);
```

## ofsWindowCreated

Check if the specified window was created during the last transaction with the server (ofsSendRecv).

### Syntax

```
int ofsWindowCreated(int iControlID, char *sControlName);
```

### Return Value

TRUE if the window was created, FALSE otherwise

### Parameters

Parameter	Description
iControlID	Captured ID of the GUI control for the current message.

sControlName	Name of the control.
--------------	----------------------

### Example

```
ofsSendRecv(1);  
ofsWindowCreated(710, "Account information");
```

## QALoad

### QALoad Common Commands

#### BEGIN\_TRANSACTION

Defines the beginning of the script's transaction loop.

#### BeginCheckpoint

Marks the beginning of a checkpoint.

#### CLOSE\_ALL\_DATA\_POOLS

Closes all open local datapool files.

#### CLOSE\_DATA\_POOL

Closes the specified local datapool file.

#### COUNTER\_VALUE

This command is used to update or increment the values of custom counters defined using the DEFINE\_COUNTER command. As counter values are written to the timing file, they are time stamped with the elapsed time.

#### DATE\_TIME

Gets the current time and/or date from the local machine.

#### DefaultCheckpointsOn

QALoad automatically adds this command when the Include Default Checkpoint statements convert option is selected in Workbench. When this command is found in a QALoad script, QALoad will not automatically generate checkpoints inside the middleware when Auto Timings is enabled in the QALoad Conductor. Instead, QALoad uses checkpoint statements found within the QALoad script.

#### DEFINE\_COUNTER

Use the DEFINE\_COUNTER command to define custom counters. Custom counters are written and managed on a per user basis. They will be saved to the timing file and can be graphed in Analyze. Counter data types can be either signed longs or floats. The counter type can be either cumulative or instance (which tells Analyze how to graph the counter.) Works in conjunction with the COUNTER\_VALUE command.

#### DEFINE\_TRANS\_TYPE

Associates a description for the transaction loop displayed in QALoad Analyze.

#### DO\_AbortOnError

Enables or disables error handling in the script.

#### DO\_ExtractString

Finds a sub-string in a null-terminated buffer.

#### [DO\\_MSLEEP](#)

Inserts a sleep for the number of seconds defined in the parameter.

#### [DO\\_SetTransactionClean up](#)

Defines a point at the end of the transaction for anything that needs to be de-allocated or uninitialized. When transaction restarting occurs for a failed transaction, QALoad will first execute any code starting after the call to `DO_SetTransactionClean up` allowing you to clean up important information and prevent memory leaks before retrying the transaction.

#### [DO\\_SetTransactionStart](#)

Defines a point at the beginning of the transaction loop that QALoad uses to rewind the transaction if the transaction fails and Restart Transaction error handling is selected in the QALoad Conductor.

#### [DO\\_SetValue](#)

Associates a value to a variable name. Variable names are embedded into parameter strings of QALoad functions and the value is interpolated at replay. Currently, `DO_Http` and `DO_Https` are the only functions that interpolate the variables.

#### [DO\\_SLEEP](#)

Inserts a sleep for the number of seconds defined in the parameter.

#### [END\\_TRANSACTION](#)

This command marks the end of the transaction loop.

#### [EndCheckpoint](#)

Indicates the end of a checkpoint, corresponding to a `BeginCheckpoint` command.

#### [EXIT](#)

Stops script processing and returns control back to the Conductor.

#### [GET\\_ABSOLUTE\\_VUNUM](#)

Gets the absolute virtual user number.

#### [GET\\_DATA](#)

Requests that QALoad Conductor send the next datapool record to the script.

#### [GET\\_DATA\\_FIELD](#)

Accesses the fields from the data record that was just read using the `READ_DATA_RECORD` statement. Field numbering starts at 1.

#### [GET\\_DATAPOOLES\\_DIR](#)

Retrieves the name of the QALoad Datapools directory.

#### [GET\\_HOME\\_DIR](#)

Retrieves the name of the QALoad installation directory.

#### [GET\\_LOGFILES\\_DIR](#)

Retrieves the name of the QALoad LogFiles directory.

#### [GET\\_RELATIVE\\_VUNUM](#)

Gets the relative virtual user number.

#### [GET\\_SCRIPTS\\_DIR](#)

## Language Reference Commands

Retrieves the name of the QALoad Scripts directory.

### GET\_TIMINGFILES\_DIR

Retrieves the name of the QALoad Timing Files directory.

### LOG\_ERROR

Sends the corresponding message to the Conductor, so that it can be displayed within the [Player Messages](#) window in the Conductor.

### Modify\_Encoding

Modifies the encoding for a string parameter.

### OctalToChar

Converts any octal escape sequences to binary. Octal sequences consist of a backslash followed by two digits. This can be useful for adding binary data to a datapool file in the form of octal escape sequences since datapool files must contain only ASCII strings. For example:

### OPEN\_DATA\_POOL

Opens the datapool file.

### RANDOM\_NUMBER

Returns a string representation of a random number.

### RANDOM\_STRING

Returns a string with a random set of alpha or alphanumeric characters of the specified width.

### READ\_DATA\_RECORD

Reads a data record from a local datapool file.

### RND\_DELAY

Delays the script for a random interval before proceeding.

### RND\_DELAY\_RANGE

Delays the script for a random interval, within a specified range, before proceeding.

### RR\_FailedMsg

Outputs a fatal error message to the Conductor.

### RR\_GetDebugFlag

Gets the debug flag for the script.

### RR\_printf

Prints formatted output to the standard output stream.

### SET\_ABORT\_FUNCTION

Registers a callback function within the virtual user to call whenever the test operator manually aborts a test from the QALoad Conductor.

### SET\_SCRIPT\_LANGUAGE

Specifies the encoding used for literal strings contained within the script. The default encoding is "SLID\_English".

### SLEEP

Pauses a script for the specified number of seconds. This command is not affected by the sleep factor percentage specified in QALoad Conductor.

## SYNCHRONIZE

Pauses script execution on the virtual user until the Conductor tells it to continue.

## VARDATA

Replaces a string with a datapool variable.

## BEGIN\_TRANSACTION

Defines the beginning of the script's transaction loop.

QALoad automatically inserts `BEGIN_TRANSACTION` and `END_TRANSACTION` statements inside the script during the convert process. QALoad repeatedly executes the code between the `BEGIN_TRANSACTION` and `END_TRANSACTION` statements until you reach a maximum number of transactions or until the session duration time (specified in QALoad Conductor) is reached.

For each script, specify a frequency of execution with the pacing parameter in the QALoad Conductor. QALoad pauses the script after each transaction is complete, ensuring that it does not send transactions to the system under test more rapidly than the pacing value specifies. This pause occurs at the `BEGIN_TRANSACTION` command.

### Syntax

```
BEGIN_TRANSACTION( );
```

### Return Value

### Parameters

None.

### Example

```
BEGIN_TRANSACTION( );
...
...
END_TRANSACTION( );
```

## BeginCheckpoint

Marks the beginning of a checkpoint.

You can turn enhanced checkpoints on or off from the QALoad Script Development Workbench's [Convert Options dialog box](#). `BeginCheckpoint` is always used in conjunction with an [EndCheckpoint](#) command.

### Syntax

```
BeginCheckpoint ( char* CheckpointName );
```

### Return Value

### Parameters

Parameter	Description
CheckpointName	String containing a description of the checkpoint. This value cannot be longer than 127 characters.

### Example

```
BeginCheckpoint("Testing User-defined");  
DO_Http("GET http://compuweb.compuware.com/ HTTP/ 1.0\r\n\r\n");  
EndCheckpoint("Testing User-defined");
```

## CLOSE\_ALL\_DATA\_POOLS

Closes all open local datapool files.

All local datapool files should be closed at the end of the script using this statement.

### Syntax

```
CLOSE_ALL_DATA_POOLS ();
```

### Return Value

### Parameters

None.

### Example

```
BeginCheckpoint();  
RR__printf("Datapool Entry #1: %s", GET_DATA_FIELD 1);  
DO_SLEEP(500);  
EndCheckpoint(1);  
CLOSE_ALL_DATA_POOLS ();  
END_TRANSACTION( );
```

## CLOSE\_DATA\_POOL

Closes the specified local datapool file.

All local datapool files should be closed at the end of the script using these statements or the `CLOSE_ALL_DATA_POOLS` command.

### Syntax

```
CLOSE_DATA_POOL (int datapool ID);
```

### Return Value

### Parameters

Parameter	Description
Datapool ID	The local datapool file to close.

### Example

```
END_TRANSACTION();  
CLOSE_DATA_POOL( SS_1 ); /* Default placement after */  
/* END_TRANSACTION */
```

## COUNTER\_VALUE

Updates or increments the values of custom counters defined using the `DEFINE_COUNTER` command.



## Versions

Versions of COUNTER\_VALUE are:

`COUNTER_VALUE ( int Counter_ID, long Counter_Value );`

`COUNTER_VALUE ( int Counter_ID, float Counter_Value );`

## DATE\_TIME

Gets the current time and/or date from the local machine.

### Syntax

```
char * DATE_TIME(const char *pformat);
```

### Return Value

char \*: Formatted date/time string. This string should be freed when it is no longer needed.

### Parameters

Parameter	Description
pformat	<p>A formatted control string that determines how to format the date/time string. The following formats can be used:</p> <ul style="list-style-type: none"> <li>! %a: Abbreviated weekday name</li> <li>! %A: Full weekday name</li> <li>! %b: Abbreviated month name</li> <li>! %B: Full month name</li> <li>! %c: Date and time representation appropriate for locale</li> <li>! %d: Day of month as a decimal number (01-31)</li> <li>! %H: Hour in a 24-hour format (00-23)</li> <li>! %I: Hour in a 12-hour format (01-12)</li> <li>! %j: Day of the year as a decimal number (001-366)</li> <li>! %m: Month as a decimal number (01-12)</li> <li>! %M: Minute as a decimal number (00-59)</li> <li>! %p: Current locale's AM/PM indicator for a 12-hour clock format</li> <li>! %S: Second as a decimal number (00-59)</li> <li>! %U: Week of the year as a decimal number, with Sunday as the first day of the week (00-53)</li> <li>! %w: Weekday as a decimal number (0-6, Sunday is 0)</li> <li>! %W: Week of the year as a decimal number, with Monday as the first day of the week (00-53)</li> <li>! %x: Date representation for the current locale</li> <li>! %X: Time representation for the current locale</li> <li>! %y: Year without a century, as a decimal number (00-99)</li> <li>! %Y: Year with a century, as a decimal number</li> <li>! %Z: Time zone name or abbreviation; no characters if the time zone is unknown</li> <li>! %%%: Percent sign</li> </ul>

## Language Reference Commands

### Example

```
char *temp = NULL;
temp = DATE_TIME("Today is %A, day %d of %B in the year %Y.");
free(temp);
//might produce the following:
//Today is Wednesday, day 21 of January in the year 2004.
```

### DefaultCheckpointsOn

Automatically added when the Include Default Checkpoint statement's convert option is selected in Workbench.

When this command is found in a QALoad script, QALoad does not automatically generate checkpoints inside the middleware when Auto Timings is enabled in the QALoad Conductor. Instead, QALoad uses checkpoint statements found within the QALoad script.

#### Syntax

```
void DefaultCheckpointsOn (void);
```

#### Return Value

#### Parameters

None


#### Example

```
...
// Checkpoints have been included by the convert process
DefaultCheckpointsOn ();
...
```

### DEFINE\_COUNTER

Defines custom counters.

Custom counters are written and managed on a per user basis. They are saved to the timing file and can be graphed in Analyze. Counter data types can be either signed longs or floats. The counter type can be either cumulative or instance, which tells Analyze how to graph the counter. Works in conjunction with the COUNTER\_VALUE command.

 **Note:** If you call DEFINE\_COUNTER more than once, with all of the same parameters, it returns the same counter ID.

#### Syntax

```
int DEFINE_COUNTER ( char* Group_Name, char* Counter_Name, char* Units, CounterDataTypeEnum
Data_Type, CounterCounterTypeEnum Counter_Type );
```

#### Return Value

any value except -1 if successful  
-1 if unsuccessful

#### Parameters

Parameter	Description
-----------	-------------

Group_Name	The name of the group this counter belongs to.						
Counter_Name	The name of the counter.						
Units	The counter units. Can be NULL if no units are needed for this counter.						
Data_Type	<p><i>CounterDataTypeEnum</i></p> <p>Counter data type. Valid values are:</p> <table> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>DATA_LONG</td> <td>The counter values will be of type long.</td> </tr> <tr> <td>DATA_FLOAT</td> <td>The counter values will be of type float.</td> </tr> </tbody> </table>	Value	Description	DATA_LONG	The counter values will be of type long.	DATA_FLOAT	The counter values will be of type float.
Value	Description						
DATA_LONG	The counter values will be of type long.						
DATA_FLOAT	The counter values will be of type float.						
Counter_Type	<p><i>CounterCounterTypeEnum</i></p> <p>Counter type. Valid values are:</p> <table> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>COUNTER_CUMULATIVE</td> <td>The counter data is cumulative.</td> </tr> <tr> <td>COUNTER_INSTANCE</td> <td>The counter data is instance.</td> </tr> </tbody> </table>	Value	Description	COUNTER_CUMULATIVE	The counter data is cumulative.	COUNTER_INSTANCE	The counter data is instance.
Value	Description						
COUNTER_CUMULATIVE	The counter data is cumulative.						
COUNTER_INSTANCE	The counter data is instance.						

### Example

```
// "CounterGroup", "Counter Name",
// "Counter Units (Optional)" , Data Type, Counter Type.

id1 = DEFINE_COUNTER( "Cumulative Group", "Cumulative long",
    0, DATA_LONG, COUNTER_CUMULATIVE);
id2 = DEFINE_COUNTER( "Cumulative Group", "Cumulative float",
    0, DATA_FLOAT, COUNTER_CUMULATIVE);
id3 = DEFINE_COUNTER( "Instance Group", "Instance long",
    0, DATA_LONG, COUNTER_INSTANCE);
id4 = DEFINE_COUNTER( "Instance Group", "Instance float",
    0, DATA_FLOAT, COUNTER_INSTANCE);
SYNCHRONIZE();
BEGIN_TRANSACTION();
```

The following is an example of a command to call each time an error occurs:

```
void ErrorOneOccurred()
{
int errorCounterID;
errorCounterID = DEFINE_COUNTER( "Some Error Group", "Error One", 0, DATA_LONG,
COUNTER_CUMULATIVE );
COUNTER_VALUE( errorCounterID, 1 );
}
```

### DEFINE\_TRANS\_TYPE

Associates a description for the transaction loop displayed in QALoad Analyze .

#### Syntax

```
DEFINE_TRANS_TYPE ( char* text );
```

## Return Value

## Parameters

Parameter	Description
text	A string of one to 60 characters enclosed in quotes.

## Example

```
DEFINE_TRANS_TYPE ( "Receiving in Acquisition" );
```

## DO\_AbortOnError

Used to enable or disable error handling in a script.

The parameter that is passed to `DO_AbortOnError` sets how functions respond when an error is encountered. When an error is encountered, functions can continue or abort the script.


Under normal conditions, error handling is set in the Script Development Workbench (for validation), or in the Conductor. `DO_AbortOnError` overrides these product settings.

## Syntax

```
DO_AbortOnError( bool flag );
```

## Return Value

## Parameters

Parameter	Description
flag	TRUE or FALSE. A flag indicating whether the script should abort upon receiving an error.  Tip: If you choose FALSE, you must implement error checking for all functions that return a value to ensure that NULL or incorrect values are not subsequently used in the script.

## Example

```
char *p;
char temp[1000];
...
...
strcpy( temp, "Here is the search string." );

DO_AbortOnError(FALSE);
p = DO_GetUniqueStringEx( temp, "the", "string" );

DO_AbortOnError(TRUE);
if (p != NULL )
{
RR_printf( "String value = %s", p );
free( p );
}
else
{
//error handling if a NULL value is returned.
RR_printf( "String not found" );
}
```

## DO\_ExtractString

Finds a sub-string in a null-terminated data buffer.

Retrieves a unique value in the data buffer `szBuffer`. The parameters `szLeft` and `szRight` represent data just to the left and just to the right of a string in `szBuffer`. The `nCount` parameter specifies which left string to use if there is more than one matching string. The `pszResult` parameter is the address of a string (`char*`) that holds the resulting extracted string.

 **Note:** The left string and the right string must be provided or an error is returned.

### Syntax

```
BOOL DO_ExtractString(const char* szBuffer, int nCount, const char* szLeft, const char*
szRight, char** pszResult);
```

### Return Value

TRUE if successful  
`char* szResult = NULL;`

...

/\*

\* The page returns a page containing "<title>Enter Login</title>"

\*/

```
DO_Http("GET http://www.host.com/ HTTP/1.1\r\n\r\n");
```

```
DO_ExtractString(DO_GetReplyBuffer(), 1, "<title>", "</title>", &szResult);
```

/\*

\* prints "The extracted title: Enter Login"

\*/


```
RR_printf("The extracted title: %s", szResult);
```

```
free(szResult);
```

```
szResult = NULL;
```

FALSE if not successful

`DO_ExtractString` allocates enough space in the parameter passed in as the string buffer to hold the string (including the NULL).

 **Caution:** The result parameter variable should be explicitly initialized to NULL. Failure to do so results in a memory error in the script.

Once the result parameter has been allocated, it can be reused within the same transaction loop without being explicitly freed. However, the buffer memory should be freed at the end of the transaction loop and the pointer should be set to NULL. Failure to do so results in a memory leak.

### Parameters

Parameter	Description
<code>szBuffer</code>	The buffer to search.
<code>nCount</code>	The number of occurrences in the left string before a match is made.
<code>szLeft</code>	The left side of the string to match.
<code>szRight</code>	The right side of the string to match.

pszResult	The address of the return string.
-----------	-----------------------------------

### Example

```
char* szResult = NULL;
...
/*
 * The page returns a page containing "<title>Enter Login</title>"
 */
DO_Http("GET http://www.host.com/ HTTP/1.1\r\n\r\n");
DO_ExtractString(DO_GetReplyBuffer(), 1, "<title>", "</title>", &szResult);
/*
 * prints "The extracted title: Enter Login"
 */
RR_printf("The extracted title: %s", szResult);
free(szResult);
szResult = NULL;
```

## DO\_MSLEEP

Inserts a sleep for the number of seconds defined in the parameter.

The parameter passed to DO\_MSLEEP is first scaled by the sleep factor percentage specified in QALoad Conductor. During unit testing of the script, setting the sleep factor percentage to 0 (zero percent) causes DO\_MSLEEP not to sleep at all.

This command is ideal for unit testing where delays may not be wanted. Once the script is unit tested, the sleep factor percentage may be reset back to a suitable value, generally somewhere between 80% and 100%.

In addition, the sleep factor percentage can be set to Random in the QALoad Conductor. In this case, when a DO\_MSLEEP command is encountered, it sleeps for a random time frame ranging from 0 to the value specified.

### Syntax

```
DO_MSLEEP( int nMilliseconds );
```

### Return Value

### Parameters

Parameter	Description
nMilliseconds	Number of milliseconds to sleep.

### Example

This example shows how to pause a script for 5 seconds using the sleep function call. This example sleeps 5 seconds if the sleep factor percentage is set to 100 in the QALoad Conductor .

```
DO_MSLEEP( 5 ); /* Sleep 5 seconds */
```

## DO\_SetTransactionCleanup

Defines a point at the end of the transaction for anything that needs to be deallocated or uninitialized.

When transaction restarting occurs for a failed transaction, QALoad first executes any code starting after the call to `DO_SetTransactionCleanup`, allowing you to clean up important information and prevent memory leaks before retrying the transaction. This function is used in conjunction with [DO\\_SetTransactionStart](#).

### Syntax

```
DO_SetTransactionCleanup() ;
```

### Return Value

### Parameters

None.

### Example

```
BEGIN_TRANSACTION();
DO_SetTransactionStart();
TRANSACTION CODE...
DO_SetTransactionCleanup();
DO_HttpCleanup();
DO_SomeOtherMiddlewareCleanup();
END_TRANSACTION();
```

## DO\_SetTransactionStart

Defines a point at the beginning of the transaction loop that QALoad uses to rewind the transaction if the transaction fails and Restart Transaction error handling is selected in the QALoad Conductor. This function is used in conjunction with `DO_SetTransactionCleanup`.

### Syntax

```
DO_SetTransactionStart() ;
```

### Return Value

### Parameters

None.

### Example

```
BEGIN_TRANSACTION();
DO_SetTransactionStart();

TRANSACTION CODE...
DO_SetTransactionCleanup();
DO_HttpCleanup();
DO_SomeOtherMiddlewareCleanup();
END_TRANSACTION();
```

## DO\_SetValue

Associates a value to a variable name.


Variable names are embedded into parameter strings of QALoad functions and the value is interpolated at replay. Currently, `DO_Http` and `DO_Https` are the only functions that interpolate the variables.

To embed a variable name, the name is wrapped by `{` and `}`. The default interpolation is to use the variable name as a part of the substituted value. For example, a name of `"{this-name}"` with a value of `"this-value"` is

interpolated in the string "{this-name}" as "this-name=this-value". To suppress the variable name in the interpolated value, put an asterisk (\*) right after the opening {. For example, a name of "this-name", with a value of "this-value" is interpolated in the string "{\*this-name}" as "this-value".

After a variable is interpolated, it is removed from the variable table. For example, a name of "this-name" with a value of "this-value" is interpolated in the string "{\*this-name} {\*this-name}" as "this-value {this-name}".

If a variable is needed twice, it must be set twice. To suppress the removal of the variable from the variable table, put an exclamation (!) before the closing }. For example, a name of "this-name", with a value of "this-value" is interpolated in the string "{\*this-name!} {\*this-name!}" as "this-value".

 **Note:** When using DO\_SetValue to store CGI parameters, the parameters must be CGI encoded. This is done automatically by DO\_GetFormValueByName, by the string constants inserted during conversion.

### Syntax

```
BOOL DO_SetValue( const char *name, const char *value )
```

### Return Value

TRUE if successful  
FALSE if unsuccessful.

### Parameters

Parameter	Description
name	String containing the name of the field in which to set a value.
value	String containing the value to set this field.

### Example

```
...
...
DO_SetValue("name", "Joe+Smith" );
DO_SetValue("name", "Joe+Smith" );
DO_Http("GET http://company.com/forms.pl?{name} HTTP/1.0\r"
"\n Referer: http://company.com/forms.html\r\n Unused:"
"{*name}\r\n\r\n" );
...
...
QALoad will expand the statement internally as follows:
"GET http://company.com/forms.pl?name=Joe+Smith HTTP/1.0\r"
"\n Referer: http://company.com/forms.html\r\n"
"Unused: Joe+Smith\r\n\r\n"
```

## DO\_SLEEP

Inserts a sleep for the number of seconds defined in the parameter.

The parameter passed to DO\_SLEEP is first scaled by the sleep factor percentage specified in QALoad Conductor. During unit testing of the script, setting the sleep factor percentage to 0 (zero percent) causes DO\_SLEEP not to sleep at all.

This command is ideal for unit testing where delays may not be wanted. Once the script is unit tested, the sleep factor percentage may be reset back to a suitable value, generally somewhere between 80% and 100%.



In addition, the sleep factor percentage can be set to Random in the QALoad Conductor. In this case, when a DO\_SLEEP command is encountered, it sleeps for a random time frame ranging from 0 to the value specified.

### Syntax

```
DO_SLEEP( int nSeconds );
```

### Return Value

### Parameters

Parameter	Description
nSeconds	Number of seconds to sleep.

### Example

This example shows how to pause a script for 5 seconds using the sleep function call. This example sleeps 5 seconds if the sleep factor percentage is set to 100 in the QALoad Conductor .

```
DO_SLEEP( 5 ); /* Sleep 5 seconds */
```

## END\_TRANSACTION

Marks the end of the transaction loop.

At the end of the transaction loop, the virtual user performs the following actions:

1. Records the transaction's elapsed time, from BEGIN\_TRANSACTION to END\_TRANSACTION. This is reported on the Analyze report as the Duration.
2. Determines if another transaction should be processed on this virtual user:
  - ! If the test is over, script processing continues with the command following the END\_TRANSACTION.
  - ! If the test is not over, QALoad jumps to the BEGIN\_TRANSACTION command, where the script is paused for pacing, if specified.

A test is over if one or more of the following conditions are met:

- ! The amount of time the test has been running exceeds the maximum session duration as set up in the session ID file.
- ! The operator has manually ended the test.
- ! This virtual user has executed the maximum number of transactions for the virtual users running this script as set on the Conductor's Script Assignment tab.

### Syntax

```
END_TRANSACTION ( );
```

### Return Value

### Parameters

None.

## Language Reference Commands

### Example

```
...
BEGIN_TRANSACTION ( );
...
...
END_TRANSACTION ( );
```

### EndCheckpoint

Indicates the end of a checkpoint, corresponding to a BeginCheckpoint command.

BeginCheckpoint and EndCheckpoint correspond to QALoad's enhanced checkpoints. You can turn enhanced checkpoints on or off from the QALoad Script Development Workbench's [Convert Options dialog box](#). EndCheckpoint is always used in conjunction with a [BeginCheckpoint](#) command.

### Syntax

```
EndCheckpoint ( char* CheckpointName ) ;
```

### Return Value

### Parameters

Parameter	Description
CheckpointName	String containing a description of the checkpoint. This value cannot be longer than 127 characters.

### Example

```
BeginCheckpoint("Testing User-defined");
DO_Http("GET http://compuweb.compuware.com/ HTTP/ 1.0\r\n\r\n");
EndCheckpoint("Testing User-defined");
```

## EXIT

Stops script processing and returns control back to the Conductor.

### Syntax

```
EXIT ( );
```

### Return Value

### Parameters

None.

### Example

```
...
...
EXIT( );
```

## GET\_ABSOLUTE\_VUNUM

Gets the absolute virtual user number. This value is used to identify a virtual user uniquely within an entire test.

## Syntax

```
int GET_ABSOLUTE_VUNUM ( );
```

## Return Value

int -- absolute virtual user number

## Parameters

None.

## Example

```
int vunum;
nuvum = GET_ABSOLUTE_VUNUM();
RR_printf("I am vu %d", vunum);
```

## GET\_DATA

Requests that QALoad Conductor send the next datapool record to the script.

If you reach the end of the datapool file when this command is called, the script either exits with an END OF DATA status in QALoad Conductor, or rewinds to the beginning of the datapool file, depending on the status of the rewind option in QALoad Conductor.

## Syntax

```
GET_DATA ( );
```

## Return Value

## Parameters

None.

## Example

```
BEGIN_TRANSACTION( ); /*Beginning of transaction loop*/
GET_DATA ( );
...
RR_printf(VARDATA(1) );
```

## GET\_DATA\_FIELD

Accesses the fields from the data record that were just read using the READ\_DATA\_RECORD statement. Field numbering starts at one (1).

## Syntax

```
GET_DATA_FIELD (int datapool ID, int FieldNum);
```

## Return Value

## Parameters

Parameter	Description
Datapool ID	The datapool whose record should be used. This is necessary because you can have up to 32 local datapool files open at once.
FieldNum	Which field of the record to read. Field numbering starts at one (1).

### Example

```
BeginCheckpoint();  
RR_printf("Datapool Entry #1: %s", GET_DATA_FIELD (1, 1) );  
DO_SLEEP(500);  
EndCheckpoint(1);
```

## GET\_DATAPOOLS\_DIR

Retrieves the name of the QALoad Datapools directory.

For example, this function call returns the directory `\Program Files\Compuware\QALoad\Datapools`.

### Syntax

```
const char *GET_DATAPOOLS_DIR()
```

### Return Value

### Parameters

None.

### Example

```
const char *pDatapoolsDir;  
pDatapoolsDir = GET_DATAPOOLS_DIR();  
  
// As an example, the default install directory for pDatapoolsDir would =  
c:\ProgramFiles\Compuware\QALoad\ Datapools ;  
  
// To print out the datapools directory, type  
RR_printf("datapools directory = %s\n", GET_DATAPOOLS_DIR() ) ;
```

## GET\_HOME\_DIR

Retrieves the name of the QALoad installation directory.

For example, this function call returns the directory `\Program Files\Compuware\ QALoad .`

### Syntax

```
const char *GET_HOME_DIR()
```

### Return Value

### Parameters

None.

### Example

```
const char *pHomeDir;  
pHomeDir = GET_HOME_DIR();  
  
// As an example, the default installation directory for  
// pHomeDir would = c:\Program Files\Compuware\ QALoad ;
```

## GET\_LOGFILES\_DIR

Retrieves the name of the QALoad LogFiles directory.

For example, this function call will return the directory \Program Files\Compuware\QALoad\LogFiles.

### Syntax

```
const char *GET_LOGFILES_DIR()
```

### Return Value

### Parameters

None.

### Example

```
const char *pLogFilesDir;
pLogFilesDir = GET_LOGFILES_DIR();

// As an example, the default installation directory for
// pLogFilesDir would = c:\Program Files\Compuware\QALoad\LogFiles;
```

## GET\_RELATIVE\_VUNUM

Gets the relative virtual user number. This value is used to identify a virtual user uniquely within a player instance.

### Syntax

```
int GET_RELATIVE_VUNUM ();
```

### Return Value

int -- relative virtual user number

### Parameters

None.

### Example

```
int vunum;
nunun = GET_RELATIVE_VUNUM();
RR_printf("I am vu %d", vunum);
```

## GET\_SCRIPTS\_DIR

Retrieves the name of the QALoad Scripts directory.

For example, this function call will return the directory \ Program Files\ Compuware\ QALoad\ scripts.

### Syntax

```
const char *GET_SCRIPTS_DIR()
```

### Return Value

### Parameters

None.

## Language Reference Commands

### Example

```
const char *pScriptsDir;
pScriptsDir = GET_SCRIPTS_DIR();

// As an example, the default installation directory for
// pScriptsDir would = c:\Program Files\Compuware\QALoad\Scripts;
```

## GET\_TIMINGFILES\_DIR

Retrieves the name of the QALoad Timing Files directory.

For example, this function call will return directory \Program Files\Compuware\QALoad\TimingFiles.

### Syntax

```
const char *GET_TIMINGFILES_DIR()
```

### Return Value

### Parameters

None.

### Example

```
const char *pTimingFilesDir;
pTimingFilesDir = GET_TIMINGFILES_DIR();

// As an example, the default installation directory for
// pTiming FilesDir would = c:\Program Files\Compuware\QALoad\TimingFiles ;
```

## LOG\_ERROR

Sends the corresponding message to the Conductor, so that it can be displayed within the [Player Messages](#) window in the Conductor.

### Syntax

```
LOG_ERROR( int nSendMsg, char* msg );
```

### Return Value

### Parameters

Parameter	Description
nSendMsg	Specifies whether msg should be sent to the Conductor.
msg	String that corresponds to the message to send to the Conductor.

### Example

```
int rrobot_script( PLAYER_INFO *s_info )
{
    SET_ABORT_FUNCTION(abort_function);
    DEFINE_TRANS_TYPE( "CP01" );
    SYNCHRONIZE();
    BEGIN_TRANSACTION();
    LOG_ERROR(TRUE, "Message text here");
}
```

```

END_TRANSACTION();
REPORT(SUCCESS);
EXIT();
return(0);
}

```

## Modify\_Encoding

Modifies the encoding for a string parameter.

Modify\_Encoding is used in scripts to convert strings to UTF8, EUCJP or to the language used by the script.

### Syntax

```
char* Modify_Encoding(PLAYERINFO* pInfo, EncodingLangEnum encodingID, const char* strInput,
char** szResult)
```

### Return Value

A char pointer to the encoded string if successful; NULL if not successful.

### Parameters

Parameter	Description								
pInfo	Pointer to the PLAYERINFO struct, pInfo.								
encodingID	<p><i>EncodingTypeEnum</i></p> <p>Counter data type. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>UTF8</td> <td>UTF8 encoding.</td> </tr> <tr> <td>EUCJP</td> <td>EUCJP encoding.</td> </tr> <tr> <td>SCRIPT_LANGUAGE</td> <td>Script language encoding.</td> </tr> </tbody> </table>	Value	Description	UTF8	UTF8 encoding.	EUCJP	EUCJP encoding.	SCRIPT_LANGUAGE	Script language encoding.
Value	Description								
UTF8	UTF8 encoding.								
EUCJP	EUCJP encoding.								
SCRIPT_LANGUAGE	Script language encoding.								
strInput	The input string.								
szResult	The resulting encoded string. Note that this buffer will need to be freed to prevent memory leaks.								

### Example

The following is an example of a encoding a string:

```
Modify_Encoding(SCRIPT_LANGUAGE, DO_Http("GET http://www.google.com/ HTTP/1.0\r\n\r\n"),
&test);
```

## OctalToChar

Converts any octal escape sequences to binary.

Octal sequences consist of a backslash followed by two digits. This can be useful for adding binary data to a datapool file in the form of octal escape sequences, since datapool files must contain only ASCII strings.

For example:

\77 is equivalent to an ASCII 63 which is a question mark character.

## Language Reference Commands

\12 is equivalent to an ASCII 10 which is a linefeed character.

### Syntax

```
int OctalToChar (char* str);
```

### Return Value

n The length of the string after conversion.

### Parameters

Parameter	Description
str	A null-terminated string.

### Example

```
char str[80];  
...  
strcpy(input, GET_DATA_FIELD(1, 1)); //copy data from datapool field into string variable  
OctalToChar(input);  
DO_WSK_Send(S1, input);
```

## OPEN\_DATA\_POOL

Opens the datapool file.

This command line is typically placed before the BEGIN\_TRANSACTION( ) statement.

### Syntax

```
OPEN_DATA_POOL (char* frame, int pNumber, int rewindflag);
```

### Return Value

### Parameters

Parameter	Description
frame	The name of the datapool file, including a drive and path.
pNumber	The ID that was given to the datapool when it was inserted into the script. This is used anytime the script reads a record or field from the datapool.
rewindFlag	TRUE if the datapool file should be rewound to the beginning after it reaches the end. FALSE if it should not rewind.

### Example

```
OPEN_DATA_POOL( "C:\\Program Files\\Compuware\\ QALoad \\Middlewares\\  
SQLServer\\Scripts\\junk.dat", SS_1, TRUE );  
  
/* Default placement before BEGIN_TRANSACTION */  
SYNCHRONIZE();  
BEGIN_TRANSACTION();
```



## RANDOM\_NUMBER

Returns a string representation of a random number between Low and High using Leading and Decimals to format the number.

The seed value that is used to generate the random number is automatically generated from the Player.

### Syntax

```
char* RANDOM_NUMBER(int Low, int High, int Leading, int Decimals);
```

### Return Value

char\*: A pseudo-random random number string. This string should be freed when it is no longer needed.

### Parameters

Parameter	Description
Low	Lowest number that is generated.
High	Highest number that is generated.
Leading	If greater than zero, this value specifies how many digits must be present to the left of the decimal point. Values are padded with zeroes to reach the specified value.
Decimals	If greater than zero, this value specifies how many digits must be present to the right of the decimal point. If zero is specified, no decimal point is generated.

### Example

```
char *temp = NULL;
temp = RANDOM_NUMBER(1, 100, 3, 2);
free(temp);
//might produce the following strings:
// "004.38"
// "099.03"
// "077.12"
```

## RANDOM\_STRING

Returns a string with a random set of alpha or alphanumeric characters of the specified width.

The seed value that is used to generate the random number is automatically generated from the Player.

### Syntax

```
char* RANDOM_STRING(int AlphaNum, int WidthMin, int WidthMax);
```

### Return Value

char\*: A pseudo-random random alphanumeric string. This string should be freed when it is no longer needed.

### Parameters

Parameter	Description
AlphaNum	One of the following values:

	0: Returning string should contain only numeric values 1: Returning string should contain only alpha values 2: Returning string should contain alpha and numeric values
WidthMin	Minimum width of the variable width format of the call.
WidthMax	Maximum width of the variable width format of the call.

### Example

```
char *temp = NULL;
temp = RANDOM_STRING(1, 4, 10);
free(temp);

//might produce the following strings:
// "fj32"
// "mfigkec973"
// "fik34kf"
```

## READ\_DATA\_RECORD

Reads a data record from a local datapool file.

This statement is typically placed after the BEGIN\_TRANSACTION statement, although it is possible to read more than one record from the file during a single transaction.

### Syntax

```
READ_DATA_RECORD( int datapool_ID );
```

### Return Value

### Parameters

Parameter	Description
Datapool_ID	Tells from which local datapool file to read the record.

### Example

```
BEGIN_TRANSACTION();
READ_DATA_RECORD( SS_1 ); /* Default placement - Start of */
/* Transaction loop */
```

## RND\_DELAY

Delays the script for a random interval before proceeding.

Each time the script executes the RND\_DELAY command, the Player generates a random number. It uses a uniform distribution, between 0 and n seconds, where n is the parameter to the RND\_DELAY command. The average delay time for multiple occurrences of this command is n/2 seconds.

### Syntax

```
RND_DELAY ( int nSeconds );
```

### Return Value

## Parameters

Parameter	Description
nSeconds	Maximum number of seconds to delay before script execution proceeds.

## RND\_DELAY\_RANGE

Delays the script for a random interval, within a specified range, before proceeding.

Each time the script executes the RND\_DELAY\_RANGE command, the Player generates a random number. It uses a uniform distribution between minTime and maxTime seconds.

### Syntax

```
int RND_DELAY_RANGE (int minTime, int maxTime);
```

### Parameters

Parameter	Description
minTime	Minimum number of seconds to delay before script execution continues.
maxTime	Maximum number of seconds to delay before script execution continues.

### Example

In this example, the script pauses for a pseudo-random range between 2 and 10 seconds using the random delay range function.

```
RND_DELAY_RANGE(2, 10); /* Sleep between 2 and 10 seconds. */
```

## RR\_FailedMsg

Outputs a fatal error message to the Conductor. Use this function to describe an error condition encountered that caused the script to fail.

Do not call RR\_FailedMsg in an SAP or Citrix script if the script includes a restart transaction operation. [SAPGui\\_error\\_handler](#) or [CTX\\_error\\_handler](#) can be called with the same parameters as RR\_FailedMsg to output a fatal error message while still allowing a proper clean up of the current transaction before restarting the transaction.

### Syntax

```
int RR_FailedMsg (PLAYERINFO *pPlayerInfo, char* msg);
```

### Return Value

### Parameters

Parameter	Description
pPlayerInfo	Pointer to the PLAYERINFO struct, sinfo.
msg	Message to be passed to the Conductor.

## Language Reference Commands

### Example

```
int ret = 0;
ret = myFunc();
if(ret == ERROR)
RR__FailedMsg(s_info, "Virtual User Failed on myFunc!");
```

### RR\_\_GetDebugFlag

Gets the debug flag for the script.

#### Syntax

```
int RR__GetDebugFlag ();
```

#### Return Value

True if the debug flag is on.

False if the debug flag is off.

#### Parameters

none

#### Example

```
RR__GetDebugFlag ();
```

### RR\_\_printf

Prints formatted output to the standard output stream.

RR\_\_printf formats and prints a series of characters and values to the standard output stream, stdout. If arguments follow the format string, the format string must contain specifications that determine the output format for the arguments.

The format argument consists of ordinary characters, escape sequences, and, if arguments follow format, format specifications. The ordinary characters and escape sequences are copied to stdout in order of their appearance.

For example, the line:

```
RR__printf("Line one\n\t\tLine two\n");
```

produces the output:

```
Line one
Line two
```

Format specifications always begin with a percent sign (%) and are read left to right. When RR\_\_printf encounters the first format specification, if any, it converts the value of the first argument after format and outputs it accordingly. The second format specification causes the second argument to be converted and output, and so on. If there are more arguments than there are format specifications, the extra arguments are ignored. The results are undefined if there are not enough arguments for all the format specifications.

#### Syntax

```
int RR__printf(const char * format [, argument]...);
```

#### Return Value

The number of characters printed or a negative value if an error occurs.

## Parameters

Parameter	Description
format	Format control.
argument	Optional arguments.

## Example

```
/* This code segment shows examples of the usage of the RR_printf function to produce
formatted output for various datatypes. */
```

```
char ch='h', *string="computer";
int count=-9234;
double fp=251.7366;
wchar_t wch=L'w', *wstring=L"Unicode";

/*Display integers. */
RR_printf("Integer formats:\n" "\tDecimal: %d Justified: %.6d Unsigned: %u\n", count,
count, count, count);

RR_printf("Decimal %d as:\n\tHex: %Xh C hex: 0x%x Octal: %o\n", count, count, count,
count);

/* Display in different radices. */
RR_printf("Digits 10 equal:\n\tHex: %i Octal: %i Decimal: %i\n",0x10, 010, 10);

/* Display characters. */
RR_printf("Characters in field:\n%10c%5hc%5C%5lc\n", ch, ch, wch, wch);

/* Display strings. */
RR_printf("Strings in field:\n%25s\n%25.4hs\n\t%S%25.3ls\n", string, string, wstring,
wstring);

/* Display real numbers. */
RR_printf("Real numbers:\n\t%f%.2f%e%E\n", fp, fp, fp, fp);

/* Display pointer. */
RR_printf("\nAddress as:\t%p\n", &count);

/* Count characters printed. */
RR_printf("\nDisplay to here:\n");
RR_printf("1234567890123456%n78901234567890\n", &count);
RR_printf("\tNumber displayed: %d\n\n", count);
```

## Output

Integer formats:

```
    Decimal: -9234
    Justified: -009234
    Unsigned: 4294958062
```

Decimal -9234 as:

```
    Hex: FFFDBEEh
    C hex: 0xffffdbee
    Octal: 37777755756
```

Digits 10 equal:

```
    Hex: 16
    Octal: 8
    Decimal: 10
```

Characters in field:

```
    h h w w
```

## Language Reference Commands

Strings in field:

```
computer
4hs
Uni
```

Real numbers:

```
251.736600
251.74 2.517366e+002
```

Address as:

```
0141FDC0
```

Display to here:

```
123456789012345678901234567890
```

Number displayed:

```
16
```

## SCRIPT\_MESSAGE

The **SCRIPT\_MESSAGE** command inserts custom script messages into a timing file during test execution. The command takes a group name and a message as parameters; the messages appear on the Error report in Analyze when they are used.

### Syntax

```
SCRIPT_MESSAGE ( char* group, char* msg );
```

### Parameters

Parameter	Description
group	Message group name.
msg	Message.

### Example

```
int rrobot_script( PLAYER_INFO *s_info )
{
    SET_ABORT_FUNCTION(abort_function);
    DEFINE_TRANS_TYPE( "CP01" );
    SYNCHRONIZE();

    BEGIN_TRANSACTION();
    SCRIPT_MESSAGE("My Group", "Message text here");
    END_TRANSACTION();
    REPORT(SUCCESS);
    EXIT();
    return(0);
}
```

## SET\_ABORT\_FUNCTION

Registers a callback function within the virtual user to call whenever the test operator manually aborts a test from the QALoad Conductor.

When the abort callback function returns, the script automatically exits.

 **Note:** Checkpoints executed during an abort are not recorded in the timing file.

### Syntax

```
SET_ABORT_FUNCTION ( char* functionName );
```

### Return Value

### Parameters

Parameter	Description
functionName	Name of a function to call when the test is aborted.

### Example

```
{
/* Script Initialization */
:
SET_ABORT_FUNCTION( abort_function ) ;
/* Script */
}

void abort_function( PLAYER_INFO * s-info ) ;

{
/* Abort functionality goes here */
EXIT( ) ;
}
```

## SET\_SCRIPT\_LANGUAGE

Specifies the encoding used for literal strings contained within the script. The default encoding is "SLID\_English".

 **Note:** This statement must precede the initialization of the middleware being used.

### Syntax

```
void SET_SCRIPT_LANGUAGE (SCRIPT_LANG languageID);
```

### Return Value

None

### Parameters

Parameter	Description
languageID	Identifies the language encoding of strings within the script. Possible values are: <ul style="list-style-type: none"> <li>! SLID_English</li> <li>! SLID_Chinese_Simplified</li> <li>! SLID_Chinese_Traditional</li> </ul>

## Language Reference Commands

	! SLID_Japanese
	! SLID_Korean

### Example

```
// Establish 'Japanese' as the language of the encoded strings
SET_SCRIPT_LANGUAGE (SLID_Japanese);
DO_InitHttp(s_info); // SET_SCRIPT_LANGUAGE() must precede the
// middleware's initialization statement
```

## SLEEP

Pauses a script for the specified number of seconds.

This command is not affected by the sleep factor percentage specified in QALoad Conductor.

### Syntax

```
SLEEP ( int nSeconds );
```

### Return Value

### Parameters

Parameter	Description
nSeconds	The number of seconds to sleep before execution proceeds.

## SYNCHRONIZE

Pauses script execution on the virtual user until the Conductor tells it to continue.

Normal usage is to have all scripts synchronize when they have reached the point at which transaction processing is to begin. There can be only one SYNCHRONIZE command per script.

### Syntax

```
SYNCHRONIZE( );
```

### Return Value

### Parameters

None.

### Example


```
...
...
SYNCHRONIZE( );
BEGIN_TRANSACTION( );
...
...
```



## SYNCH

This command is used to synchronize all virtual users for a particular script. When this statement is reached, QALoad halts execution of the virtual user. The virtual user remains halted until all other virtual users for this script have also halted at this statement. Then, the Conductor instructs all virtual users to continue.

Unlike the SYNCHRONIZE command, which is automatically added to the script above the BEGIN\_TRANSACTION statement by the convert process, you can insert any number of SYNCH commands into a script.

 Note: This function applies to virtual users that are already running. SYNCH does not apply to users who have not yet started the test.

### Syntax

```
SYNCH( );
```

### Parameters

None.

### Example

```
...
...
SYNCHRONIZE( );
...
BEGIN_TRANSACTION( );
...
SYNCH( );
...
...
END_TRANSACTION( );
```

## VARDATA

Replaces a string with a datapool variable.

To insert data from the fields in a datapool, substitute VARDATA(n) expressions wherever you want to replace a string with variable data. Note that datapool field numbering starts at 1.

### Syntax

```
VARDATA(n)
```

### Return Value

### Parameters

Parameter	Description
n	The datapool field number. Field numbering starts at 1.

### Example

```
Do_TuxFMLData ( 8302, 0, VARDATA(1));
```

## SAP

### SAP Commands

#### **SAPGuiApplication**

Allows scripts to call SAP GUI low-level administrative objects of the SAP GUI.

#### **SAPGuiCheckScreen**

Acts as a synchronization point in the script.

#### **SAPGuiCheckStatusbar**

Specifies the method (or property) that is called (or set), allowing the script access to the SAP GuiStatusbar object.

#### **SAPGuiCmd0**

Specifies the method (or property) that is called (or set) in the object specified in the previous SAPGuiPropIdStr call. No parameters are sent.

#### **SAPGuiCmd1**

Specifies the method (or property) that is called (or set) in the object specified in the previous SAPGuiPropIdStr call. One parameter is sent.

#### **SAPGuiCmd1Coll**

Specifies the method (or property) that is called (or set) in the object specified in the previous SAPGuiPropIdStr call. One parameter is sent. Use this variation to deal with Collection object information only.

#### **SAPGuiCmd1Elmnt**

Specifies the method (or property) that is called (or set) in the object specified in the previous SAPGuiPropIdStr call. One parameter is sent. This variation is to be used for entering COM array element info only (VB Collections).

#### **SAPGuiCmd1Sub**

Specifies the method (or property) that is called (or set) in the object specified in the previous SAPGuiPropIdStr call. One parameter is sent. This variation is to be used for dealing with subtype information only.

#### **SAPGuiCmd1Sub1**

Specifies the method (or property) that is called (or set) in the object specified in the previous SAPGuiPropIdStr call. One parameter is sent. This variation is to be used for dealing with subtype and SubParameter information only.

#### **SAPGuiCmd2**

Specifies the method (or property) that is called (or set) in the object specified in the previous SAPGuiPropIdStr call. Two parameters are sent.

#### **SAPGuiCmd3**

Specifies the method (or property) that is called (or set) in the object specified in the previous SAPGuiPropIdStr call. Three parameters are sent.

#### **SAPGuiConnect**

Specifies to which server a connection should be made.

#### **SAPGuiContentCheck**

Compares data from an SAP server returned control with input string based on the comparison options.

#### **SAPGuiCreateColl**

Specifies the method (or property) that is called (or set) in the object specified in the previous SAPGuiPropIdStr call. This call creates a collection.

**SAPGuiDestroyColl**

Specifies the method (or property) that is called (or set) in the object specified in the previous SAPGuiPropIdStr call. This call destroys a collection and decrements the reference count.

**SAPGuiGetControlText**

Extracts data from a SAP server returned control.

**SAPGuiGetUniqueString**

Extracts data from an SAP server returned control that occurs between the left and right input strings.

**SAPGuiPropIdStr**

Specifies the object ID string to use with subsequent SAPGui calls.

**SAPGuiPropIdStrExists**

Specifies the object ID string to use with subsequent SAPGui calls.

**SAPGuiPropIdStrExistsEnd**

Marks the end of the block of code that is executed if the condition in a prior SAPGuiPropIdStrExists command is true.

**SAPGuiSessionInfo**

Specifies the method (or property) that will be called, allowing the script access to the SAP GuiSessionInfo objects.

**SAPGuiSetCheckScreenWildcard**

Specifies the wildcard character to use for wildcard matching with SAPGuiCheckScreen.

**SAPGuiVerCheckStr**

Specifies the SAP GUI frontend version number at the time the capture file was made.

**SAPGuiApplication**

Allows scripts to call low-level administrative objects of the SAP GUI.

**Syntax**

SAPGuiApplication(char\* FuncName);

**Parameters**

Parameter	Description
FuncName	Function name.

**Example**

```

.
.
.

BEGIN_TRANSACTION();
DO_SetTransactionStart();
try{
    SAPGuiConnect( s_info,"qacsapdb");
    SAPGuiApplication(RegisterROT);
    SAPGuiVerCheckStr("6402.160.1");
}
    
```

.  
.  
.

## SAPGuiCheckScreen

Used as a synchronization point in your QALoad script.

Call this command after each request block to ensure that the screen being returned by the server is the one expected by the script. Each event sent from the SAP application server to the client includes the name of the ABAP program and the current screen title. This command ensures that the script and the application remain in synch.

Use `SAPGuiCheckScreen` with `SAPGuiSetCheckScreenWildcard` to perform a wildcard search for a screen title. This is especially useful if the screen title is likely to change with each new entry/lookup in the database during replay.

If you insert the wildcard (set in `SAPGuiSetCheckScreenWildcard`) as the first character of the title, then all titles with the same right-most characters will match. If the wildcard is located in any character position other than the first, QALoad does not treat it as a wildcard. For example, `*est` will match `test`, `tempest`, and `est`, but will not match `tester`. This prevents possible conflicts when a wildcard character is present in a captured string, but is not intended to be a wildcard. This also prevents conflicts within pre-existing scripts that were converted before the wildcard matching option was added in Release 4.4.

If the end of a title is problematic during replay, it is not necessary to use a wildcard match. Instead, reduce the number of characters that are compared in the title. For example, if the order number in the title `ORDER# PROCESSED: 12345` is likely to change during replay, shorten the title to remove the characters that are changing. In this case, shorten the title to `ORDER# PROCESSED:`. This results in a match with any title during replay that contains the first characters `ORDER# PROCESSED:`.

### Syntax

```
SAPGuiCheckScreen ( const char* OKCode, const char* ScreenName, const char* title );
```

### Return Value

### Parameters

Parameter	Description
OKCode	A string containing the current transaction code.
ScreenName	A string containing the current screen name.
title	A string containing the current string title.

### Example

```
SAPGuiCheckScreen( "SESSION_MANAGER", "SAPLSMTR_NAVIGATION", "SAP Easy Access" );
//Check the OKcode, ScreenName, and screen title after each command

SAPGuiPropIdStr("wnd[0]");
SAPGuiCmdl(GuiMainWindow,SendVKey,0);
SAPGuiCheckScreen( "S000", "SAPMSYST", "SAP" );

SAPGuiCmd3(GuiMainWindow,ResizeWorkingPane,94,24,false);
SAPGuiPropIdStr("wnd[0]/tbar[0]/okcd");
SAPGuiCmdl(GuiOkCodeField,PutText,"bibs");
SAPGuiPropIdStr("wnd[0]");
SAPGuiCmdl(GuiMainWindow,SendVKey,0);
```

```
SAPGuiCheckScreen( "SESSION_MANAGER", "SAPLSMTR_NAVIGATION", "SAP Easy Access" );

SAPGuiPropIdStr("wnd[0]/usr/subSA_0100_1:SAPLEXAMPLE_ENTRY_SCREEN:0200/subSA_200_1:SAPLEXAMP
LE_ENTRY_SCREEN:0800/cntlCC_HTML_INDEX/shellcont/shell");
SAPGuiCmd3(GuiCtrlHTMLViewer,SapEvent,"","","sapevent:ALV_SHORT?ALV");
SAPGuiCheckScreen( "BIBS", "SAPLEXAMPLE_ENTRY_SCREEN", "Style Guide: Check boxes" );
```

## SAPGuiCheckStatusbar

Specifies the method or property that is called or set, allowing the script access to the SAP GuiStatusbar object.

### Syntax

```
SAPGuiCheckStatusbar ( const char* ID, const char* statusBarValue );
```

### Return Value

### Parameters


Parameter	Description
ID	ID to specify access to the status bar object.
statusBarValue	Status bar string to check against.

### Example

```
SAPGuiCheckScreen("S000", "SAPMSYST", "SAP");
SAPGuiCmd3(GuiMainWindow, ResizeWorkingPane, 94, 24, false);
//SAPGuiCheckStatusbar returns TRUE if the message is found
//and FALSE if not found
BOOL bRetSts = SAPGuiCheckStatusbar("wnd[0]/sbar", "E: Make an entry in all required
fields");
if (bRetSts)
RR__printf(" True\n");
else
RR__printf(" False\n");
```

## SAPGuiCmd0

Specifies the method or property that is called or set in the object specified in the previous SAPGuiPropIdStr call. The 0 in the name indicates that zero parameters are sent.

 Note: For more information about SAP parameters, refer to SAP's publication titled "SAP GUI Scripting API for the Windows and Java Platforms".

### Syntax

```
SAPGuiCmd0( const char* Type, const char* FuncName);
```

### Return Value

### Parameters

Parameter	Description
-----------	-------------

Type	Type of object.
FuncName	Function or method/property related to the object.


**Example**

```
SAPGuiPropIdStr("wnd[0]/usr/subSA_0100_1:SAPLEXAMPLE_ENTRY_SCREEN:
  0200/subSA_200_2:SAPLEXAMPLE_ENTRY_SCREEN:
  2000/cntlCCCONTAINER/shellcont/shell");
SAPGuiCmd2(GuiCtrlGridView, SetCurrentCell, -1, "SEATSOCC");
//Call GuiCtrlGridView class method ClearSelection
SAPGuiCmd0(GuiCtrlGridView, ClearSelection);
SAPGuiCreateColl(GuiCollection, CreateGuiCollection, coll1);
SAPGuiCmd1Coll(GuiCollection, Add, coll1, "PRICE");
SAPGuiCmd1Coll(GuiCollection, Add, coll1, "SEATSMAX");
SAPGuiCmd1Coll(GuiCollection, Add, coll1, "SEATSOCC");
SAPGuiCmd1(GuiCtrlGridView, PutSelectedColumns, coll1);
SAPGuiDestroyColl(GuiCollection, coll1);

SAPGuiPropIdStr("wnd[0]/tbar[0]/btn[3]");
SAPGuiCmd0(GuiButton, Press);
SAPGuiCheckScreen( "BIBS", "SAPLEXAMPLE_ENTRY_SCREEN", "Style Guide: Alv grid" );
```

**SAPGuiCmd1**

Specifies the method or property that is called or set in the object specified in the previous SAPGuiPropIdStr call. The 1 in the name indicates that one parameter is sent.

 **Note:** For more information about SAP parameters, refer to SAP's publication titled "SAP GUI Scripting API for the Windows and Java Platforms".

**Syntax**

```
SAPGuiCmd1( const char* Type, const char* FuncName, const char* Param);
```

**Return Value**

**Parameters**

Parameter	Description
Type	Type of object.
FuncName	Function or method/property related to the object.
Param	The first parameter to send.

**Example**

```
SAPGuiCmd1(GuiPasswordField, PutCaretPosition, 3);
SAPGuiCmd1Pwd(GuiPasswordField, PutText, "~encr~1111111111");


//This variation is to be used for entering passwords only.
SAPGuiCmd1Pwd(GuiPasswordField, PutText, "~encr~1111111111" );

//Call the GuiMainWindow class method SendVKey with one parameter that has a value of 0
SAPGuiPropIdStr("wnd[0]");
SAPGuiCmd1(GuiMainWindow, SendVKey, 0);
SAPGuiCheckScreen( "SESSION_MANAGER", "SAPLSMTR_NAVIGATION", "SAP Easy Access" );
```

## SAPGuiCmd1Coll

Specifies the method or property that is called or set in the object specified in the previous SAPGuiPropIdStr call. The 1 in the name indicates that one parameter is sent.

Use this variation to deal with Collection object information only.

 Note: For more information about SAP parameters, refer to SAP's publication titled "SAP GUI Scripting API for the Windows and Java Platforms".

### Syntax

```
SAPGuiCmd1Coll( const char* Type, const char* FuncName, ISapGenericCollectionPtr Coll, const char* Param);
```

### Return Value

### Parameters

Parameter	Description
Type	Type of object.
FuncName	Function or method/property related to the object.
Coll	Collection name of collection.
Param	The first parameter to send.

### Example

```
//multiple selections of columns
SAPGuiPropIdStr("wnd[0]/usr/subSA_0100_1:SAPLEXAMPLE_ENTRY_SCREEN:
    0200/subSA_200_2:SAPLEXAMPLE_ENTRY_SCREEN:
    2000/cntlCCCONTAINER/shellcont/shell");
SAPGuiCmd2(GuiCtrlGridView,SetCurrentCell,-1,"SEATSOCC");
SAPGuiCmd0(GuiCtrlGridView,ClearSelection);
SAPGuiCreateColl(GuiCollection,CreateGuiCollection,coll1);


//adds columns to a collection that was created by the selection of columns
SAPGuiCmd1Coll(GuiCollection,Add,coll1, "PRICE");
SAPGuiCmd1Coll(GuiCollection,Add,coll1, "SEATSMAX");
SAPGuiCmd1Coll(GuiCollection,Add,coll1, "SEATSOCC");
SAPGuiCmd1(GuiCtrlGridView,PutSelectedColumns,coll1);
SAPGuiDestroyColl(GuiCollection,coll1);

SAPGuiPropIdStr("wnd[0]/tbar[0]/btn[3]");
SAPGuiCmd0(GuiButton,Press);
SAPGuiCheckScreen("BIBS", "SAPLEXAMPLE_ENTRY_SCREEN", "Style Guide: Alv grid");
```

## SAPGuiCmd1Elmnt

Specifies the method or property that is called or set in the object specified in the previous SAPGuiPropIdStr call. The 1 in the name indicates that one parameter is sent.

Use this variation for entering COM array element information only (VB collections).

 Note: For more information about SAP parameters, refer to SAP's publication titled "SAP GUI Scripting API for the Windows and Java Platforms".

### Syntax

```
SAPGuiCmd1Elmnt( const char* Type, const char* SubPropType, const char* FuncName,
IDispatchPtr ElmntAry, int ElmntIdx, const char* SubFuncName, const char* Param);
```

Return Value

Parameters

Parameter	Description
Type	Type of object.
SubPropType	The type of the sub-property.
FuncName	Function or method/property related to the object.
ElmntAry	Name of the COM element array.
ElmntIndx	Index of location in array.
SubFuncName	Function name in collection array.
Param	The first parameter to send.

Example


```
SAPGuiPropIdStr("wnd[0]/usr/subSA_0100_1:SAPLEXAMPLE_ENTRY_SCREEN:
    0200/subSA_200_2:SAPLEXAMPLE_ENTRY_SCREEN:
    2100/tblSAPLEXAMPLE_ENTRY_SCREENTC535");
SAPGuiCmdl(GuiTableControl, ReorderTable, "0 2 5 3 1 4 6 7" );

//Call GuiTableControl class of type
//GuiCollection with the GetColumns method.
//At elements 0, 4, and 2, set
//the width to 8, 8, and 7, respectively.
SAPGuiCmdlElmnt(GuiTableControl, GuiCollection, GetColumns, ElementAt, 0, PutWidth, 8 );
SAPGuiCmdlElmnt(GuiTableControl, GuiCollection, GetColumns, ElementAt, 4, PutWidth, 8 );
SAPGuiCmdlElmnt(GuiTableControl, GuiCollection, GetColumns, ElementAt, 2, PutWidth, 7 );
```

SAPGuiCmd1Sub

Specifies the method or property that is called or set in the object specified in the previous SAPGuiPropIdStr call. The 1 in the name indicates that one parameter is sent.

Use this variation of the SAPGuiCmd command for dealing with subtype information only.

 Note: For more information about SAP parameters, refer to SAP's publication titled "SAP GUI Scripting API for the Windows and Java Platforms".

Syntax

```
SAPGuiCmd1Sub( const char* Type, const char* SubPropType, const char* FuncName, const char*
SubFuncName, const char* Param);
```

Return Value

Parameters

Parameter	Description
-----------	-------------



Type	Type of object.
SubPropType	The type of the sub-property.
FuncName	Function or method/property related to the object.
SubFuncName	Function name in the collection array.
Param	The first parameter to be sent.

### Example


```
// Call GuiTableControl class of type
// GuiCollection. Get all columns and
// set the width to a value of 2.

SAPGuiPropIdStr("wnd[0]/usr/tblMP400100TC3000");
SAPGuiCmd1Sub1(GuiTableControl, GuiTableRow, GetAbsoluteRow, PutSelected, true, 0);
SAPGuiCmd1Sub(GuiTableControl, GuiCollection, GetColumns, ElementAt, -1, PutWidth, 2);
```

## SAPGuiCmd1Sub1

Specifies the method or property that is called or set in the object specified in the previous SAPGuiPropIdStr call. The 1 in the name indicates that one parameter is sent.

Use this variation of the SAPGuiCmd command to deal with subtype and SubParameter information only.

 **Note:** For more information about SAP parameters, refer to SAP's publication titled "SAP GUI Scripting API for the Windows and Java Platforms".

### Syntax

```
SAPGuiCmd1Sub1( const char* Type, const char* SubPropType, const char* FuncName, const char*
SubFuncName, const char* Param, const char* SubParam);
```

### Return Value

### Parameters

Parameter	Description
Type	Type of object.
SubPropType	The type of the sub-property.
FuncName	Function or method/property related to the object.
SubFuncName	Function name in the collection array.
Param	The first parameter to send.
SubParam	The parameter to be sent to the SubFunction.

### Example


```
//Call GuiTableControl class of type
//GuiTableRow. Call GetAbsoluteRow with
//a value of 0 and put a value of True.
```

## Language Reference Commands

```
SAPGuiPropIdStr("wnd[0]/usr/tblMPP400100TC3000");  
SAPGuiCmd1Sub1(GuiTableControl, GuiTableRow, GetAbsoluteRow, PutSelected, true, 0);  
SAPGuiCmd1Sub(GuiTableControl, GuiCollection, GetColumns, ElementAt, -1, PutWidth, 2);
```

### SAPGuiCmd2

Specifies the method or property that is called or set in the object specified in the previous SAPGuiPropIdStr call. The 2 in the name indicates that two parameters are sent.

 Note: For more information about SAP parameters, refer to SAP's publication titled "SAP GUI Scripting API for the Windows and Java Platforms".

#### Syntax

```
SAPGuiCmd2( const char* Type, const char* FuncName, const char* Param1, const char* Param2);
```

#### Return Value

#### Parameters


Parameter	Description
Type	Type of object.
FuncName	Function or method/property related to the object.
Param1	The first parameter to send.
Param2	The second parameter to send.

#### Example

```
//Call SetCurrentCell with two parameters  
SAPGuiPropIdStr("wnd[0]/usr/subSA_0100_1:SAPLEXAMPLE_ENTRY_SCREEN:  
0200/subSA_200_2:SAPLEXAMPLE_ENTRY_SCREEN:  
2000/cntlCCCONTAINER/shellcont/shell");  
SAPGuiCmd2(GuiCtrlGridView, SetCurrentCell, -1, "SEATSOCC");  
SAPGuiCmd0(GuiCtrlGridView, ClearSelection);  
SAPGuiCreateColl(GuiCollection, CreateGuiCollection, coll1);  
SAPGuiCmd1Coll(GuiCollection, Add, coll1, "PRICE");  
SAPGuiCmd1Coll(GuiCollection, Add, coll1, "SEATSMAX");  
SAPGuiCmd1Coll(GuiCollection, Add, coll1, "SEATSOCC");  
SAPGuiCmd1(GuiCtrlGridView, PutSelectedColumns, coll1);  
SAPGuiDestroyColl(GuiCollection, coll1);  
  
SAPGuiPropIdStr("wnd[0]/tbar[0]/btn[3]");  
SAPGuiCmd0(GuiButton, Press);  
SAPGuiCheckScreen("BIBS", "SAPLEXAMPLE_ENTRY_SCREEN", "Style Guide: Alv grid");
```

### SAPGuiCmd3

Specifies the method or property that is called or set in the object specified in the previous SAPGuiPropIdStr call. The 3 in the name indicates that three parameters are sent.

 Note: For more information about SAP parameters, refer to SAP's publication titled "SAP GUI Scripting API for the Windows and Java Platforms".

### Syntax

```
SAPGuiCmd3( const char* Type, const char* FuncName, const char* Param1, const char* Param2,
const char* Param3);
```

### Return Value

### Parameters

Parameter	Description
Type	Type of object.
FuncName	Function or method/property that is related to the object.
Param1	The first parameter to send.
Param2	The second parameter to send.
Param3	The third parameter to send.

### Example

```
//Resize the main window
SAPGuiPropIdStr("wnd[0]");
SAPGuiCmd3(GuiMainWindow, ResizeWorkingPane, 94, 24, false);
```

## SAPGuiConnect

Specifies to which server description a connection should be made.

### Syntax

```
HRESULT SAPGuiConnect( PLAYER_INFO* s_info, char* server description);
```

### Return Value

### Parameters

Parameter	Description
s_info	Structure used by each virtual user.
server description	String that matches a server in the SAPLogon specifications.

### Example

```
//Connect to the SAP server named testsap620
SAPGuiConnect( s_info, "testsap620");
SAPGuiVerCheckStr("6205.132.36");
```

## SAPGuiContentCheck

Compares data from an SAP server returned control with input string based on the comparison options.

### Syntax

```
int SAPGuiContentCheck(const char* id, const char* type, const char* searchString, Bool
bCaseSensitive, SAP_CONTENTCHECK_OPTION nType);
```

## Language Reference Commands

### Return Value

- 1 When an error occurs, for example, the control does not exist.
- 0
  - If the content and the input string are identical (nType = ENTIRE)
  - If the input string is prefix of content (nType = PREFIX)
  - If the input string is suffix of content (nType = SUFFIX)
  - If the input string is substring of content (nType = SUBSTRING)
- 1
  - If the content and the input string are not identical (nType = ENTIRE)
  - If the input string is not prefix of content (nType = PREFIX)
  - If the input string is not suffix of content (nType = SUFFIX)
  - If the input string is not substring of content (nType = SUBSTRING)

### Parameters

Parameter	Description										
id	The SAP control ID.										
type	The SAP control type.										
searchString	A character string specifying a content to search for in the control's text property.										
bCaseSensitive	Case sensitive or case insensitive comparison.										
nType	<i>SAP_CONTENTCHECK_OPTION</i> Type corresponding to the comparison options available on the QALoad Script Development Workbench Convert Options wizard. Valid values are: <table border="1"><thead><tr><th>Value</th><th>Description</th></tr></thead><tbody><tr><td>ENTIRE</td><td>Compare entire SAP text</td></tr><tr><td>PREFIX</td><td>Compare SAP text prefix</td></tr><tr><td>SUFFIX</td><td>Compare SAP text suffix</td></tr><tr><td>SUBSTRING</td><td>Compare SAP text substring</td></tr></tbody></table>	Value	Description	ENTIRE	Compare entire SAP text	PREFIX	Compare SAP text prefix	SUFFIX	Compare SAP text suffix	SUBSTRING	Compare SAP text substring
Value	Description										
ENTIRE	Compare entire SAP text										
PREFIX	Compare SAP text prefix										
SUFFIX	Compare SAP text suffix										
SUBSTRING	Compare SAP text substring										


### Example

```
int n;  
....  
...  
n = SAPGuiGetContentCheck("wnd[0]/usr/txtRSYST-BNAME","GuiTextField","qa", false, PREFIX);  
RR_printf("return value = %d", n);  
...  
..
```

## SAPGuiCreateColl

Specifies the method or property that is called or set in the object specified in the previous SAPGuiPropIdStr call.

This call creates a collection with the name specified by Coll.

 Note: For more information about SAP parameters, refer to SAP's publication titled "SAP GUI Scripting API for the Windows and Java Platforms".

### Syntax

```
SAPGuiCreateColl( char* Type, char* FuncName, ISapGenericCollectionPtr Coll)
```

### Return Value

### Parameters

Parameter	Description
Type	Type of object.
FuncName	Function or method/property related to the object.
Coll	Collection name of collection.

### Example

```
SAPGuiCreateColl(GuiCollection, CreateGuiCollection, coll1);

SAPGuiPropIdStr("wnd[0]/usr/subSA_0100_1:
    SAPLEXAMPLE_ENTRY_SCREEN:0200/subSA_200_2:
    SAPLEXAMPLE_ENTRY_SCREEN:2000/cntlCCCONTAINER/shellcont/shell");

SAPGuiCmd2(GuiCtrlGridView, SetCurrentCell, -1, "SEATSOCC");
SAPGuiCmd0(GuiCtrlGridView, ClearSelection);


//Multiple selections of columns creates a collection for the selection of columns
SAPGuiCreateColl(GuiCollection, CreateGuiCollection, coll1);
SAPGuiCmd1Coll(GuiCollection, Add, coll1, "PRICE");
SAPGuiCmd1Coll(GuiCollection, Add, coll1, "SEATSMAX");
SAPGuiCmd1Coll(GuiCollection, Add, coll1, "SEATSOCC");
SAPGuiCmd1(GuiCtrlGridView, PutSelectedColumns, coll1);
SAPGuiDestroyColl(GuiCollection, coll1);

SAPGuiPropIdStr("wnd[0]/tbar[0]/btn[3]");
SAPGuiCmd0(GuiButton, Press);
SAPGuiCheckScreen( "BIBS", "SAPLEXAMPLE_ENTRY_SCREEN", "Style Guide: Alv grid" );
```

## SAPGuiDestroyColl

Specifies the method or property that is called or set in the object specified in the previous SAPGuiPropIdStr call.

This call destroys a collection and decrements reference count.

 Note: For more information about SAP parameters, refer to SAP's publication titled "SAP GUI Scripting API for the Windows and Java Platforms".

### Syntax

```
SAPGuiDestroyColl( const char* Type, ISapGenericCollectionPtrColl );
```

### Return Value

Parameters

Parameter	Description
Type	Type of object.
Coll	Collection name of collection

Example


```
SAPGuiDestroyColl(GuiCollection, coll1);

SAPGuiPropIdStr("wnd[0]/usr/subSA_0100_1:SAPLEXAMPLE_ENTRY_SCREEN:
    0200/subSA_200_2:SAPLEXAMPLE_ENTRY_SCREEN:
    2000/cntlCCCONTAINER/shellcont/shell");
SAPGuiCmd2(GuiCtrlGridView, SetCurrentCell, -1, "SEATSOCC");
SAPGuiCmd0(GuiCtrlGridView, ClearSelection);
SAPGuiCreateColl(GuiCollection, CreateGuiCollection, coll1);
SAPGuiCmd1Coll(GuiCollection, Add, coll1, "PRICE");
SAPGuiCmd1Coll(GuiCollection, Add, coll1, "SEATSMAX");
SAPGuiCmd1Coll(GuiCollection, Add, coll1, "SEATSOCC");
SAPGuiCmd1(GuiCtrlGridView, PutSelectedColumns, coll1);
//Multiple selections of columns
//destroys a collection that was
//created by a selection of columns
SAPGuiDestroyColl(GuiCollection, coll1);

SAPGuiPropIdStr("wnd[0]/tbar[0]/btn[3]");
SAPGuiCmd0(GuiButton, Press);
SAPGuiCheckScreen( "BIBS", "SAPLEXAMPLE_ENTRY_SCREEN", "Style Guide: Alv grid" );
```

SAPGuiGetControlText

Extracts data from a SAP server returned control.

 Note: For more information about SAP parameters, refer to SAP's publication titled "SAP GUI Scripting API for the Windows and Java Platforms".

Syntax

```
char* SAPGuiGetControlText(const char id, const char* type);
```

Return Value

The string (null-terminated) of characters containing the text of an SAP control.

SAPGuiGetControlText allocates enough space in the parameter passed in as the string buffer to hold the string (including the NULL). Please remember to free any memory after using the returned string. Any memory created with this command that is not explicitly freed results in a memory leak.

Parameters

Parameter	Description
id	The SAP control ID.
type	The SAP control type.

Example

```
char *p;
....
```


```

...
p = SAPGuiGetControlText("wnd[0]/usr/txtRSYST-MANDT", "GuiTextField");
RR_printf("text = %s", p);
...
..
free(p);

```

## SAPGuiGetUniqueString

Extracts data from an SAP server returned control that occurs between the left and right input strings.

 **Note:** For more information about SAP parameters, refer to SAP's publication titled "SAP GUI Scripting API for the Windows and Java Platforms".

### Syntax

```
char* SAPGuiGetUniqueString (const char id, const char* type, const char* left, const char* right);
```

### Return Value

The string (null-terminated) of characters between the left and right search strings.

NULL if either the left or right search strings are not found, an error message will also be given.

NULL if the left search string and the right search string convert all text property of the SAP control.

SAPGuiGetUniqueString allocates enough space in the parameter passed in as the string buffer to hold the string (including the NULL). Please remember to free any memory after using the returned string. Any memory created with this command that is not explicitly freed results in a memory leak.

### Parameters

Parameter	Description
id	The SAP control ID.
type	The SAP control type.
left	A string containing the left search string.
right	A string containing the right search string.

### Example

```

char *p;
...
...
p = SAPGuiGetUniqueString("wnd[0]/usr/txtRSYST-BNAME", "GuiTextField", "qa", "23");
RR_printf("String value = %s", p);
...
..
free(p);

```

## SAPGuiPropIdStr

Specifies the object ID string to use with subsequent SAPGui calls.

This object ID remains in effect until another call to SAPGuiPropIdStr is made.

### Syntax

```
SAPGuiPropIdStr( char* Object_ID );
```

### Return Value

### Parameters

Parameter	Description
Object_ID	String used for subsequent SAPGui command calls.

### Example

```
//Set the object ID to "wnd[0]"
SAPGuiPropIdStr("wnd[0]");
SAPGuiCmdl(GuiMainWindow, SendVKey, 0);
SAPGuiCheckScreen("SESSION_MANAGER", "SAPLSMTR_NAVIGATION", "SAP Easy Access");
```

## SAPGuiPropIdStrExists

Specifies the object ID string to use with subsequent SAPGui calls.

This object ID remains in effect until another call to SAPGuiPropIdStr or SAPGuiPropIdStrExists is made.

### Syntax

```
SAPGuiPropIdStrExists (char* Object_Id);
```

### Return Value

### Parameters

Parameter	Description
Object_Id	String used for subsequent SAPGui command calls.

### Example

```
SAPGuiCheckScreen("S000", "SAPMSYST", "SAP");
DO_SLEEP(3);
SAPGuiPropIdStrExists("wnd[1]/usr/radMULTI_LOGON_OPT2");
    SAPGuiCmd0(GuiRadioButton, Select);
    SAPGuiCmd0(GuiRadioButton, SetFocus);
    SAPGuiPropIdStr("wnd[1]/tbar[0]/btn[0]");
    SAPGuiCmd0(GuiButton, Press);
    SAPGuiCheckScreen("S000", "SAPMSYST", "License Information for Multiple Logon");
SAPGuiPropIdStrExistsEnd("wnd[1]/usr/radMULTI_LOGON_OPT2");
```

## SAPGuiPropIdStrExistsEnd

Marks the end of the block of code that is executed if the condition in a prior SAPGuiPropIdStrExists command is true.

### Syntax

```
SAPGuiPropIdStrExistsEnd (char* Object_Id);
```



## Return Value

### Parameters


Parameter	Description
Object_Id	String used for matching <code>SAPGuiPropIdStrExists</code> command calls.

### Example

```
SAPGuiCheckScreen("S000", "SAPMSYST", "SAP");
DO_SLEEP(3);
SAPGuiPropIdStrExists("wnd[1]/usr/radMULTI_LOGON_OPT2");
    SAPGuiCmd0(GuiRadioButton, Select);
    SAPGuiCmd0(GuiRadioButton, SetFocus);
    SAPGuiPropIdStr("wnd[1]/tbar[0]/btn[0]");
    SAPGuiCmd0(GuiButton, Press);
    SAPGuiCheckScreen("S000", "SAPMSYST", "License Information for Multiple Logon");
SAPGuiPropIdStrExistsEnd("wnd[1]/usr/radMULTI_LOGON_OPT2");
```

## SAPGuiSessionInfo

Specifies the method or property that is called allowing the script access to the SAP GuiSessionInfo objects.

 **Note:** For more information about SAP parameters, refer to SAP's publication titled "SAP GUI Scripting API for the Windows and Java Platforms".

### Syntax

```
SAPGuiSessionInfo( const char* FuncName, const char* Param1 )
```

### Return Value

### Parameters

Parameter	Description
FuncName	Function or method/property related to the object.
Param1	The first parameter to send.

### Example

In this example, RoundTrip data and Flush data are stored in custom counters

```
int id1, id2, id3, id4;
long lRoundTrips, lFlushes;

id1 = DEFINE_COUNTER("Cumulative Group", "Cumulative RoundTrips", 0, DATA_LONG,
COUNTER_CUMULATIVE);
id2 = DEFINE_COUNTER("Cumulative Group", "Cumulative Flushes", 0, DATA_LONG,
COUNTER_CUMULATIVE);
id3 = DEFINE_COUNTER("Instance Group", "Instance RoundTrips", 0, DATA_LONG,
COUNTER_INSTANCE);
id4 = DEFINE_COUNTER("Instance Group", "Instance Flushes", 0, DATA_LONG, COUNTER_INSTANCE);
```

## Language Reference Commands

```
.  
. .  
//Retrieve the number of round trips  
SAPGuiSessionInfo(GetRoundTrips, lRoundTrips);  
//Retrieve the number of times the buffer is flushed  
SAPGuiSessionInfo(GetFlushes, lFlushes);  
SAPGuiPropIdStr("wnd[1]/usr/btnSPOP-OPTION1");  
SAPGuiCmd0(GuiButton, Press);  
SAPGuiCheckScreen("SESSION_MANAGER", "SAPLSP01", "Log Off" );  
  
COUNTER_VALUE(id1, lRoundTrips);  
COUNTER_VALUE(id2, lFlushes);  
COUNTER_VALUE(id3, lRoundTrips);  
COUNTER_VALUE(id4, lFlushes);
```

### SAPGuiSetCheckScreenWildcard

Specifies the wildcard character that `SAPGuiCheckScreen` uses for wildcard matching.

Although all converted scripts include `SAPGuiSetCheckScreenWildcard ('*')` as one of the first functions, you can specify a different wildcard character to use later in the script.

#### Syntax

```
SAPGuiSetCheckScreenWildcard (unsigned short wildcard);
```

#### Return Value

#### Parameters

Parameter	Description
wildcard	A character to match in <code>SAPGuiCheckScreen</code> .

#### Example

```
//Set the wildcard character to *  
SAPGuiSetCheckScreenWildcard('*');  
SYNCHRONIZE();  
BEGIN_TRANSACTION();  
  
try{  
SAPGuiConnect( s_info, "testsap620");  
SAPGuiVerCheckStr("6205.132.36");  
  
. .  
. .  
}  
  
catch(_com_error e){  
  
. .  
. .  
}
```

## SAPGuiVerCheckStr

Specifies the SAP GUI front end version number at the time the capture file was made.

This information includes the major version, the minor version, and the patch level that was installed at the time of capture. If the information does not match, it may not be possible to do a playback from this capture.

### Syntax

```
SAPGuiVerCheckStr( char* version );
```

### Return Value

### Parameters

Parameter	Description
version	String that includes the major version number, minor version number, and patch level number of the installed SAP client. Format: "Major version.Minor version.Patchlevel"

### Example

```
SAPGuiConnect(s_info, "testsap620");
SAPGuiVerCheckStr("6204.119.32");
```

## SSL

### SSL Commands

#### DO\_Https

Applies to **SSL** requests. Makes a secured request to the server specified by the http\_statement.

#### DO\_SetSSLConnectString

Applies to **SSL** requests. Sets the proxy authorization when accessing **SSL** pages passed through a proxy server (also known as "SSL tunneling").

#### DO\_SSLReuseSession

Applies to **SSL** requests. Re-uses the current session's communication information (session ID) for all page requests within the transaction.

#### DO\_SSLUseCipher

Applies to **SSL** requests. Sets the encryption algorithm for playback.

#### DO\_SSLUseClientCert

Applies to **SSL** requests. Specifies a client certificate to pass upon request while recording **SSL** requests.

#### DO\_SSLUseClientCertPass

Applies to **SSL** requests. Specifies a password (plain text or encrypted) that is needed to read a client certificate.

#### DO\_SSLUseProxy

Applies to **SSL** requests. Specifies a proxy server for all **SSL** requests to be sent through.

## DO\_Https

Applies to **SSL** requests. Makes a secured request to the server specified by the `http_statement`.

This command returns a string containing the HTML response from the secured server.

### Syntax

```
DO_Https ( const char *http_statement );
```

### Return Value

Character: **S**tring containing the response from the secured server.

### Parameters

Parameter	Description
<code>http_statement</code>	A string containing the URL of the secured server and any headers to be sent.


### Example

```
...
...
DO_Https("GET HTTPS://www.yahoo.com HTTP/1.0\r\n"
"Referer: HTTP://company/index.htm\r\n"
"Proxy-Connection: Keep-Alive\r\n"
"User-Agent: Mozilla/3.01 WinNT;I)\r\n"
"Host: www.yahoo.com\r\n"
"Accept: */*\r\n");
...
...
```

## DO\_SetSSLConnectString

Applies to **SSL** requests. Sets the proxy authorization when accessing **SSL** pages passed through a proxy server (also known as "SSL tunneling").

This command will be called for each **SSL** request connecting to a different server.

 **Note:** `DO_SetSSLConnectString` is a deprecated command. It is used internally by `QALoad`. Connection strings are created internally by `QALoad`. In addition, the `DO_SetSSLConnectString` command will be commented out in converted scripts to help create a custom connect string if needed.

### Syntax

```
int DO_SetSSLConnectString ( const char *connectstring );
```

### Return Value

0 if the function is successful.  
1 if the function is unsuccessful.

### Parameters

Parameter	Description
<code>connectstring</code>	A character string specifying the command to be sent to the <b>SSL</b> proxy server to allow <b>SSL</b> requests to be sent. This is in the format "CONNECT

servername:port". The connect string must be terminated by a double CR-LF pair.

**Example**

```

...
...
DO_SetSSLConnectString("CONNECT www.yahoo.com:443 HTTP/ 1.0\n"
"Proxy-authorization: Basic cGZobGFwMDpicm9uaWNh\r\n"
"User-Agent: Mozilla/4.04 [en] (WinNT; U)\r\n\r\n");
DO_Https("GET HTTPS://www.yahoo.com HTTP/1.0\r\n"
"Referer: HTTP://company/index.htm\r\n"
"Proxy-Connection: Keep-Alive\r\n"
"User-Agent: Mozilla/3.01 WinNT;I)\r\n"
"Host: www.yahoo.com\r\n"
"Accept: */*\r\n");
...
...

```

**DO\_SSLReuseSession**

Applies to **SSL** requests. Re-uses the current session's communication information (session ID) for all page requests within the transaction.

DO\_SSL\_ReuseSession is related to the option **Reuse SSL Session ID** check box on the **WWW Advanced** dialog box. The **WWW Advanced** dialog box is accessed from the **Convert Options** wizard by clicking the **Advanced** button.

Place **DO\_SSLReuseSession** before the **BEGIN\_TRANSACTION** statement to use the session ID for all transactions, or place it after the **BEGIN\_TRANSACTION** statement to reuse the session ID only for statements within that transaction.

**Syntax**

```
DO_SSLReuseSession( BOOL bEnable );
```

**Return Value**

Always returns 0

**Parameters**

Parameter	Description
bEnable	Starts (TRUE) or stops (FALSE) the reuse of a session ID.

**Examples**

In the following example, the very first **SSL** connection will establish a **Session ID**, which will be reused again for all **SSL** requests and transactions accessing the same **Web server**:

```

...
...
DO_SSLReuseSession(1);
BEGIN_TRANSACTION();
...
...
END_TRANSACTION();
...
...

```

In the following example, the first SSL connection within a transaction will establish a Session ID, which will be reused again for all SSL requests accessing the same Web Server within the same transaction:


```
...
...
BEGIN_TRANSACTION();
DO_SSLReuseSession(1);
...
...
END_TRANSACTION();
...
...
```

### DO\_SSLUseCipher

Applies to SSL requests. Sets the encryption algorithm for playback.

By default, QALoad scripts negotiate the strongest common SSL cipher for each SSL session. The Convert facility automatically inserts a commented out DO\_SSLUseCipher whenever it encounters an encryption algorithm that changed while recording. You can uncomment this call to force playback to use a specific cipher.

It is possible to change the algorithms, and even choose to have several encryption algorithms in one script.

 Note: DO\_SSLUseCipher is a deprecated command. Cipher selection is done internally by QALoad . If you do not have an encryption license, the listed encryption codes does not work. If you have an export grade license, only 40-bit codes work with your scripts. If you have a 128-bit license, all of the listed codes work with your scripts.

### Encryption Algorithms

The codes for available algorithms are as follows:

Export grade (40 bit):

```
EXP-EDH-RSA-DES-CBC
EXP-EDH-DSS-DES-CBC-SHA
EXP-DES-CBC-SHA
EXP-RC4-MD5
EXP-RC2-CBC-MD5
```

128-bit encryption:

```
RC4-SHA
RC4-MD5
EDH-RSA-DES-CBC3-SHA
EDH-DSS-DES-CBC3-SHA
DES-CBC3-SHA
EDH-RSA-DES-CBC-SHA
EDH-DSS-DES-CBC-SHA
DES-CBC-SHA
DES-CBC3-MD5
DES-CBC-MD5
RC2-CBC-MD5
```

### Syntax

```
int DO_SSLUseCipher(const char *cipher)
```

### Return Value

1 if successful.  
0 if unsuccessful.

### Parameters

Parameter	Description
cipher	A character string representing the encryption algorithm to be used during playback.

### Example

```

...
...
BEGIN_TRANSACTION();
...
...
DO_SSLUseCipher("EXP-RC4-MD5");
...
...
END_TRANSACTION();
...
...

```

### DO\_SSLUseClientCert

Applies to **SSL** requests. Specifies a client certificate to pass upon request while recording **SSL** requests.

QALoad's convert facility uses the name of the certificate used while recording. The certificate can be selected from the QALoad Script Development Workbench Record Options wizard.

#### Syntax

```
int DO_SSLUseClientCert(const char *name);
```

#### Return Value

1 if successful.  
0 if unsuccessful.

#### Parameters

Parameter	Description
name	A string containing the name of the client certificate to use.

### Example

In the following example, the client certificate "qaload\_cl" is used whenever the server requests one.

```
DO_SSLUseClientCert("qaload_cl");
```

### DO\_SSLUseClientCertPass

Applies to **SSL** requests. Specifies a password (plain text or encrypted) that is needed to read a client certificate.

#### Syntax

```
BOOL DO_SSLUseClientCertPass(const char *szPassword);
```

### Return Value

TRUE if successful.  
FALSE if unsuccessful.

### Parameters

Parameter	Description
szPassword	A string containing the password to use.

### Example

```
DO_SSLUseClientCert( "my_passwd" );
```

## DO\_SSLUseProxy

Applies to SSL requests. Specifies a proxy server for all SSL requests to be sent through.

### Syntax

```
int DO_SSLUseProxy ( const char *proxyURL ) ;
```

### Return Value

Always returns 0

### Parameters

Parameter	Description
proxyURL	A character string indicating the servername and port of the proxy server, specified in "servername:port" format.

### Example

```
...  
...  
BEGIN_TRANSACTION();  
...  
...  
DO_UseProxy ( "internet.company.com:80" );  
DO_SSLUseProxy ( "internet.company.com:90" );  
DO_ProxyExceptions( "company.sample.com, "company2.company.com" );  
...  
...
```

## TestPartner

### TestPartner Commands

Since there are no convert or record options for a TestPartner session, these commands do not appear in the [Function Wizard](#).

#### TP\_Init

Used to create an instance of the Test Partner COM object. When an instance is created, the TestPartner application process is loaded and QALoad is able to interface with its functionality. This function must be called before any other function in this library.



### TPExecuteScript

This function is used to execute a script within TestPartner.

### TPExecuteVisualTest

This function is used to execute a visual test within TestPartner.

### TPSetType

This function is used to set the value of a visual test parameter.

### TP\_Uninit

This function is called to release an instance of the TestPartner COM object. Once the instance is released, the TestPartner application process is closed. This function should be called when the test has been completed or aborted.

## TP\_Init

Used to create an instance of the TestPartner COM object. When an instance is created, the TestPartner application process is loaded and QALoad is able to interface with its functionality. This function must be called before any other function in this library.

TP\_Init must occur exactly once per script and must be placed outside of the transaction loop.

### Syntax

```
TP_Init(PPLAYER_INFO *s_info);
```

### Return Value

True/False

### Parameters

Parameter	Description
s_info	A pointer to the PPLAYER_INFO structure for this virtual user.

### Example

```
TP_Init(s_info);
```

 Note: Since there are no convert or record options for a TestPartner session, TestPartner commands do not appear in the [Function Wizard](#).

## TP\_Uninit

This function is called to release an instance of the TestPartner COM object. Once the instance is released, the TestPartner application process is closed. This function should be called when the test has been completed or aborted.

TP\_Uninit must occur exactly once per script, be placed outside of the transaction loop, and occur once in `abort_function` after `printf`.

### Syntax

```
TP_Uninit();
```

### Return Value

N/A

## Parameters

None

## Example

```

    END_TRANSACTION();

    TP_Uninit();
    EXIT();
}
int abort_function(PLOYER_INFO * s_info)
{
    printf("Task id: %i, Abort called!", S_task_id);

    TP_Uninit();
    EXIT();
}

```

 Note: Since there are no convert or record options for a TestPartner session, TestPartner commands do not appear in the [Function Wizard](#).

## TPExecuteScript

This function is used to execute a script within TestPartner.

### Syntax

```
TPExecuteScript(char * username, char * password, char * DSN, char * project, char * script);
```

### Return Value

True/False

### Parameters

Parameter	Description
username	The user name to use when connecting to the TestPartner database.
password	The password to use when connecting to the TestPartner database.
DSN	The data from the DSNConfiguration.ini file in TestPartner 5.4 or 5.6. In TestPartner 5.1, 5.2, or 5.3, this data is from the ODBC System DSN (you might see a DSN name that does not belong to TestPartner). In TestPartner 6.0, this data is from the TestPartner COM object.
project	The project that exists in the associated DSN.
script	The script associated with the project.

### Example

```
TPExecuteScript("Admin", "~encr~010E606B626660", "TestPartner", "Common" , "Script1");
```

 Note: Since there are no convert or record options for a TestPartner session, TestPartner commands do not appear in the [Function Wizard](#).

## TPExecuteVisualTest

This function is used to execute a visual test within TestPartner.

### Syntax

```
TPExecuteVisualTest(char * username, char * password, char * DSN, char * project, char * script);
```

### Return Value

True/False

### Parameters

Parameter	Description
username	The user name to use when connecting to the TestPartner database.
password	The password to use when connecting to the TestPartner database.
DSN	The data from the DSNConfiguration.ini file in TestPartner 5.4 or 5.6. In TestPartner 5.1, 5.2, or 5.3, this data is from the ODBC System DSN (you might see a DSN name that does not belong to TestPartner). In TestPartner 6.0, this data is from the TestPartner COM object.
project	The project that exists in the associated DSN.
script	The script (visual test) associated with the project.

### Example

```
TPExecuteVisualTest("Admin", "admin", "TestPartner", "Common", "Script1");
```

 **Note:** Since there are no convert or record options for a TestPartner session, TestPartner commands do not appear in the [Function Wizard](#).

## TPSetType

This function is used to set the value of a visual test parameter.

### Syntax

```
TPSetType(char * Type, char * ParamName, char * Value);
```

### Return Value

True/False

### Parameters

Parameter	Description
Type	Type of variable. Valid values are: Long, Double, Text, and Boolean
ParamName	Parameter data extracted from TestPartner.
Value	Value entered by user.

### Example

```
TPSetType ("NumberLong", "numberVar1", "2653");
```

## Language Reference Commands

```
TPSetType ("NumberDouble", "numberVar2", "48.62");  
TPSetType ("Text", "TextVar3", "Hello World");  
TPSetType ("Boolean", "BoolVar1", "True");
```

 Note: Since there are no convert or record options for a TestPartner session, TestPartner commands do not appear in the [Function Wizard](#).

## UNIFACE

### UNIFACE Commands

#### BEGIN\_UENTITY

Begins the declaration of the UNIFACE entity.

#### DO\_Logfile\_URB

Controls whether or not to generate a log file showing load test information, such as requests and responses.

#### DO\_URB\_AsciiToHex

Converts the ASCII hexadecimal represented buffer into its binary representation.

#### DO\_URB\_Init

Sets all necessary internal variables needed to load test a UNIFACE script.

#### DO\_URB\_setoprretry

Sets the number of times to retry an operation activation.

#### DO\_URB\_ubin2uf

Converts binary data to a UNIFACE format.

#### DO\_URB\_udbl2uf

Converts a double float to a UNIFACE format.

#### DO\_URB\_uecreate

Creates a UNIFACE environment.

#### DO\_URB\_uedelete

Closes a UNIFACE environment.

#### DO\_URB\_uentcreo

Creates an occurrence and makes it current. Note that this function can only be used with entity parameters and not with occurrence parameters.

#### DO\_URB\_uentoccs

Returns the number of occurrences that exist in an entity.

#### DO\_URB\_uentseto

Makes an occurrence current. Note that this function can only be used with entity parameters and not with occurrence parameters.

**DO\_URB\_ufreeh**

Deletes a handle.

**DO\_URB\_uinstdel**

Deletes a component instance.

**DO\_URB\_uinstnew**

Creates an instance of a component.

**DO\_URB\_uinstopr**

Returns a handle to an operation.

**DO\_URB\_ulist2uf**

Converts an item list to a UNIFACE format.

**DO\_URB\_ulistdel**

Deletes an item.

**DO\_URB\_ulistfree**

Frees a UNIFACE list.

**DO\_URB\_ulistget**

Gets an item.

**DO\_URB\_ulistnew**

Creates an item list.

**DO\_URB\_ulistput**

Puts an item.

**DO\_URB\_ulistputlist**

Copies an item from a specified source to the items of a list.

**DO\_URB\_ulistputx**

Puts an item.

**DO\_URB\_ulong2uf**

Converts a long to a UNIFACE format.

**DO\_URB\_unifree**

Frees memory.

**DO\_URB\_uniname**

Returns the name. Caller supplies allocated memory for name. Field names are not supported.

**DO\_URB\_uopract**

Activates an operation.

**DO\_URB\_uoprprms**

Returns the number of parameters.

**DO\_URB\_uprmdir**

Returns the direction of a parameter.

## Language Reference Commands

### [DO\\_URB\\_uprmgeth](#)

Gets a reference to a parameter of an operation or a field of an entity. Or detaches a parameter from an operation.

### [DO\\_URB\\_uprmtype](#)

Returns the data type of a parameter or entity field.

### [DO\\_URB\\_ustr2uf](#)

Converts a string to a UNIFACE format.

### [DO\\_URB\\_uuf2bin](#)

Converts a UNIFACE format to binary data.

### [DO\\_URB\\_uuf2dbl](#)

Converts a UNIFACE format to a double float.

### [DO\\_URB\\_uuf2list](#)

Converts a UNIFACE format to item list.

### [DO\\_URB\\_uuf2long](#)

Converts a UNIFACE format to a long.

### [DO\\_URB\\_uuf2str](#)

Converts a UNIFACE format to string.

### [END\\_UENTITY](#)

Ends the declaration of a UNIFACE entity.

### [UFIELD](#)

Declares or defines a UNIFACE field.

## [BEGIN\\_UENTITY](#)

Begins the declaration of a Uniface entity.

### [Syntax](#)

```
BEGIN_UENTITY(UNIFACE_ENTITY* entname, char* name, char* model, char* type, char* trxdef);
```

### [Return Value](#)

### [Parameters](#)

Parameter	Description
entname	The pointer to the UNIFACE_ENTITY structure.
name	The name of the Uniface entity.
model	The name of the Uniface model.
type	The type of the Uniface entity.
trxdef	The definitions of the transactions that are defined for the entity.



## DO\_URB\_Init

Sets all necessary internal variables needed to load test a Uniface script.

### Syntax

```
long DO_URB_Init(PLOYERINFO *s_info);
```

### Return Value

0 (zero)

### Parameters

Parameter	Description
s_info	Pointer to a PLOYERINFO structure.

### Example

```
DO_URB_Init( s_info );
```

## DO\_URB\_setoprretry

Sets the number of times to retry an operation activation.

### Syntax

```
long DO_URB_setoprretry(int Retries, int Sleep);
```

### Return Value

0 (zero)

### Parameters

Parameter	Description
Retries	Number of times to retry operation.
Sleep	Time to sleep between retries.

## DO\_URB\_ubin2uf

Converts binary data to a Uniface format.

### Syntax

```
long DO_URB_ubin2uf(int nHandle,int seqNr,char extData,long nLen);
```

### Return Value

0 = successful

<>0 = not successful

### Parameters

Parameter	Description
nHandle	Integer handle to an operation or entity.
seqNr	Integer sequence number.



extData	Char external binary data.
nLen	Long external data length.

### Example

```
strcpy( urb_buffer, "0212035903107248");
DO_URB_AsciiToHex( urb_buffer );
DO_URB_ubin2uf( 4, 8, urb_buffer, 8 );
```

## DO\_URB\_udbl2uf

Converts a double float to a Uniface format.

### Syntax

```
DO_URB_udbl2uf( nHandle, seqNr, dData );
```

### Return Value

0 = successful

<>0 = not successful

### Parameters

Parameter	Description
nHandle	Integer handle to an operation or entity.
seqNr	Integer sequence number.
dData	External double float data.

### Example

```
DO_URB_udbl2uf( 3, 1, 12345 );
```

## DO\_URB\_uecreate

Creates a Uniface environment.

This function sets up a Uniface environment based on the configuration parameters: command line, assignment file, and working directory. Only one Uniface environment is allowed per process. The application start-up shell parameter `apsName` is ignored.

### Syntax

```
DO_URB_uecreate( runmode, hInstance, cmdLine, asnName, apsName, workDir, envHandle )
```

### Return Value

1 = Success

-1 = Load Error

-2 = License Error

-4 = Allocation Error

### Parameters

Parameter	Description
-----------	-------------

## Language Reference Commands

runMode	How Uniface is executed (batch or interactive). Always set this to 1.
hInstance	Instance handle. hInstance can be set to 0.
cmdLine	Command line.
asnName	.asn file name.
apsName	.aps file name.
workDir	Working directory.
envHandle	Uniface environment handle.

### Example

```
DO_URB_ucreate( 1, 0, "/ini=c:\\usys72\\bin\\usys.ini /pri=48",  
"c:\\u@training\\formula1\\formula1.asn", "", "c:\\u@training\\formula1\\formula1", 0 );
```

## DO\_URB\_udelete

Closes a Uniface environment.

### Syntax

```
long DO_URB_udelete(int envHandle,int level);
```

### Return Value

- 1 = Success
- 1 = Load Error
- 2 = License Error
- 4 = Allocation Error

### Parameters

Parameter	Description
envHandle	Uniface environment handle
level	Shutdown level.

### Example

```
...  
...  
DO_URB_ucreate( 1, 0, "/ini=c:\\usys72\\bin\\usys.ini /pri=48",  
"c:\\u@training\\formula1\\formula1.asn", "", "c:\\u@training\\formula1\\formula1", 0 );  
...  
...  
...  
DO_URB_udelete( 0, -1 );  
...  
...
```

## DO\_URB\_uentcreo

Creates an occurrence and makes it current. Note that this function can only be used with entity parameters and not with occurrence parameters.

### Syntax

```
long DO_URB_uentcreo(int nHandle, long occNr);
```

### Return Value

0 = successful

<>0 = not successful

### Parameters

Parameter	Description
nHandle	Handle to the entity.
occNr	Sequence number of the occurrence.

### Example

```
DO_URB_uinstnew( 0, "S_ANY", "", "", "", 1, "", 1);
DO_URB_uinstopr( 1, "STORE ", 0, 2 ); |
DO_URB_uprmgeth( 2, 1, FALSE, 3 ); /* get an entity handle */
DO_URB_uentcreo( 3, 1 ); /* creates first occurrence */
DO_URB_ustr2uf( 3, 1, "Field 1 data" );
DO_URB_ustr2uf( 3, 2, "Field 2 data" );
...
...
DO_URB_ufreeh( 3 );
DO_URB_ufreeh( 2 );
...
...
```

## DO\_URB\_uentoccs

Gets the number of occurrences that exist in an entity.

### Syntax

```
long DO_URB_uentoccs(int nHandle, long *occNr);
```

### Return Value

0 = success

<>0 = not successful

### Parameters

Parameter	Description
nHandle	Handle to a Uniface entity.
occNr	(output) Number of occurrences that exist in the entity.

## DO\_URB\_uentseto

Makes an occurrence current. Note that this function can only be used with entity parameters and not with occurrence parameters.

### Syntax

```
long DO_URB_uentseto(int nHandle,long occNr);
```

### Return Value

0 = successful

<>0 = not successful

### Parameters

Parameter	Description
nHandle	Handle to an entity.
occNr	Sequence number of the occurrence.

### Example

```
char *pString;
DO_URB_uinstnew( 0, "S_ANY", "", "", 1, "", 1);
DO_URB_uinstopr( 1, "RETRIEVE ", 0, 2 );
DO_URB_uopract( 2 );
DO_URB_uprmgeth( 2, 1, FALSE, 3 ); /* get an entity handle */
DO_URB_uentseto( 3, 1 ); /* make occurrence 1 current*/
DO_URB_uuf2str( 3, 1, pString );
...
... /* do some manipulation with the returned string */
...
DO_URB_unifree( 3, pString ); /* free the memory */
DO_URB_ufreeh( 3 );
DO_URB_ufreeh( 2 );
```

## DO\_URB\_ufreeh

Deletes a handle.

### Syntax

```
long DO_URB_ufreeh(int nHandle);
```

### Return Value

0 = success

<>0 = not successful

### Parameters

Parameter	Description
nHandle	Any handle. Parameter hAny is always set to 0.

### Example

```
DO_URB_uinstnew( 0, "S_RACE", "", "", 1, "", 1);
DO_URB_uinstopr( 1, "LIST", 0, 2 );
...
```

```
...
DO_URB_ufreeh( 2 );
```

## DO\_URB\_uinstdel

Deletes a component instance.

### Syntax

```
long DO_URB_uinstdel(int nHandle);
```

### Return Value

0 = successful

<>0 = not successful

### Parameters

Parameter	Description
nHandle	Handle to a component instance.

### Example

```
...
...
DO_URB_uinstnew( 0, "S_RACE", "", "", 1, "", 1);
...
...
DO_URB_uinstdel( 1 );
DO_URB_ufreeh( 1 )
```

## DO\_URB\_uinstnew

Creates an instance of a component.

The parameter options is UDEFAULT\_COMM\_MODE, USYNC\_COMM\_MODE, and so on. The parameter propList is a NULL-character separated item list. The item list ends in two NULL characters. The parameters compID, and propList are optional.

### Syntax

```
DO_URB_uinstnew(envHandle, compName, compID, instName, options, propList, newHandle);
```

### Return Value

0 = successful

<>0 = not successful

### Parameters

Parameter	Description
envHandle	Uniface environment handle.
compName	Component name.
compID	Component ID.
instName	Instance name.

## Language Reference Commands

options	Options.
propList	Property list.
newHandle	Instance handle.

### Example

```
...
...
DO_URB_ucreate( 1, 0, "/ini=c:\\usys72\\bin\\usys.ini /pri=48",
"c:\\u@training\\formula1\\formula1.asn", "", "c:\\u@training\\formula1\\formula1", 0 );
...
...
DO_URB_uinstnew( 0, "S_RACE", "", "", 1, "", 1);
DO_URB_uinstopr( 1, "LIST", 0, 2 );
```

## DO\_URB\_uinstopr

Returns a handle to an operation.

### Syntax

```
long DO_URB_uinstopr(int nHandle, long oprName, int newHandle);
```

### Return Value

0 = successful

<>0 = not successful

### Parameters

Parameter	Description
nHandle	Handle to a component instance.
oprName	Operation name.
newHandle	Handle to the instance.

### Example

```
...
...
DO_URB_uinstnew( 0, "S_RACE", "", "", 1, "", 1);
DO_URB_uinstopr( 1, "LIST", 0, 2 );
...
...
DO_URB_ufreeh( 2 );
```

## DO\_URB\_uinst2uf

Converts an item list to a Uniface format.

### Syntax

```
long DO_URB_uinst2uf(int nHandle, int SeqNr, int hList);
```

### Return Value

0 = successful

<>0 = not successful

### Parameters

Parameter	Description
nHandle	Handle to an operation or entity.
SeqNr	Sequence number.
hList	Handle to item list.

### Example

```
DO_URB_uinstnew(0,"S_SERVICE","", "",1,"",1);
DO_URB_uinstopr(1, "DO_SOMETHING", 0, 2);
...
...
DO_URB_ulistnew( 2, 3 ); /* FIELDS */
DO_URB_ulistput( 3, UITEM_OPTION_NONE, 1, "", "TRACK_NAME" );
DO_URB_ulistput( 3, UITEM_OPTION_NONE, 2, "", "TRACK_MAP" );
...
DO_URB_ulist2uf( 2, 3, 3 ); /* Field Name "FIELDS" */
DO_URB_ufreeh( 3 );
```

### DO\_URB\_ulistdel

Deletes an item.

This function corresponds with the Proc statement delitem. If UITEM\_OPTION\_NONE is specified, a value for index is expected and ID is ignored. If UITEM\_OPTION\_ID or UITEM\_OPTION\_ID\_CASE is specified, index is ignored and a value for ID is expected.

### Syntax

```
long DO_URB_ulistdel(int nHandle, int option, int index, char id);
```

### Return Value

0 = successful

<>0 = not successful

### Parameters

Parameter	Description
nHandle	Handle to an item list.
option	Option (UITEM_OPTION_NONE, UITEM_OPTION_ID or UITEM_OPTION_ID_CASE).
index	Item index.
id	pointer to an item ID.

### Example

```
DO_URB_uinstnew(0,"S_SERVICE","", "",1,"",1);
DO_URB_uinstopr(1, "DO_SOMETHING", 0, 2);
...
...
DO_URB_uopract( 2 );
...

```

## Language Reference Commands

```
...
DO_URB_ulistnew( 2, 3 ); /* FIELDS */
...
...
DO_URB_uuf2list( 2, 3, 3 ); /* Field Name "FIELDS" */
DO_URB_ulistdel( 3, UITEM_OPTION_NONE, 1, "");
DO_URB_ufreeh( 3 );
...
...
```

### DO\_URB\_ulistfree

Frees a Uniface list.

#### Syntax

```
long DO_URB_ulistfree(int Handle);
```

#### Return Value

0 = successful

< 0 = error

See the error descriptions that follow:

- 201 Unknown protocol specified.
- 202 An error was detected in the returned transaction. This error will be sent to the Player as a warning, since it may be normal.
- 203 Invalid length of a parameter.
- 204 A unexpected NULL parameter was passed to a call.
- 205 Invalid entity. The entity passed as a parameter to a call is invalid. It may not have been opened using the DO\_PSV\_open call.
- 206 Invalid field name.
- 207 Invalid hit. The hit used in an update or in a fetch call is not the result of a DO\_PSV\_select call. The hit header is invalid.
- 401 Invalid token found while parsing where clause or aggregate statements.
- 501 No hit.

#### Parameters

Parameter	Description
Handle	Handle to a list to be freed.

### DO\_URB\_ulistget

Gets an item.

This function corresponds with the Proc statement getitem. The parameter option is UITEM\_OPTION\_NONE, UITEM\_OPTION\_ID or UITEM\_OPTION\_ID\_CASE. If UITEM\_OPTION\_NONE is specified, a value for index is expected and ID is ignored. If UITEM\_OPTION\_ID or UITEM\_OPTION\_ID\_CASE is specified, index is ignored and a value for ID is expected.

#### Syntax

```
DO_URB_ulistget(int nHandle, UnifaceURBListOptionEnum option, int index, char* id, char** pItem)
```

#### Return Value

0 = successful



<>0 not successful

### Parameters

Parameter	Description								
nHandle	Handle to an item list.								
option	<p><i>UnifaceURBListOptionEnum</i></p> <p>List option. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>UITEM_OPTION_NONE</td> <td>Delete matching item index value. No item ID required</td> </tr> <tr> <td>UITEM_OPTION_ID</td> <td>Delete item ID value. No item index required</td> </tr> <tr> <td>UITEM_OPTION_ID_CASE</td> <td>Delete item ID by case value. No item index required</td> </tr> </tbody> </table>	Value	Description	UITEM_OPTION_NONE	Delete matching item index value. No item ID required	UITEM_OPTION_ID	Delete item ID value. No item index required	UITEM_OPTION_ID_CASE	Delete item ID by case value. No item index required
Value	Description								
UITEM_OPTION_NONE	Delete matching item index value. No item ID required								
UITEM_OPTION_ID	Delete item ID value. No item index required								
UITEM_OPTION_ID_CASE	Delete item ID by case value. No item index required								
index	Item index.								
id	Pointer to an item ID.								
pItem	Item								

### Example

```
char *pItem;
...
...
DO_URB_uinstnew(0, "S_SERVICE", "", "", 1, "", 1);
DO_URB_uinstopr(1, "DO_SOMETHING", 0, 2);
...
...
DO_URB_uopract( 2 );
...
DO_URB_ulistnew( 2, 3 ); /* FIELDS */
...
DO_URB_uuf2list( 2, 3, 3 ); /* Field Name "FIELDS" */
DO_URB_ulistget( 3, UITEM_OPTION_NONE, 1, "", &pItem );
...
/* use pItem */
DO_URB_unifree( 3, pItem );
DO_URB_ufreeh( 3 );
...
...
```

### DO\_URB\_ulistnew

Creates an item list.

#### Syntax

```
long DO_URB_ulistnew(int nHandle, int newHandle);
```

#### Return Value

0 = successful

<>0 not successful

Parameters

Parameter	Description
nHandle	Any handle.
newHandle	A handle to an item list.

Example

```
DO_URB_uinstnew(0,"S_SERVICE","", "",1,"",1);
DO_URB_uinstopr(1, "DO_SOMETHING", 0, 2);
...
...
DO_URB_uolistnew( 2, 3 ); /* FIELDS */
DO_URB_uolistput( 3, UITEM_OPTION_NONE, 1, "", "TRACK_NAME" );
DO_URB_uolistput( 3, UITEM_OPTION_NONE, 2, "", "TRACK_MAP" );
...
DO_URB_uolist2uf( 2, 3, 3 ); /* Field Name "FIELDS" */
DO_URB_ufreeh( 3 );
...
...
```

DO\_URB\_uolistput

Puts an item.

This function corresponds with the Proc statement putitem. The parameter option is UITEM\_OPTION\_NONE, UITEM\_OPTION\_ID or UITEM\_OPTION\_ID\_CASE. If UITEM\_OPTION\_NONE is specified, a value for index is expected and ID is ignored. If UITEM\_OPTION\_ID or UITEM\_OPTION\_ID\_CASE is specified, index is ignored and a value for ID is expected.

Syntax

```
long DO_URB_uolistput(int nHandle, UnifaceURBListOptionEnum option, int index, char* id, char** item);
```

Return Value

0 = successful

<>0 not successful

Parameters

Parameter	Description						
nHandle	Handle to an item list.						
option	<p><i>UnifaceURBListOptionEnum</i></p> <p>List option. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>UITEM_OPTION_NONE</td> <td>Delete matching item index value. No item ID required</td> </tr> <tr> <td>UITEM_OPTION_ID</td> <td>Delete item ID value. No item index required</td> </tr> </tbody> </table>	Value	Description	UITEM_OPTION_NONE	Delete matching item index value. No item ID required	UITEM_OPTION_ID	Delete item ID value. No item index required
Value	Description						
UITEM_OPTION_NONE	Delete matching item index value. No item ID required						
UITEM_OPTION_ID	Delete item ID value. No item index required						

	UITEM_OPTION_ID_CASE Delete item ID by case value. No item index required
index	Item index.
id	Pointer to an item ID.
item	Pointer to an item.

**Example**

```
DO_URB_uinstnew(0, "S_SERVICE", "", "", 1, "", 1);
DO_URB_uinstopr(1, "DO_SOMETHING", 0, 2);
...
...
DO_URB_ulistnew( 2, 3 ); /* FIELDS */
DO_URB_ulistput( 3, UITEM_OPTION_NONE, 1, "", "TRACK_NAME" );
DO_URB_ulistput( 3, UITEM_OPTION_NONE, 2, "", "TRACK_MAP" );
...
DO_URB_ulist2uf( 2, 3, 3 ); /* Field Name "FIELDS" */
DO_URB_ufreeh( 3 );
...
...
```

**DO\_URB\_ulistputlist**

Copies an item from a specified source to the items of a list.

**Syntax**

```
long DO_URB_ulistputlist(int nHandleDst, int index, char *id, int nHandleSrc);
```

**Return Value**

0 = successful  
 <>0 not successful

**Parameters**

Parameter	Description
nHandleDst	Handle to the destination entity.
index	Item index.
id	Pointer to an item ID.
nHandleSrc	Handle to the source entity.

**DO\_URB\_ulistputx**

Puts an item.

**Syntax**

```
long DO_URB_ulistput(int nHandle, char *id, char *item, int sepcntr);
```

**Return Value**

0 = successful

<>0 not successful

Parameters

Parameter	Description
nHandle	Handle to an item list.
id	Pointer to an item ID.
item	Pointer to an item.
sepcntr	Number of separators for list and sublists.

Example

```
DO_URB_ulistnew( 2, 3 ); /* FIELDS */
DO_URB_ulistputx( 3, "ORDER", "52", 2 );
```

DO\_URB\_ulong2uf

Converts a long to a Uniface format.

Syntax

```
long DO_URB_ulong2uf(int nHandle, int seqNr, long lData);
```

Return Value

0 = successful

<>0 not successful

Parameters

Parameter	Description
nHandle	Handle to an operation or entity.
seqNr	Sequence number.
lData	External long data.

Example

```
DO_URB_ulong2uf( 3, 1, 1234 );
```

DO\_URB\_unifree

Frees memory.

Syntax

```
long DO_URB_unifree(int nHandle, void *pvoid);
```

0 = successful

<>0 = not successful

Parameters

Parameter	Description
-----------	-------------

nHandle	Any handle.
pvoid	Pointer to start address of allocated memory.

### Example

```

char *pString;
DO_URB_uinstnew( 0, "S_ANY", "", "", 1, "", 1);
DO_URB_uinstopr( 1, "RETRIEVE ", 0, 2 );
DO_URB_uopract( 2 );
DO_URB_uprmgeth( 2, 1, FALSE, 3 ); /* get an entity handle */
DO_URB_entseto( 3, 1 ); /* make occurrence 1 current*/
DO_URB_uuf2str( 3, 1, pString );
...
...
/* do some manipulation with the returned string */
...
DO_URB_unifree( 3, pString ); /* free the memory */
DO_URB_ufreeh( 3 );
DO_URB_ufreeh( 2 );

```

### DO\_URB\_uniname

Returns the name. Caller supplies allocated memory for name. Field names are not supported.

When working with an operation handle, if seqNr is 0, the name of the operation itself is returned. If seqNr is a legal parameter sequence number, the name of the parameter is returned.

### Syntax

```
long DO_URB_uniname(int nHandle, int seqNr, int maxLen, char name);
```

### Return Value

### Parameters

Parameter	Description
nHandle	Handle to a component instance, operation, or parameter.
seqNr	Sequence number.
maxLen	Size of name.
name	Name of the instance.

### Example

```

char sName[128];
...
...
DO_URB_uinstnew( 0, "S_RACE", "", "", 1, "", 1);
DO_URB_uinstopr( 1, "LIST", 0, 2 );
DO_URB_uniname( 2, 1, 128, sName );
...
...
DO_URB_ufreeh( 2 );

```

## DO\_URB\_uopract

Activates an operation.

### Syntax

```
long DO_URB_uopract(int nHandle);
```

### Return Value

0 = successful

<>0 = not successful

### Parameters

Parameter	Description
nHandle	Handle to an operation.

### Example

```
DO_URB_uinstnew( 0, "S_RACE", "", "", 1, "", 1);
DO_URB_uinstopr( 1, "LIST", 0, 2 );
DO_URB_ustr2uf( 2, 1, "19990101" );
DO_URB_ustr2uf( 2, 2, "19991231" );
DO_URB_uopract( 2 );
...
...
DO_URB_ufreeh( 2 );
```

## DO\_URB\_uoprprms

Returns the number of parameters.

### Syntax

```
long DO_URB_uoprprms(int nHandle, long *pPrmCount);
```

### Return Value

0 = successful

<>0 = not successful

### Parameters

Parameter	Description
nHandle	Handle to an operation
pPrmCount	Pointer to number of parameters

### Example

```
int nParameterCount;
...
...
DO_URB_uinstnew( 0, "S_RACE", "", "", 1, "", 1);
DO_URB_uinstopr( 1, "LIST", 0, 2 );
DO_URB_uoprprms( 2, &nParameterCount );
...
...
DO_URB_ufreeh( 2 );
```

## DO\_URB\_uprmdir

Returns the direction of a parameter.

### Syntax

```
long DO_URB_uprmdir(int nHandle, int seqNr, int *pDirection );
```

### Return Value

0 = successful

<>0 = not successful

### Parameters

Parameter	Description
nHandle	Handle to an operation.
seqNr	Sequence number.
pDirection	Pointer to parameter direction. The parameter pDirection is UPARM_INPUT for IN direction, UPARM_OUTPUT for OUT direction, and (UPARM_INPUT   UPARM_OUTPUT) for INOUT direction. It is not relevant whether or not parameter data is attached to the operation parameter list.

### Example

```
int nDirection;
DO_URB_uinstnew( 0, "S_RACE", "", "", 1, "", 1);
DO_URB_uinstopr( 1, "LIST", 0, 2 );
DO_URB_uprmgeth( 2, 1, FALSE, 3 );
DO_URB_uprmdir( 3, &nDirection);
...
...
DO_URB_ufreeh( 3 );
DO_URB_ufreeh( 2 );
```

## DO\_URB\_uprmgeth

Gets a reference to a parameter of an operation or a field of an entity. Or detaches a parameter from an operation.

### Syntax

```
long DO_URB_uprmgeth(int nHandle, int seqNr, int bDetach, int newHandle );
```

### Return Value

0 = successful

<>0 = not successful

### Parameters

Parameter	Description
nHandle	Handle to an operation or entity parameter.
seqNr	Sequence number.
bDetach	Detach data option (TRUE/FALSE).

newHandle	Handle to a basic parameter, entity parameter or entity field. If parameter bDetach is TRUE, the data of handle nHandle is detached from the constructed handle nHandle. It is not allowed to detach a field from an entity.
-----------	--

**Example**

```
int nType;
DO_URB_uinstnew( 0, "S_RACE", "", "", 1, "", 1);
DO_URB_uinstopr( 1, "LIST", 0, 2 );
DO_URB_uprmgeth( 2, 1, FALSE, 3 );
DO_URB_uprmtype( 3, &nType);
...
...
DO_URB_ufreeh( 3 );
DO_URB_ufreeh( 2 );
```

**DO\_URB\_uprmtype**

Returns the data type of a parameter or entity field.

**Syntax**

```
long DO_URB_uprmtype(int nHandle, int *pType );
```

**Return Value**

- 0 = successful
- <>0 = not successful

**Parameters**

Parameter	Description
nHandle	Handle to a parameter or entity field.
pType	Pointer to data type. The parameter pType is UTYPE_STRING, UTYPE_BOOLEAN, and so on.

**Example**

```
int nType;
DO_URB_uinstnew( 0, "S_RACE", "", "", 1, "", 1);
DO_URB_uinstopr( 1, "LIST", 0, 2 );
DO_URB_uprmgeth( 2, 1, FALSE, 3 );
DO_URB_uprmtype( 3, &nType);
...
...
DO_URB_ufreeh( 3 );
...

```

**DO\_URB\_ustr2uf**

Converts a string to a Uniface format.

**Syntax**

```
long DO_URB_ustr2uf(int nHandle,int seqNr,char *string)
```



### Return Value

0 = successful  
<>0 = not successful

### Parameters

Parameter	Description
nHandle	Handle to an operation or entity.
seqNr	Sequence number.
string	Pointer to an external string data.

### Example

```
DO_URB_uinstnew( 0, "S_RACE", "", "", 1, "", 1);
DO_URB_uinstopr( 1, "LIST", 0, 2 );
DO_URB_uistr2uf( 2, 1, "19990101" );
```

## DO\_URB\_uuf2bin

Converts a Uniface format to binary data.

### Syntax

```
long DO_URB_uuf2bin(int nHandle, int seqNr, char pExData, long *pnLen);
```

### Return Value

0 = successful  
<>0 = not successful

### Parameters

Parameter	Description
nHandle	Handle to an operation or entity.
seqNr	Sequence number.
pExData	External (output) binary data. The parameter pExtData is allocated on the heap. It has to be freed with DO_URB_unifree.
pnLen	Pointer to external data length.

### Example

```
char *pBinaryData;
long nLen;
...
...
DO_URB_uinstnew( 0, "S_ANY", "", "", "", 1, "", 1);
DO_URB_uinstopr( 1, "RETRIEVE", 0, 2 );
DO_URB_uopract( 2 );
DO_URB_uuf2bin ( 2, 4, &pBinaryData, &nLen );
...
...
DO_URB_unifree( 2, pBinaryData );
DO_URB_ufreeh( 2 );
```

## DO\_URB\_uuf2dbl

Converts a Uniface format to a double float.

### Syntax

```
long DO_URB_uuf2dbl(int nHandle,int seqNr,double *pdData);
```

### Return Value

0 = succesful  
<>0 = not successful

### Parameters

Parameter	Description
nHandle	Handle to an operation or entity.
seqNr	Sequence number.
pdData	Pointer to an external double float data.

### Example

```
double dNumber;
...
...
DO_URB_uinstnew( 0, "S_ANY", "", "", "", 1, "", 1);
DO_URB_uinstopr( 1, "RETRIEVE ", 0, 2 );
DO_URB_uopract( 2 );
DO_URB_uuf2dbl ( 2, 2, &dNumber );
...
...
DO_URB_ufreeh( 2 );
```

## DO\_URB\_uuf2list

Converts a Uniface format to item list.

### Syntax

```
long DO_URB_uuf2list(int nHandle, int seqNr, int hList);
```

### Return Value

0 = successful  
<>0 = not successful

### Parameters

Parameter	Description
nHandle	Handle to an operation or entity
seqNr	Sequence number
hList	Create the parameter hList with DO_URB_ulistnew before calling this function. After using the item list, free it using DO_URB_ulistdel

### Example

```
char *pItem;
...
```

```

...
DO_URB_uinstnew(0,"S_SERVICE","", "",1,"",1);
DO_URB_uinstopr(1, "DO_SOMETHING", 0, 2);
...
...
DO_URB_uopract( 2 );
...
...
DO_URB_uulistnew( 2, 3 ); /* FIELDS */
...
DO_URB_uuf2list( 2, 3, 3 ); /* Field Name "FIELDS" */
DO_URB_uulistget( 3, UITEM_OPTION_NONE, 1, "", &pItem );
...
/* use pItem */
DO_URB_unifree( 3, pItem );
DO_URB_ufreeh( 3 );

```

## DO\_URB\_uuf2long

Converts a Uniface format to a long.

### Syntax

```
long DO_URB_uuf2long(int nHandle, int seqNr, long *plData);
```

### Return Value

0 = successful  
<>0 = not successful

### Parameters

Parameter	Description
nHandle	Handle to an operation or entity.
seqNr	Sequence number.
plData	Pointer to external long data.

### Example

```

long lNumber;
...
...
DO_URB_uinstnew( 0, "S_ANY", "", "", "", 1, "", 1);
DO_URB_uinstopr( 1, "RETRIEVE ", 0, 2 );
DO_URB_uopract( 2 );
DO_URB_uuf2long ( 2, 1, &lNumber );
...
...
DO_URB_ufreeh( 2 );
...
...

```

## DO\_URB\_uuf2str

Converts a Uniface format to string.

### Syntax

```
long DO_URB_uuf2str(int nHandle,int SeqNr,char **pExString);
```

### Return Value

0 = successful  
 <>0 = not successful

### Parameters

Parameter	Description
nHandle	Handle to an operation or entity
SeqNr	Sequence number
pExString	External string data. The parameter pExString is allocated on the heap. It has to be freed with DO_URB_unifree.

### Example

```
char *pString;
...
...
DO_URB_uinstnew( 0, "S_ANY", "", "", "", 1, "", 1);
DO_URB_uinstopr( 1, "RETRIEVE ", 0, 2 );
DO_URB_uopract( 2 );
DO_URB_uuf2str ( 2, 3, &pString );
..
..
DO_URB_unifree( 2 , pString );
DO_URB_ufreeh( 2 );
```

## END\_UENTITY

Ends the declaration of a Uniface entity.

### Syntax

```
END_UENTITY(UNIFACE_ENTITY* pointer, UNIFACE_ENTITY* pointee);
```

### Return Value

### Parameters

Parameter	Description
pointer	New pointer for the entity.
pointee	The original pointer used in BEGIN_UENTITY as entname.

### Example

```
END_UENTITY(RACE_FORMULA1, race_formulal);
```

## UFIELD

Declares or defines a Uniface field.

### Syntax

```
UFIELD (char* name, char* type, int size, char* index);
```

## Return Value

## Parameters

Parameter	Description
name	Field name.
type	Data and interface type.
size	Length of the field.
index	If the field is a key for the entity, this field holds the index.

## Example

```
UFIELD( "RACE_ID", "N2", 4, "1.101" );
```

# Winsock

## Winsock Commands

### AddrByte

Returns a byte of an internet address.

### DO\_WSK\_Accept

Accepts an incoming connection on the specified socket.

### DO\_WSK\_Bind

Associates a local name with a connection/socket that is not yet named.

### DO\_WSK\_Closesocket

Closes the specified connection.

### DO\_WSK\_Connect

Establishes a connection with a server.

### DO\_WSK\_Expect

Waits for a unique pattern to occur that should signify the end of the response.

### DO\_WSK\_ExpectAny

Waits for any of the specified patterns to be matched.

### DO\_WSK\_ExpectAnyExpr

DO\_WSK\_ExpectAnyExpr( ) waits for any of the unique patterns specified by the passed UNIX-style regular expressions to occur. The patterns should signify any of the possible ends of the response.

### DO\_WSK\_ExpectExpr

DO\_WSK\_ExpectExpr( ) waits for a unique pattern specified by a UNIX-style regular expression to occur. The pattern should signify the end of the response.

### DO\_WSK\_GetSocket

## Language Reference Commands

Returns the socket handle for the specified connection.

### [DO\\_WSK\\_Getsockname](#)

Gets the local address for a connection.

### [DO\\_WSK\\_HexDecode](#)

Converts hexadecimal characters to binary data suitable for sending to a connection using `DO_WSK_Write()`.

### [DO\\_WSK\\_Init](#)

Initializes internal structures and variables in preparation for a virtual user run.

### [DO\\_WSK\\_Ioctlsocket](#)

Controls the mode of a socket.

### [DO\\_WSK\\_IsReadable](#)

Specifies whether or not the connection has data available to be read.

### [DO\\_WSK\\_IsWriteable](#)

Indicates if the connection is available for writing.

### [DO\\_WSK\\_Listen](#)

Puts the specified socket in listening mode for incoming connections.

### [DO\\_WSK\\_Quiet](#)

Waits for a period of silence, identified by `seconds_of_quiet`, on the named socket.

### [DO\\_WSK\\_Read](#)

Reads the number of bytes identified by `bytes_to_read` from the socket.

### [DO\\_WSK\\_Recv](#)

Receives data from a connected socket.

### [DO\\_WSK\\_Recvfrom](#)

Receives data from a connected or unconnected socket.

### [DO\\_WSK\\_Reorder](#)

`DO_WSK_Reorder()` swaps the byte order of the given integer variable.

### [DO\\_WSK\\_Select](#)

Allows you to determine if a set of sockets are read or writable.

### [DO\\_WSK\\_Send](#)

Sends data to a socket.

### [DO\\_WSK\\_SendAll](#)

Sends a number of strings to a connection.

### [DO\\_WSK\\_Sendto](#)

Sends data on either a connected or unconnected socket to a remote host.

### [DO\\_WSK\\_Setsockopt](#)

Sets options associated with the specified socket.

### [DO\\_WSK\\_Shutdown](#)

Disables the sending or receiving of data on a socket.

#### [DO\\_WSK\\_Socket](#)

Creates a socket and associates it with a connection handle.

#### [DO\\_WSK\\_Write](#)

Writes the number of bytes identified by `bytes_to_write` to the socket from `data_to_send`.

#### [EscapeStr](#)

Converts `^` and null characters into `^^` and `^@`, respectively, so that data with those characters can be passed to `DO_WSK_Send()`, `DO_WSK_Expect()`, or `DO_WSK_ExpectAny()`.

#### [GetLocalAddr](#)

Returns the local address used by a connection in host-byte order.

#### [GetLocalPort](#)

Returns the port bound to for the named socket on the local side of the connection.

#### [GetRemoteAddr](#)

Returns the port connected to on the remote side of a connection.

#### [GetRemotePort](#)

Returns the port connected to on the remote side of a connection.

#### [HiByte](#)

Returns the high-order byte of the passed short integer.

#### [LoByte](#)

Returns the low-order byte of the passed short integer.

#### [Log](#)

Records the character string passed into the log file.

#### [MyByteOrder](#)

`MyByteOrder()` returns the byte order of the machine running the script either of the constants `MSBF` (Most Significant Byte First) or `LSBF` (Least Significant Byte First).

#### [Response](#)

Returns a pointer to the first character in the response buffer.

#### [ResponseLength](#)

Returns the number of characters in the response buffer.

#### [ScanExpr](#)

Scans the scan buffer for a string specified by the UNIX-style regular expression, into the given buffer.

#### [ScanFloat](#)

Scans a floating point value of the given byteorder and length into the argument which should be the address of an appropriate program variable of the same size and type, casted to a `char *`. Valid lengths are 4 or 8. The byteorder should be either specified as either of the constants `MSBF` or `LSBF`.

#### [ScanInt](#)

`ScanInt()` scans an integer of the given byteorder and length into the argument which should be the address of an appropriate program variable of the same size and type, casted to a `char *`. Valid lengths are 1, 2, or 4. The byteorder should be either specified as one of the constants `MSBF` or `LSBF`.

### ScanLenString

ScanLenString( ) expects input of the format [count][string] where length is an integer of the given byteorder and length and string is a string of count bytes. The string will be placed in the given pointer and count, which should be the address of an appropriate integral program variable, casted to a char \*, and to be updated with the count.

### ScanRewind

Resets the scan pointer and length to the beginning and length of the response buffer respectively.

### ScanSkip

Skips the specified number of bytes in the scan buffer.

### ScanString

Scans a string of the given length from the current location in the scan buffer into the given buffer. The scan pointer and length are incremented by the argument length.

### SetTimeout

Sets the number of seconds to wait for subsequent synchronization commands (DO\_WSK\_Expect, DO\_WSK\_ExpectAny, or DO\_WSK\_Read) to be satisfied.

### SetTyperate

Sets the type rate, in characters per second, for data sent on a Telnet connection.

### SkipExpr

Scans the scan buffer for a string specified by the UNIX-style regular expression, and skips ahead over the matched pattern.

### UnEscapeStr

Converts a string with escaped ^ control character sequences to raw text so that it can be manipulated.

## AddrByte

Returns a byte of an internet address.

Only useful in very specific instances, particularly when scripting an FTP client that requires sending the address of the client-side data port as separate bytes.

AddrByte returns the byte of the passed address indicated by which\_byte.

### Syntax

```
unsigned char  
AddrByte(unsigned long address, int which_byte)
```

### Return Value

### Parameters

Parameter	Description
unsigned long address	The address of the client-side data port.
int which byte	The byte to send.



### Example

```

unsigned char byte0, byte1, byte2, byte3;
...
byte0 = AddrByte(GetLocalAddr(S2), 0);
byte1 = AddrByte(GetLocalAddr(S2), 1);
byte2 = AddrByte(GetLocalAddr(S2), 2);
byte3 = AddrByte(GetLocalAddr(S2), 3);

```

### DO\_WSK\_Accept

Accepts an incoming connection on the specified socket.

#### Syntax

```
SOCKET DO_WSK_Accept(int nSocketHandle, int newSocketHandle)
```

#### Return Value

New socket handler if successful

1 if an error occurs

#### Parameters

Parameter	Description
nSocketHandle	Socket handle from a previous call to DO_WSK_Socket.
newSocketHandle	New Socket handle for accepting connections.

#### Example

```
DO_WSK_Accept(S1, S2 );
```

### DO\_WSK\_Bind

Associates a local name with a connection/socket that is not yet named.

#### Syntax

```
DO_WSK_Bind (int nConnectHandle, char * szLocalInetAddr, unsigned short usPort);
```

#### Return Value

#### Parameters

Parameter	Description
nConnectHandle	A connection handle returned from a previous call to DO_WSK_Socket.
szLocalInetAddr	Points to a string containing the Internet address the socket is to bind to. For example, to bind to INADDR_ANY, szLocalInetAddr would point to "0.0.0.0".
usPort	The port to bind to in host byte order. To bind to any (non-specific) port, pass 0.

#### Example

```
DO_WSK_Bind (0, "0.0.0.0", 0);
```

## DO\_WSK\_Closesocket

Closes the specified connection.

### Syntax

```
DO_WSK_Closesocket (int nConnectHandle);
```

### Return Value

### Parameters

Parameter	Description
nConnectHandle	A connection handle returned from a previous call to DO_WSK_Socket.

### Example

```
DO_WSK_Closesocket (0);
```

## DO\_WSK\_Connect

Establishes a connection with a server.

### Syntax

```
int DO_WSK_Connect (int nConnectHandle, char * szServerInetAddr, unsigned short usPort, int nAddressfamily);
```

### Return Value

0 if successful  
-1 if an error occurred.

### Parameters

Parameter	Description
nConnectHandle	Connection handle returned from a previous call to DO_WSK_Socket.
szServerInetAddr	Points to a string containing the Internet address of the server with which to connect.
usPort	The port (in host-byte order) on the server with which to connect.
nAddressfamily	Address family, usually AF_INET.

### Example

```
DO_WSK_Connect ( 0, "172.22.1.130", 53, 2 );
```

## DO\_WSK\_Expect

Waits for a unique pattern to occur that should signify the end of the response.

When the capture file is converted, this pattern is identified automatically. If the response changes, the pattern may need to be adjusted or another synchronization command substituted in the place of `DO_WSK_Expect()`.

### Syntax

```
int DO_WSK_Expect(int nConnectHandle, char *pattern)
```

### Return Value

0 if the pattern was found  
-1 if the timeout interval expired

### Parameters

Parameter	Description
<code>nConnectHandle</code>	A connection handle returned from a previous call to <code>DO_WSK_Socket</code> .
<code>pattern</code>	A string pattern to wait for.

### Example

```
DO_WSK_Expect(S1, "\r\n");
```

## DO\_WSK\_ExpectAny

Waits for any of the specified patterns to be matched.

### Syntax

```
int DO_WSK_ExpectAny(int nConnectHandle, int number_of_patterns, char *pattern1, ...)
```

### Return Value

0-based index of the pattern that was matched first  
-1 if not found.

### Parameters

Parameter	Description
<code>nConnectHandle</code>	The connection number.
<code>number_of_patterns</code>	The number of patterns to follow.
<code>pattern1</code>	The first pattern.

### Example

```
int i;
...
i = DO_WSK_ExpectAny(S1, 3, "this", "that", "the other");
switch(i)
{
case 0: /* do stuff because "this" was matched */ break;
case 1: /* do stuff because "that" was matched */ break;
case 2: /* do stuff because "the other" was matched */ break;
default: /* must have timed out */
}
```

## DO\_WSK\_ExpectAnyExpr

Waits for any of the unique patterns specified by the passed UNIX-style regular expressions to occur.

The patterns should signify any of the possible ends of the response.

### Syntax

```
int DO_WSK_ExpectAnyExpr(int nConnectHandle, int num_expressions, char *expression1, char *expression2, ...)
```

### Return Value

Index of the pattern that was matched (0-based)

-1 if the timeout interval expired.

### Parameters

Parameter	Description
nConnectHandle	A connection handle returned from a previous call to DO_WSK_Socket.
Expression1	String patterns to wait for.

### Example

```
DO_WSK_ExpectAnyExpr(S1, 2, "query failed [0-9]* times", "query succeeded [0-9]* times");
```

## DO\_WSK\_ExpectExpr

Waits for a unique pattern specified by a UNIX-style regular expression to occur. The pattern should signify the end of the response.

### Syntax

```
int DO_WSK_ExpectExpr(int nConnectHandle, char *expression)
```

### Return Value

0 if the pattern is found

-1 if the timeout interval expired

### Parameters

Parameter	Description
nConnectHandle	A connection handle returned from a previous call to DO_WSK_Socket.
expression	A string pattern to wait for.

### Example

```
DO_WSK_ExpectExpr(S1, "the date is [0-9][0-9]/[0-9][0-9]/[0-9][0-9]");
```

## DO\_WSK\_GetSocket

Returns the socket handle for the specified connection.

This allows more complicated examples of determining if multiple sockets are available for writing or if data is available for reading using the select() system call.

### Syntax

```
SOCKET DO_WSK_GetSocket(int ConnectHandle)
```

### Return Value

### Parameters

Parameter	Description
ConnectHandle int	The connection number.

### Example

```
SOCKET x = DO_WSK_GetSocket(S1);
SOCKET y = DO_WSK_GetSocket(S2);
fd_set readfds;
struct timeval timeout;
int maxfds;
timeout.tv_sec = 1;
timeout.tv_usec = 0;
FD_SET(x, &readfds);
FD_SET(y, &readfds);
if(x > y) maxfds = x; else maxfds = y;
select(maxfds+1, &readfds, 0, 0, timeout);
Waits for 1 second for data to be available for reading on connection S1 or S2.
```

## DO\_WSK\_Getsockname

Gets the local address for a connection.

Use this call or DO\_WSK\_Bind prior to a call to GetLocalAddr or GetLocalPort.

### Syntax

```
unsigned short DO_WSK_Getsockname(int nConnectHandle)
```

### Return Value

### Parameters

Parameter	Description
nConnectionHandle	A connection handle from a previous call to DO_WSK_Socket.

### Example

```
DO_WSK_Socket(S1, AF_INET, SOCK_DGRAM, IPPROTO_UDP);
DO_WSK_Bind(S1, "127.0.0.1", ANY_PORT);
fd_set readfds;
DO_WSK_Getsockname(S1);
```

## DO\_WSK\_HexDecode

Converts hexadecimal characters to binary data suitable for sending to a connection using DO\_WSK\_Write().

### Syntax

```
int HexDecode(char *string)
```

### Return Value

Number of bytes in the converted data (one half the number of input bytes)

### Parameters

Parameter	Description
string	A pointer to a buffer to be converted.

### Example

```
char buf[80];
int count;

...

strcpy(buf, "FEEBDAED");
count = DO_WSK_HexDecode(buf);
DO_WSK_Write(S1, buf, count);
```

## DO\_WSK\_Init

Initializes internal structures and variables in preparation for a virtual user run.

### Syntax

```
int DO_WSK_Init(s_info)
```

### Return Value

1 (one)

### Parameters

Parameter	Description
s_info	A pointer to the PLAYER_INFO structure for this virtual user.

### Example

```
DO_WSK_Init (s_info);
```

## DO\_WSK\_Ioctlsocket

Controls the mode of a socket.

### Syntax

```
DO_WSK_Ioctlsocket(int nConnectHandle, unsigned long * argument,
WinsockIOctlSocketCommandEnum command );
```

### Return Value

## Parameters

Parameter	Description								
nConnectHandle	A connection handle returned from a previous call to <code>DO_WSK_Socket</code> .								
argument	<p><i>WinsockIOctlSocketCommandEnum</i></p> <p>The parameter for command. If command is FIONBIO and argument points to a non-zero value, non-blocking mode is enabled. If command is FIONREAD, argument is used to hold the number of bytes that can be read on a socket. If command is SIOCATMARK, argument is used as a return value to determine if all out-of-band data has been read from a socket. TRUE is returned if no out-of-band data is to be read. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>FIONBIO</td> <td>Use with a nonzero second parameter to enable nonblocking mode</td> </tr> <tr> <td>FIONREAD</td> <td>Use to determine the amount of data pending that can be read</td> </tr> <tr> <td>SIOCATMARK</td> <td>Use to determine whether or not all OOB data has been read</td> </tr> </tbody> </table>	Value	Description	FIONBIO	Use with a nonzero second parameter to enable nonblocking mode	FIONREAD	Use to determine the amount of data pending that can be read	SIOCATMARK	Use to determine whether or not all OOB data has been read
Value	Description								
FIONBIO	Use with a nonzero second parameter to enable nonblocking mode								
FIONREAD	Use to determine the amount of data pending that can be read								
SIOCATMARK	Use to determine whether or not all OOB data has been read								
command	The command to perform on the sockets. Valid values are FIONBIO, FIONREAD, and SIOCATMARK.								

## Example

```
// enable non-blocking mode
u_long argument = TRUE;
DO_WSK_ioctlsocket(0, &argument, FIONBIO );
```

## DO\_WSK\_IsReadable

Specifies whether or not the connection has data available to be read.

Returns .

## Syntax

```
int DO_WSK_IsReadable(int ConnectHandle);
```

## Return Value

1 if the connection has data available to be read

0 if there is no data available

-1 if there was an error

## Parameters

Parameter	Description
ConnectHandle int	The connection number.

## Language Reference Commands

### Example

```
do
{
DO_WSK_Read(S1, 4);
}
while (DO_WSK_IsReadable(S1)) ;
//Reads 4 bytes of data at a time until there is no more data to be read.
```

### DO\_WSK\_IsWriteable

Indicates if the connection is available for writing.

#### Syntax

```
int DO_WSK_IsWriteable(int ConnectHandle);
```

#### Return Value

1 if the connection is available for writing

0 if the output queue is full

-1 if there was an error

#### Parameters

Parameter	Description
ConnectHandle int	The connection number.

### Example

```
do
{
DO_SLEEP(1);
}
while (DO_WSK_IsWriteable(S1) == 0) ;
DO_WSK_Send(S1, "stuff");
//Waits until connection S1 is writable before sending "stuff".
```

### DO\_WSK\_Listen

Puts the specified socket in listening mode for incoming connections.

#### Syntax

```
int DO_WSK_Listen(int nSocket);
```

#### Return Value

Always returns 0

#### Parameters

Parameter	Description
nSocket	Socket handle from a previous call to DO_WSK_Socket.

### Example

```
DO_WSK_Listen(S1);
```



## DO\_WSK\_Quiet

Waits for a period of silence, identified by `seconds_of_quiet`, on the named socket.

This can be useful if the response is random or you simply don't know what the response will be.

`DO_WSK_Quiet()` reads whatever characters are available. After characters are read, the `seconds_of_quiet` counter is reset. If a socket is not idle, `DO_WSK_Quiet` cannot complete.

### Syntax

```
int DO_WSK_Quiet(int nConnectHandle, double seconds_of_quiet)
```

### Return Value

Number of bytes read

-1 if an error was encountered

### Parameters

Parameter	Description
<code>nConnectHandle</code>	The connection number.
<code>seconds_of_quiet</code>	The number of seconds of silence to wait for on this connection.

### Example

```
DO_WSK_Quiet(S2, 10);
```

## DO\_WSK\_Read

Reads the number of bytes identified by `bytes_to_read` from the socket.

This can be useful if the response varies in content, but the number of bytes is consistent. It can also be used to build scripts that handle more complicated protocols.

### Syntax

```
int DO_WSK_Read(int nConnectHandle, int bytes_to_read)
```

### Return Value

Number of bytes read

-1 if an error is encountered

### Parameters

Parameter	Description
<code>nConnectHandle</code>	The connection number.
<code>bytes_to_read</code>	The number of bytes to wait for.

### Example

```
DO_WSK_Read(S2, 1024);
```

## DO\_WSK\_Recv

Receives data from a connected socket.

## Language Reference Commands

### Syntax

```
DO_WSK_Recv (int nConnectHandle, char * buffer, int * buffer_length, WinsockRecvFlagsEnum flags, int * pnBytesRecv)
```

### Return Value

### Parameters

Parameter	Description								
nConnectHandle	A connection handle returned from a previous call to DO_WSK_Socket.								
buffer	Buffer to store received data.								
buffer_length	Length of buffer.								
flags	<i>WinsockRecvFlagsEnum</i> Used to control the way in which the call is made. Valid values are: <table><thead><tr><th>Value</th><th>Description</th></tr></thead><tbody><tr><td>MSG_PEEK</td><td>Peek flag</td></tr><tr><td>MSG_OOB</td><td>OOB flag</td></tr><tr><td>0</td><td>Normal</td></tr></tbody></table>	Value	Description	MSG_PEEK	Peek flag	MSG_OOB	OOB flag	0	Normal
Value	Description								
MSG_PEEK	Peek flag								
MSG_OOB	OOB flag								
0	Normal								
pnBytesRecv	Used to return the number of bytes received.								

### Example

```
char buffer[1024];  
int nBytesReceived;  
DO_WSK_Recv (0, buffer, 1024, 0, &nBytesReceived);
```

## DO\_WSK\_Recvfrom

Receives data from a connected or unconnected socket.

### Syntax

```
DO_WSK_Recvfrom (int nConnectHandle, char * buffer, int buffer_length, WinsockRecvFlagsEnum flags, struct sockaddr *from_address, int * pnBytesRecv );
```

### Return Value

### Parameters

Parameter	Description
nConnectHandle	A connection handle returned from a previous call to DO_WSK_Socket.
buffer	Buffer to store received data.
buffer_length	Length of buffer.

	<p><i>WinsockRecvFlagsEnum</i></p> <p>Used to control the way in which the call is made. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>MSG_PEEK</td> <td>Peek flag</td> </tr> <tr> <td>MSG_OOB</td> <td>OOB flag</td> </tr> <tr> <td>0</td> <td>Normal</td> </tr> </tbody> </table>	Value	Description	MSG_PEEK	Peek flag	MSG_OOB	OOB flag	0	Normal
Value	Description								
MSG_PEEK	Peek flag								
MSG_OOB	OOB flag								
0	Normal								
flags									
from_address	Optional. If not NULL, it is used to hold the address of the sender upon function return.								
pnBytesRecv	Used to return the number of bytes received.								

### Example

```
char buffer[1024];
int nBytesReceived;
DO_WSK_Recvfrom(0, buffer, 1024, 0, NULL, &nBytesReceived);
```

## DO\_WSK\_Reorder

DO\_WSK\_Reorder() swaps the byte order of the given integer variable.

### Syntax

```
void DO_WSK_Reorder(int size, void *value)
```

### Return Value

None

### Parameters

Parameter	Description
size	Size of the integer variable (1, 2, or 4 bytes).
value	The address of the variable.

### Example

```
int var;
var = 2;
DO_WSK_Reorder(sizeof(int), (char *)&var);
DO_WSK_Send(S2, EscapeStr((char *)&var, sizeof(int)));
```

## DO\_WSK\_Select

Allows you to determine if a set of sockets are read or writable

### Syntax

```
Int DO_WSK_Select(fd_set *readfds, fd_set *writefds, fd_set *selectfds, struct timeval *timeout);
```

Return Value

Parameters

Parameter	Description
readfds	Set of sockets (struct fd_set) to check for read.
writefds	Set of sockets (struct fd_set) to check for write.
selectfds	Set of sockets (struct fd_set) to check for errors.
timeout	Maximum time for select to wait using timeval struct.

Example

```
fd_set *Set1 = malloc(sizeof(fd_set));
fd_set *Set2 = malloc(sizeof(fd_set));
fd_set *Set3 = malloc(sizeof(fd_set));
struct timeval *Time = malloc(sizeof(fd_set));

....

....

DO_WSKk_Socket(S3, AF_INET, SOCK_STREAM, IPPROTO TCP);
DO_WSK_Bind(S3, ANY_ADDR, ANY_PORT);
DO_WSK_Getsockname(S3);
DO_WSK_Connect(S3, "172.22.11.25", 80, AF_INET);

Set1->fd_count = 1;
Set2->fd_count = 1;
Set3->fd_count = 1;
Set1->fd_array[0] = S3;
Set2->fd_array[0] = S3;
Set3->fd_array[0] = S3;
Time->tv_sec = 1;
DO_WSK_Select(Set1, Set2, Set3, Time);
free(Set1);
free(Set2);
free(Set3);
free(Time);
```

DO\_WSK\_Send

Sends data to a socket.

Syntax

```
DO_WSK_Send(int nConnectHandle, char *data)
```

Return Value

0 if successful

Parameters

Parameter	Description
nConnectHandle	A connection handle returned from a previous call to DO_WSK_Socket.
data	Data to be sent.

### Example

```
DO_WSK_Send(S1, "This is sent to connection S1");
```

## DO\_WSK\_SendAll

Sends a number of strings to a connection.

### Syntax

```
DO_WSK_SendAll(int nConnectHandle, int numstrings, char string1, char *string2, ...);
```

### Return Value

### Parameters

Parameter	Description
nConnectHandle	A connection handle returned from a previous call to DO_WSK_Socket.
numstrings	The number of strings to be sent.
string1	The strings to be sent, separated by commas.

### Example

```
DO_WSK_Socket(S3, AF_INET, SOCK_STREAM, IPPROTO_TCP);
DO_WSK_Bind(S3, ANY_ADDR, ANY_PORT);
DO_WSK_Getsockname(S3);
DO_WSK_Connect(S3, "172.22.11.25, 80, AF_INET);
DO_WSK_Setsockopt(S3, IPPROTO_TCP, TCP_NODELAY, 1);
DO_WSK_Setsockopt(S3, SOL_SOCKET, SO_LINGER, 0x100);
DO_WSK_SendAll(S3, 2, "GET/HTTP/1.1\r\nAccept: image/gif,"
"image/x-bitmap, image/jpeg, image/pjpeg, application/"
"vnd.ms-excel, application/msword, application/x-shock"
"wave-flash, */*\r\nAccept-Language:en-us\r\nAccept-En"
"coding: gzip, deflate\r\nIf-Modified-Since: Mon, 03 Feb"
"2003 15:03:15 GMT\r\nIf-None-Match:\"82f2e16095cbc21:"
"973\"", "\r\nUser-Agent: Mozilla/4.0 (compatible; MSIE"
"6.0; Windows NT 5.0; .NET CLR 1.0.3705)\r\nHost:"
"qaappserv\r\nConnection: Keep-Alive\r\n\r\n");
```

## DO\_WSK\_Sendto

Sends data on either a connected or unconnected socket to a remote host.

### Syntax

```
Int DO_WSK_Sendto(int nConnectHandle, char * wsk_statement, char szServerInetAddr, unsigned short port );
```

### Return Value

### Parameters

Parameter	Description
-----------	-------------

nConnectHandle	A connection handle returned from a previous call to DO_WSK_Socket.
wsk_statement	Buffer of data to be sent.
szServerInetAddr	Character string containing the Internet address of the destination socket.
unsigned short port	The port (in host-byte order) of the destination socket.

**Example**

```
DO_WSK_Socket(S1, AF_INET, SOCK_DGRAM, IPPROTO_IP);
DO_WSK_Setsockopt(S1, SOL_SOCKET, SO_BROADCAST, 1);
DO_WSK_Bind(S1, ANY_ADDR, ANY_PORT);
DO_WSK_Sendto(S1, "0$^B^A^@^D^Fpublic\241^W^B^A^A^B^A^@^B^A^@0\f0\n^F^F+^F^"
"A^B^A^A^E^@", "172.22.6.71", 161);
```

**DO\_WSK\_Setsockopt**

Sets options associated with the specified socket.

**Syntax**

```
DO_WSK_Setsockopt(int nConnectHandle, int level, int option_name,
WinsockSetSockOptionLevelEnum wsk_sockopt_optval );
```

**Return Value**

**Parameters**

Parameter	Description						
nConnectHandle	A connection handle returned from a previous call to DO_WSK_Socket.						
level	The level at which the socket option is defined. This can be either SOL_SOCKET or IPPROTO_TCP.						
option_name	Option name. Refer to your Winsock documentation for a complete list of values.						
wsk_sockopt_optval	<p><i>WinsockSetSockOptionLevelEnum</i></p> <p>Integer variable will receive the values of option_name upon function return. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>SOL_SOCKET</td> <td>Socket level</td> </tr> <tr> <td>IPPROTO_TCP</td> <td>TCP level</td> </tr> </tbody> </table>	Value	Description	SOL_SOCKET	Socket level	IPPROTO_TCP	TCP level
Value	Description						
SOL_SOCKET	Socket level						
IPPROTO_TCP	TCP level						

**Example**

```
DO_WSK_Connect(S3, "172.22.11.25", 80, AF_INET);
DO_WSK_Setsockopt(S3, IPPROTO_TCP, TCP_NODELAY, 1);
DO_WSK_Setsockopt(S3, SOL_SOCKET, SO_LINGER, 0x100);
```

## DO\_WSK\_Shutdown

Disables the sending or receiving of data on a socket.

### Syntax

```
DO_WSK_Shutdown (int nConnectHandle, WinsockShutdownMethodEnum shutdown_type );
```

### Return Value

### Parameters

Parameter	Description								
nConnectHandle	A connection handle returned from a previous call to <code>DO_WSK_Socket</code> .								
shutdown_type	<p><i>WinsockShutdownMethodEnum</i></p> <p>Shutdown method options. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>0</td> <td>All receives are disabled</td> </tr> <tr> <td>1</td> <td>All sends are disabled</td> </tr> <tr> <td>2</td> <td>All sends and receives are disabled</td> </tr> </tbody> </table>	Value	Description	0	All receives are disabled	1	All sends are disabled	2	All sends and receives are disabled
Value	Description								
0	All receives are disabled								
1	All sends are disabled								
2	All sends and receives are disabled								

### Example

```
// disable sends
DO_WSK_Shutdown (0, 1);
```

## DO\_WSK\_Socket

Creates a socket and associates it with a connection handle.

### Syntax

```
DO_WSK_Socket (int nConnectHandle , int address_family, WinsockSocketTypeEnum type, int protocol );
```

### Return Value

### Parameters

Parameter	Description		
nConnectHandle	A connection handle to associate with a new socket.		
address_family	The address family the socket uses. Refer to your Winsock documentation for a complete list.		
type	<p><i>WinsockSocketTypeEnum</i></p> <p>The Winsock socket type. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> </table>	Value	Description
Value	Description		

	SOCK_DGRAM	UDP socket
	SOCK_STREAM	TCP socket
protocol	Specifies which protocol is used with the socket. Refer to your Winsock documentation for a complete list of protocols.	

### Example

```
// create a stream socket
DO_WSK_Socket (0, AF_INET, SOCK_STREAM, 0 );
```

### DO\_WSK\_Write

Writes the number of bytes identified by bytes\_to\_write to the socket from data\_to\_send.

This can be used in place of DO\_WSK\_Send() when coding scripts by hand. DO\_WSK\_Send() expects a string that has certain control and null characters encoded. DO\_WSK\_Write does not expect any encoding, and so can be used to send data without having to use EscapeStr to encode any possible control characters.

#### Syntax

```
int DO_WSK_Write(int nConnectHandle, char *data_to_send, int bytes_to_write)
```

#### Return Value

Number of bytes written

-1 if an error was encountered

#### Parameters

Parameter	Description
nConnectHandle	The connection number.
data_to_send	The data to write to the connection.
bytes_to_write	The number of bytes to write.

### Example

```
DO_WSK_Write(S2, buffer, 1024);
```

### EscapeStr

Converts ^ and null characters into ^^ and ^@, respectively, so that data with those characters can be passed to DO\_WSK\_Send(), DO\_WSK\_Expect(), or DO\_WSK\_ExpectAny().

#### Syntax

```
char * EscapeStr(char *string, int count)
```

#### Return Value

A pointer to the converted characters

#### Parameters

Parameter	Description
-----------	-------------



string	A pointer to a buffer to be converted.
count	The number of characters to convert.

### Example

```
char buf[80];
...
DO_WSK_Send(S1, EscapeStr("\0\0\0x^hello", 10));
```

## GetLocalAddr

Returns the local address used by a connection in host-byte order.

This can be useful in any case where the client application, and therefore, the script, uses `DO_WSK_Bind()` to bind a socket to an unspecified address or port and then does a `DO_WSK_Listen()` on that socket. This sequence indicates that the application tells the remote side what the local address and port are so that it can connect back to the application, identified by a `DO_WSK_Accept()`. In this case, it is necessary to identify how the client application is informing the remote application of what address and port it is listening on.

For example: The ftp client application binds to the first available port and does a `listen()` on that port. The client tells the remote side, which is actually the ftp server, what port it is listening on by sending a command that looks like "PORT 172,23,70,242,4,212\r\n", where 172,23,70,242 is the IP address of the local machine and 4,212 are the high-order byte and low-order byte of the port number being listened on. To make this slightly easier, we've included the `HiByte()`, `LoByte()`, and `AddrByte()` functions.

### Syntax

```
unsigned long GetLocalAddr(int nConnectHandle)
```

### Return Value

Address of the local side of the connection

### Parameters

Parameter	Description
nConnectHandle	The connection number.

### Example

```
unsigned long addr;
unsigned short port;
...
/*
the following lines have to be AFTER socket S3 is bound in a DO_WSK_Bind() call
port = GetLocalPort(S3);
addr = GetLocalAddr(S3); /* now we know both the local address and port */
...
{
char buf[80];
sprintf(buf, "PORT %d,%d,%d,%d,%d,%d\r\n",
AddrByte(addr,0),
AddrByte(addr,1),
AddrByte(addr,2),
AddrByte(addr,3),
HiByte(port),
```

## Language Reference Commands

```
LoByte(port));  
DO_WSK_Send(S4, buf);  
}
```

### GetLocalPort

Returns the port bound to for the named socket on the local side of the connection.

#### Syntax

```
unsigned short GetLocalPort(int nConnectHandle)
```

#### Return Value

#### Parameters

Parameter	Description
nConnectHandle	The connection number.

#### Example

```
unsigned short port;  
...  
port = GetLocalPort(S3);
```

### GetRemoteAddr

Returns the port connected to on the remote side of a connection.

#### Syntax

```
unsigned long GetRemoteAddr(int nConnectHandle)
```

#### Return Value

Address of the remote side of the connection as a long integer

#### Parameters

Parameter	Description
nConnectHandle	The connection number.

#### Example

```
unsigned long addr;  
...  
addr = GetRemoteAddr(S3);
```

### GetRemotePort

Returns the port connected to on the remote side of a connection.

#### Syntax

```
unsigned short GetRemotePort(int nConnectHandle)
```

## Return Value

## Parameters

Parameter	Description
nConnectHandle	The connection number.

## Example

```
unsigned short port;
...
port = GetRemotePort(S3);
```

## HiByte

Returns the high-order byte of the passed short integer.

Only useful in very specific instances, particularly when scripting an FTP client that requires sending the high and low order bytes of the client-side data port as separate bytes.

HiByte returns the high-order byte of the passed short.

## Syntax

```
unsigned char HiByte(short port)
```

## Return Value

## Parameters

Parameter	Description
port	The short value whose high-order byte is being returned.

## Example

```
unsigned char hbyte;
...
hbyte = HiByte(GetLocalPort(S3));
```

## LoByte

Returns the low-order byte of the passed short integer.

Only useful in very specific instances, particularly when scripting an FTP client that requires sending the high and low order bytes of the client-side data port as separate bytes.

LoByte returns the low-order byte of the passed short.

## Syntax

```
unsigned char LoByte(short port)
```

## Return Value

### Parameters

Parameter	Description
port	The short value for which the low byte is returned.

### Example

```
unsigned char lbyte;
...
byte = LoByte(GetLocalPort(S3));
```

## Log

Records the character string passed into the log file.

### Syntax

```
void Log(char *line_to_be_logged)
```

### Return Value

### Parameters

Parameter	Description
line_to_be_logged	A string to be written to the log file.

### Example

```
Log("Got here!");
```

## MyByteOrder

Byte order of the machine running the script.

MyByteOrder( ) returns the byte order of the machine running the script, either of the constants MSBF (Most Significant Byte First) or LSBF (Least Significant Byte First).

### Syntax

```
int MyByteOrder()
```

### Return Value

### Parameters

None.

### Example

```
short value;
int myorder = MyByteOrder();
...
ScanInt(myorder, 2, (char *)&value);
```

## Response

Returns a pointer to the first character in the response buffer.

It should be called immediately after a `DO_WSK_Expect()`, `DO_WSK_ExpectAny()`, `DO_WSK_Read()`, or `DO_WSK_Quiet()`.

Response returns a pointer to the matched response.

### Syntax

```
char * Response()
```

### Return Value

### Parameters

None.

### Example

```
char buf[80];
...
sprintf(buf, "The first 10 characters of the response
were %10.10s",Response());
Log(buf);
```

## ResponseLength

Returns the number of characters in the response buffer.

### Syntax

```
int ResponseLength()
```

### Return Value

### Parameters

None.

### Example

```
char buf[80];
...
sprintf(buf, "The length of the response was %d bytes",
ResponseLength());
Log(buf);
```

## ScanExpr

Scans the scan buffer for a string specified by the UNIX-style regular expression, into the given buffer.

`ScanExpr()` returns the number of bytes matched by the expression.

### Syntax

```
int ScanExpr(char *exprstr, char *buffer)
```

## Return Value

## Parameters

Parameter	Description
exprstr	The UNIX-style regular expression to look for.
buffer	Where to copy the string to.

## Example

```
char buffer[80];
...
SkipExpr("the name is ");
ScanExpr(".*!", buffer);
Log("the name was %s", buffer);
```

## ScanFloat

Scans a floating point value of the given byteorder and length into the argument.

This should be the address of an appropriate program variable of the same size and type, casted to a char \*. Valid lengths are 4 or 8. The byteorder should be either specified as either of the constants MSBF or LSBF.

## Syntax

```
void ScanFloat(int byteorder, int length, char *buffer)
```

## Return Value

None

## Parameters

Parameter	Description
byteorder	The byteorder of the floating point value.
length	The size of the floating point value (4 (float) or 8 (double)).
buffer	Where to copy the bytes to.

## Example

```
float v1;
double v2;
...
ScanFloat(MyByteOrder(), sizeof(float), (char *)&v1);
ScanFloat(MyByteOrder(), sizeof(double), (char *)&v2);
Log("the v1 was %d and v2 was %d", v1, v2);
```

## ScanInt

`ScanInt()` scans an integer of the given byteorder and length into the argument.

This should be the address of an appropriate program variable of the same size and type, casted to a `char *`. Valid lengths are 1, 2, or 4. The byteorder should be either specified as one of the constants `MSBF` or `LSBF`.

### Syntax

```
void ScanInt(int byteorder, int length, char *buffer)
```

### Return Value

None

### Parameters

Parameter	Description
byteorder	The byteorder of the integer value.
length	The size of the integer (1, 2, or 4).
buffer	Where to copy the bytes to.

### Example

```
short port;
int length;
ScanInt(MyByteOrder(), sizeof(short), (char *)&port);
ScanInt(MyByteOrder(), sizeof(int), (char *)&length);
Log("the port was %d and the length was %d", port, length);
```

## ScanLenString

`ScanLenString()` expects input of the format `[count][string]`, where length is an integer of the given byteorder and length and string is a string of count bytes.

The string is placed in the given pointer and count. This should be the address of an appropriate integral program variable, type-cast to a `char *`, and to be updated with the count.

### Syntax

```
void ScanLenString(int byteorder, int length, char *count, char *buffer)
```

### Return Value

None

### Parameters

Parameter	Description
byteorder	The byteorder of the count value.
length	The size of the count value (1, 2, or 4).
Count	The address of a integral program value of the appropriate size to copy the count value to.
buffer	Where to copy the string to.

## Language Reference Commands

### Example

```
int len;
char buffer[80];
...
ScanLenString(MyByteOrder(), 4, (char *)&len, buffer);
buffer[len] = '\\0';
Log("the name was %s, length was %d", buffer, len);
```

### ScanRewind

Resets the scan pointer and length to the beginning and length of the response buffer respectively.

#### Syntax

```
void ScanRewind( )
```

#### Return Value

None

#### Parameters

None.

#### Example

```
ScanRewind( );
```

### ScanSkip

Skips the specified number of bytes in the scan buffer.

#### Syntax

```
void ScanSkip(int count)
```

#### Return Value

None

#### Parameters

Parameter	Description
Count	The number of bytes to skip ahead in the scan buffer.

#### Example

```
ScanSkip(5);
```

### ScanString

Scans a string of the given length from the current location in the scan buffer into the given buffer. The scan pointer and length are incremented by the argument length.

#### Syntax

```
void ScanString(int length, char *buffer)
```



### Return Value

None

### Parameters

Parameter	Description
length	The number of bytes to copy.
buffer	Where to copy the bytes to.

### Example

```
char mybuf[6];
...
ScanString(5, mybuf);
mybuf[5] = '\\0';
Log("the name was %s", mybuf);
```

### SetTimeout

Sets the number of seconds to wait for subsequent synchronization commands (DO\_WSK\_Expect, DO\_WSK\_ExpectAny, or DO\_WSK\_Read) to be satisfied.

The default timeout value is 20 seconds. Increase this value for large user tests.

### Syntax

```
int SetTimeout(int seconds)
```

### Return Value

Previous timeout value

### Parameters

Parameter	Description
seconds	The number of seconds to wait for a pattern in an DO_WSK_Expect or DO_WSK_ExpectAny, a connection in a DO_WSK_Accept, or a number of bytes to be received in a DO_WSK_Read.

### Example

```
SetTimeout(20);
```

### SkipExpr

Scans the scan buffer for a string specified by the UNIX-style regular expression, and skips ahead over the matched pattern.

SkipExpr() returns the number of bytes matched by the expression.

### Syntax

```
void SkipExpr(char *exprstr)
```

### Return Value

### Parameters

Parameter	Description
exprstr	The UNIX-style regular expression to look for.

### UnEscapeStr

Converts a string with escaped ^ control character sequences to raw text so that it can be manipulated.

UnEscapeStr returns the .

#### Syntax

```
int UnEscapeStr(char *string)
```

#### Return Value

Length of the converted string

#### Parameters

Parameter	Description
string	A string with ^ control character sequences.

#### Example

```
char buf[80], str[6];
int len, x, y;

...

strcpy(buf, "^A^B^B^@hello\n");
len = UnEscapeStr(buf);
memcpy(&x, &buf[0], 2);
memcpy(&y, &buf[2], 2);
memcpy(str, &buf[4], 6);
```

## WWW

### WWW Commands

#### Attach

Applies to Visual Scripting. Changes the current page to the page or frame specified. This new page becomes the active page that all Web functions act on.

#### Clear

Applies to Visual Scripting. Used to clear out certain items such as the cache or cookies. Types can be ordered together to clear both.

#### Click\_On

Applies to Visual Scripting. Mimics the user clicking on text links, clickable images, and submit buttons.

#### DisableStatisticsRP

Applies to Real Networks Streaming Media. Disables capture of statistics during a load test.

#### [DO\\_AddHeader](#)

Applies to HTTP and SSL requests. Indicates headers that are common to every request (DO\_Http or DO\_Https function calls) in a script.

#### [DO\\_AdditionalSubRequest](#)

Applies to HTTP and SSL requests. DO\_AdditionalSubRequest manually adds a sub-request for the next DO\_Http or DO\_Https request. The request is specified as a URL.

#### [DO\\_AllowTrafficFrom](#)

Applies to HTTP and SSL requests. If DO\_AllowTrafficFrom is present in a script, then sub-requested URLs will only occur if the sub-request's URL contains one of the sub-strings in the substrings' list.

#### [DO\\_AttachFile](#)

Applies to HTTP and SSL requests. Specifies files that should be loaded into memory at the beginning of a script run. This is used in Post transactions that include binary files.

#### [DO\\_AutomaticSubRequests](#)

Applies to HTTP requests. Indicates whether subrequests will be downloaded during replay.

#### [DO\\_BasicAuthorization](#)

Specifies the username and password to gain access to a password protected WWW host, directory, or file.

#### [DO\\_BlankOutOfRangeData](#)

Applies to HTTP and SSL requests. If DO\_BlankOutOfRangeData is enabled, then characters in the HTTP response body which interface with text searching or the HTML parser are changed to spaces.

#### [DO\\_BlockTrafficFrom](#)

Applies to HTTP and SSL requests. If DO\_BlockTrafficFrom is present in a script, then sub-requested URLs will only occur if the sub-request's URL does not contain one of the sub-strings in the substrings' list.

#### [DO\\_Cache](#)

Applies to HTTP and SSL requests. Turns on cache emulation which caches anything with a content type beginning with "image/".

#### [DO\\_Clear](#)

Applies to HTTP and SSL requests. Used to clear out certain items such as the cache or cookies. Types can be ordered together to clear both.

#### [DO\\_ClearCache](#)

Applies to HTTP and SSL requests. Clears any cached images. Performed automatically by DO\_HttpCleanup.

#### [DO\\_ClearDNSCache](#)

Applies to HTTP and SSL requests. When DO\_Http or DO\_Https make an HTTP request, DO\_ClearDNSCache caches any DNS lookups that are performed. If that cache needs to be cleared to simulate browser, use DO\_ClearDNSCache.

#### [DO\\_ClearJavascript](#)

Applies to HTTP and SSL requests. Clears any memory allocated by the JavaScript engine. Performed automatically by DO\_HttpCleanup. DO\_ClearJavascript is the same as DO\_Clear (JAVASCRIPT\_ENGINE).

#### [DO\\_DynamicCookieHandling](#)

Applies to HTTP and SSL requests. Turns dynamic cookie handling on or off.

#### [DO\\_DynamicRedirectHandling](#)

## Language Reference Commands

Applies to HTTP requests. Retrieves a redirected URL for use in the next request.

### [DO\\_EnableJavascript](#)

Applies to HTTP requests. Enables or disables the interpretation of Javascript.

### [DO\\_EncodeString](#)

Applies to HTTP and SSL requests. `DO_EncodeString` takes in a string and URL-encodes the string to be suitable to use as a CGI parameter or in the body of a POST.

### [DO\\_FreeHttp](#)

Applies to HTTP and SSL requests. Also applies to Visual Scripting. Clears memory used by the script.

### [DO\\_GetAnchorByNumber](#)

Applies to HTTP and SSL requests. Stores the value of an anchor from an HTML reply into a string that can be substituted into subsequent requests.

### [DO\\_GetAnchorCount](#)

Applies to HTTP and SSL requests. Returns the total number of the anchors on the page.

### [DO\\_GetAnchorHREF](#)

Applies to HTTP and SSL requests. Stores the value of a named anchor off of an HTML reply into a string that can be substituted into subsequent requests.

### [DO\\_GetAnchorHREFEx](#)

Applies to HTTP and SSL requests. Stores the value of a specific occurrence of a named anchor off an HTML reply into a string that can be substituted into subsequent requests.

### [DO\\_GetCitrixICAFile](#)

Saves a WWW reply when its body is an ICA file.

### [DO\\_GetClientMapHREF](#)

Applies to HTTP and SSL requests. `DO_GetClientMapHREF` is used to extract the href URL from a particular region of a client-side image map. Client-side image maps are specified within an HTML document by the `map` tag. Inside the `map` tag, `a` and `area` tags are used to specify regions of the image map. The href attribute of the `a` or `area` tags specify the location of the URL to go to.

### [DO\\_GetCookie](#)

Applies to HTTP and SSL requests. Extracts a cookie from the QALoad internal cookie list. The cookie is retrieved based on the name of the cookie. Wildcard patterns can be used to specify the cookie name in case the cookie name is dynamic. A count is also specified in case multiple cookies match the specified name.

### [DO\\_GetCookieFromReplyEx](#)

Applies to HTTP and SSL requests. Retrieves and stores the value of a cookie when a `Set-Cookie:` statement is encountered in a reply header.

### [DO\\_GetCookiesForURL](#)

Applies to HTTP and SSL requests. `DO_GetCookiesForURL` sends a message to the QALoad internal cookie storage requesting a list of cookies for this URL. The cookies are returned in a semicolon-separated list of cookies. Each cookie in the returned cookie list is put into the "name=value" form. The returned cookie list is suitable to be used as a cookie header for an HTTP request.

### [DO\\_GetFormActionStatement](#)

Applies to HTTP and SSL requests. Gets the ACTION tag from a requested form. This feature is useful when a form dynamically changes what is stored in the ACTION tag.

### [DO\\_GetFormValueByName](#)

Applies to HTTP and SSL requests. Retrieves the value embedded in a form for the specified field.

### [DO\\_GetHeaderFromReply](#)

Applies to HTTP and SSL requests. Retrieves the value of a header in the reply resulting from a DO\_HTTP command.

### [DO\\_GetLastHttpError](#)

Applies to HTTP and SSL requests. Retrieves the integer indicating the error code of the last HTTP request sent with DO\_Http. Errors greater than 399 include the Page not found 404 error.

### [DO\\_GetRedirectedURL](#)

Applies to HTTP requests. Modifies the parameter passed in for use in the next request.

### [DO\\_GetReplyBuffer](#)

Applies to HTTP and SSL requests. DO\_GetReplyBuffer returns the HTTP response from the last DO\_Http request.

### [DO\\_GetReplyBufferLength](#)

Applies to HTTP and SSL requests. DO\_GetReplyBuffer returns the length of the HTTP response from the last DO\_Http request.

### [DO\\_GetUniqueString](#)

Applies to HTTP and SSL requests. Used to parse the most recent HTTP server reply to get the contents of a string that occurs between the left and right input strings.

### [DO\\_GetUniqueStringEx](#)

Applies to HTTP and SSL requests. Used to parse a null-terminated input string (search) to get the contents of a string that occurs between the left and right input strings.

### [DO\\_Http](#)

Applies to HTTP requests. Executes an HTTP request in the script.

### [DO\\_HttpCleanup](#)

Applies to HTTP and SSL requests. Performs all necessary cleanup operations when a script exits or the user terminates the script.

### [DO\\_Https](#)

Applies to SSL requests. Makes a secured request to the server specified by the http\_statement.

### [DO\\_HttpVersion](#)

Applies to HTTP and SSL requests. Specifies the version to use in the requests sent during playback.

### [DO\\_InitHttp](#)

Applies to HTTP and SSL requests. Also applies to Visual Scripting. Sets all necessary internal variables needed to load test an HTTP script.

### [DO\\_IPSpoofEnable](#)

Applies to HTTP and SSL requests. Enables each virtual user to appear to the web server as being sourced from a different network interface card.

### [DO\\_NTLMAuthorization](#)

Applies to HTTP requests. Provides user ID and password (plain text or encrypted) information for NTLM authentication.

### [DO\\_ProxyAuthorization](#)

Provides the username and password to access a password protected proxy server.

#### [DO\\_ProxyExceptions](#)

Applies to HTTP and SSL requests. Tells QALoad not to use the proxy server for hosts in the proxy exceptions list, so you can replay requests both inside and outside of the firewall in the same script.

#### [DO\\_ProxyHttpVersion](#)

Applies to HTTP and SSL requests. Specifies the version to use in proxy requests sent during playback. This affects whether or not the replies come back chunked. Only HTTP 1.1 requests receive chunked replies.

#### [DO\\_SaveReplyType](#)

Applies to HTTP and SSL requests. Specifies types of replies to save.

#### [DO\\_SetAssumedContentType](#)

Applies to HTTP and SSL requests. Sets the default content type if the web server doesn't send a content type header.

#### [DO\\_SetBaudRate](#)

Returns the baud rate the virtual user will use.

#### [DO\\_SetBaudRateEx](#)

Returns the transmission rate the virtual user will use.

#### [DO\\_SetCheckpointName](#)

Sets the name of the next automatic checkpoint for the next DO\_Http or DO\_Https statement in the script.

#### [DO\\_SetCookie](#)

Applies to HTTP and SSL requests. DO\_SetCookie adds a cookie to the current transaction.

#### [DO\\_SetCookieEx](#)

Applies to HTTP and SSL requests. DO\_SetCookie adds a cookie to the current transaction.

#### [DO\\_SetJavaScriptCleanupThreshold](#)

Applies to HTTP and SSL requests. Periodically QALoad will destroy its internal JavaScript model and recreate it. DO\_SetJavaScriptCleanupThreshold sets a count of the number of times JavaScript parsing is done before destroying and recreating the model.

#### [DO\\_SetJavaScriptLevel](#)

Applies to HTTP requests. Allows user to control the level of JavaScript execution for convert and replay.

#### [DO\\_SetMaxBrowserThreads](#)

Applies to HTTP and SSL requests. Specifies the number of concurrent connections to make for playback.

#### [DO\\_SetMaximumRetries](#)

Similar to the behavior of Netscape and Internet Explorer.

#### [DO\\_SetPostDelay](#)

Applies to HTTP requests. Sets how many seconds QALoad should wait for a reply from a server after the header has been sent for a POST request.

#### [DO\\_SetRefreshTimeout](#)

Specifies how long to wait for a meta refresh.

#### [DO\\_SetRetryWait](#)

Applies to SSL requests. Sets the proxy authorization when accessing SSL pages passed through a proxy

server (also known as SSL tunneling).

#### [DO\\_SetTimeout](#)

Applies to HTTP and SSL requests. Specifies how long to wait for a reply from the server. If a reply is not received within the specified time, the virtual user will fail with a fatal error.

#### [DO\\_UseEntityList](#)

Applies to HTTP and SSL requests. Decodes non-ASCII character entities.

#### [DO\\_UseNumericReferenceList](#)

Applies to HTTP and SSL requests. Decodes non-ASCII numeric references.

#### [DO\\_UsePersistentConnections](#)

Applies to HTTP and SSL requests. Turns the use of persistent connections on or off.

#### [DO\\_UseProxy](#)

Applies to HTTP and SSL requests. Specifies a proxy server to use during testing.

#### [DO\\_UseProxyAutomaticConfiguration](#)

Applies to HTTP and SSL requests. Downloads the proxy automatic configuration (PAC) script at the specified URL. The rest of the transaction will use the PAC script to determine which proxy, if any, to connect to hosts.

#### [DO\\_VerifyDocTitle](#)

Applies to HTTP and SSL requests. Compares the parameters and match type passed in the parameters against the HTML page title specified in the response received from the HTTP request.

#### [DO\\_WWWFree](#)

Applies to HTTP and SSL requests. Clears memory used by the script.

#### [DO\\_WWWInitialize](#)

Applies to HTTP and SSL requests. Sets all necessary internal variables needed to load test a WWW script.

#### [DownloadMediaFromASX](#)

Applies to Windows Media Player Streaming Media. Dynamically parses an ASX file from the previous response and initiates and waits for completion of the specified Windows Media resources download.

#### [DownloadMediaRP](#)

Applies to Real Networks Streaming Media. Initiates and waits for completion of the specified multi-media resource download.

#### [DownloadMediaWMP](#)

Applies to Windows Media Player Streaming Media. Initiates and waits for completion of the specified Windows Media resource download.

#### [EnableStatisticsRP](#)

Applies to Real Networks Streaming Media. Enables capture of media player performance statistics during a load test. Compuware recommends that this function is called in the initial section of a Web script, before the SYNCHRONIZE() call. Although it can be called at any point in the script, this command must appear in the script prior to any DownloadMediaRP call.

#### [ExtractString](#)

Applies to Visual Scripting. Retrieves data from the virtual browser. Will extract a text string from within the responses that came back from the last request. This command replaces the old method of extracting a string using the Get command.

### Fill\_In

Applies to Visual Scripting. Used to represent how the user filled in fields on a form before clicking on a submit button. The values that are passed to Fill\_In are expected to be plain text with no encoding other than using + to join multiple selects for LIST\_BOX.

### Get

Applies to Visual Scripting. Retrieves data from the virtual browser. Whole pages, specific frames, and text strings from within the document can be retrieved.

### GetSiebelValue

Retrieves the value of a Siebel record from the Siebel library and saves it in a Local Variable.

### Navigate\_To

Applies to Visual Scripting. Reads a URL typed in the Web browser's address field and constructs a request to navigate to the URL, or reads another request typed in the browser's address field, finishes the request and navigates to the request. Navigate\_To is a direct replacement for DO\_Http.

### ModifyEncoding

ModifyEncoding is used in Visual scripts to convert strings to UTF8, EUCJP or to the language used by the script.

### PlayMedia

Applies to Real Networks and Windows streaming media. Initiates and plays back the streaming media file that was stored in a previous call to the Click\_On function.

### Post\_To

Applies to Visual Scripting. Reads a URL typed in the Web browser's address field as well as the encoding type. It then constructs a request to send a post to the URL.

### RandNumString

Applies to Visual Scripting. Generates a random number from minimum to maximum.

### Region

Applies to Visual Scripting. Marks the region\_number parameter as an image map region.

### RESTART\_TRANSACTION\_BOTTOM

Applies to Visual Scripting. Used to define a point at the end of the transaction for anything that needs to be deallocated or uninitialized. When transaction restarting occurs for a failed transaction, QALoad will first execute any code starting after the call to RESTART\_TRANSACTION\_BOTTOM allowing you to clean up important information and prevent memory leaks before retrying the transaction.

### RESTART\_TRANSACTION\_TOP

Used to define a point at the beginning of the transaction loop that QALoad can use to rewind the transaction if the transaction fails and Restart Transaction error handling has been selected in the QALoad Conductor as follows:

### Set

Applies to Visual Scripting. Assigns values to the Virtual Browser, Proxy, and other parts of the QALoad replay. This command sets the properties and attributes of the script.

### ShowMediaRP

Applies to Real Networks Streaming Media. Displays the media during a load test. Audio and video can be controlled separately. If video is enabled, a dialog box displays the video. For audio, the sound from the media will play through the sound device.



### SiebelInitialize

Initializes the Siebel correlation library and treats the current script file as a Siebel file. If the Siebel correlation library dll (ssdtcorr.dll) is not present in the QALoad directory, it throws an error in the TRACE window and exits the playback.

### SiebelUpdatePage

Feeds the current response (response from last request) to the Siebel library. This tells the Siebel library to extract the Siebel parameter values from the response.

### Verify

Applies to Visual Scripting. Used to verify expected text against an element of the page just requested.

### WWW\_FATAL\_ERROR

Applies to HTTP and SSL requests. Also applies to Visual Scripting. WWW\_FATAL\_ERROR aborts or restarts a virtual user in the event of an error during replay.

### X\_Coord

Applies to Visual Scripting. Marks the x\_value parameter as an x-coordinate value.

### XMLRequest

Applies to Visual Scripting. The XMLRequest function takes in the HTTP action and a URL and constructs a request to navigate to the URL. XMLRequest is a direct replacement for Navigate\_To when the main HTTP request is for an XML document.

### Y\_Coord

Applies to Visual Scripting. Marks the y\_value parameter as a y-coordinate value.

## Attach

Applies to Visual Scripting. Supported in HTML mode only. Changes the current page to the page or frame specified.

This new page becomes the active page that all script commands act on.

### Syntax

```
boolean Attach ( const page_id& page );
```

### Return Value

True if the page was attached to.

False if not.

### Parameters

Parameter	Description
page	The page to attach to.

### Example

```
page = Get ( PAGE );
Attach ( page );
Attach ( Get ( FRAME, "index" ) );
```

## Clear

Applies to Visual Scripting. Used to clear out certain items such as the cache or cookies. Types can be ordered together to clear both.

### Prototypes

```
boolean Clear ( WWWClearEnum type );
```

### Return Value

True if cleared successfully.  
False if not cleared successfully .

### Parameters

Parameter	Description																												
type	<p><i>WWWClearEnum</i></p> <p>The type of clear to do. Valid types are listed in the following tables:</p> <table border="1"> <thead> <tr> <th>Type</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>ALL</td> <td>Clear all internal settings.</td> </tr> <tr> <td>ALL_CGI_PARAMETERS</td> <td>Clear all Set CGI_PARAMETER parameters.</td> </tr> <tr> <td>ALL_COOKIES</td> <td>Clear all stored cookies. (Transaction type)</td> </tr> <tr> <td>ALL_HEADERS</td> <td>Clear all Set HEADER header attributes.</td> </tr> <tr> <td>ALL_VALUES</td> <td>Clear all DO_SetValue variables. (Transaction type)</td> </tr> <tr> <td>ATTACHED_FILES</td> <td>Clear all files in the binary file list.</td> </tr> <tr> <td>BASIC_AUTH_FLAG</td> <td>Do not send the basic authorization until next challenge. (Transaction type)</td> </tr> <tr> <td>BASIC_AUTHORIZATION</td> <td>Clear the basic authorization user name and password.</td> </tr> <tr> <td>BAUD_RATE_CALCULATIONS</td> <td>Clear the accumulated modern emulation data. (Transaction type)</td> </tr> <tr> <td>BLOCK_TRAFFIC_FROM</td> <td>Clear the blocked traffic from list.</td> </tr> <tr> <td>CACHE</td> <td>Clear out any virtual browser cache. (Transaction type)</td> </tr> <tr> <td>CERTIFICATE</td> <td>Clear the client certificate.</td> </tr> <tr> <td>CERTIFICATE_PASSWORD</td> <td>Clear the client certificate password.</td> </tr> </tbody> </table>	Type	Description	ALL	Clear all internal settings.	ALL_CGI_PARAMETERS	Clear all Set CGI_PARAMETER parameters.	ALL_COOKIES	Clear all stored cookies. (Transaction type)	ALL_HEADERS	Clear all Set HEADER header attributes.	ALL_VALUES	Clear all DO_SetValue variables. (Transaction type)	ATTACHED_FILES	Clear all files in the binary file list.	BASIC_AUTH_FLAG	Do not send the basic authorization until next challenge. (Transaction type)	BASIC_AUTHORIZATION	Clear the basic authorization user name and password.	BAUD_RATE_CALCULATIONS	Clear the accumulated modern emulation data. (Transaction type)	BLOCK_TRAFFIC_FROM	Clear the blocked traffic from list.	CACHE	Clear out any virtual browser cache. (Transaction type)	CERTIFICATE	Clear the client certificate.	CERTIFICATE_PASSWORD	Clear the client certificate password.
Type	Description																												
ALL	Clear all internal settings.																												
ALL_CGI_PARAMETERS	Clear all Set CGI_PARAMETER parameters.																												
ALL_COOKIES	Clear all stored cookies. (Transaction type)																												
ALL_HEADERS	Clear all Set HEADER header attributes.																												
ALL_VALUES	Clear all DO_SetValue variables. (Transaction type)																												
ATTACHED_FILES	Clear all files in the binary file list.																												
BASIC_AUTH_FLAG	Do not send the basic authorization until next challenge. (Transaction type)																												
BASIC_AUTHORIZATION	Clear the basic authorization user name and password.																												
BAUD_RATE_CALCULATIONS	Clear the accumulated modern emulation data. (Transaction type)																												
BLOCK_TRAFFIC_FROM	Clear the blocked traffic from list.																												
CACHE	Clear out any virtual browser cache. (Transaction type)																												
CERTIFICATE	Clear the client certificate.																												
CERTIFICATE_PASSWORD	Clear the client certificate password.																												

CONNECTION	Reset network connection. (Transaction type)
CONNECT_REQUEST_FOR_SSL_TUNNELING	Clear the set SSL connect string.
DEFAULT_CONTENT_TYPE	Clear the default content type.
DNS_CACHE	Clear any cached DNS lookups. (Transaction type)
INTERNAL_BUFFERS	Clear any internal buffers.
JAVASCRIPT_ENGINE	Clear the Javascript state.
NTLM_AUTHORIZATION	Clear the Integrated Windows Authentication (formerly NTLM) user name and password.
ONLY_ALLOW_TRAFFIC_FROM	Clear the allowed traffic from list.
ONLY_USE_SSL_CIPHER	Clear the only use SSL cipher string.
PROXY_AUTHORIZATION	Clear the proxy authorization user name and password.
PROXY_AUTH_FLAG	Do not send the basic authorization until next challenge. (Transaction type)
PROXY_SETTINGS	Clear all proxy settings.
RECEPTION_BAUD_RATE	Turn off reception baud rate emulation.
REFERER	Clear the referer so it is not sent with the next request. (Transaction type)
SIGNIFICANT_CONTENT_TYPES	Clear the significant content type list.
SPOOFED_IP_ADDRESS	Clear any spoofed IP addresses.
TRANSACTION	Clear all temporary variables used in the transaction.
TRANSMISSION_BAUD_RATE	Turn off transmission baud rate emulation.

### Examples

```

Clear ( JAVASCRIPT_ENGINE );
Clear ( CACHE );
Clear ( CONNECTION );
Clear ( ALL_COOKIES );
Clear ( TRANSACTION );
Clear ( ALL );

```

## Click\_On

Applies to Visual Scripting. Mimics the user clicking on text links, clickable images, and submit buttons.

### Versions

Versions of Click\_On are:

boolean `Click_On` ( `WWWClickOnLinkEnum` link, string description );

boolean `Click_On` ( `WWWClickOnLinkEnum` link, integer count );

boolean `Click_On` ( `WWWClickOnLinkEnum` link, `WWWClickOnSpecifierEnum` specifier, string description );

boolean `Click_On` ( `WWWClickOnLinkEnum` link, integer count, `WWWClickOnSpecifierEnum` specifier, string description );

boolean `Click_On` ( `WWWClickOnLinkEnum` link, integer count, `WWWClickOnSpecifierEnum` specifier, string description, string x\_coord, string y\_coord );

boolean `Click_On` ( `WWWClickOnLinkEnum` link, integer count, `WWWClickOnSpecifierEnum` specifier, string description, `WWWClickOnOptionEnum` click\_option );

boolean `Click_On` ( `WWWClickOnLinkEnum` link, integer count, `WWWClickOnSpecifierEnum` specifier, string description, string region );

## DisableStatisticsRP

Applies to Real Networks Streaming Media. Disables capture of statistics during a load test.

### Notes:

- ! Real Player streaming media is only supported in process mode. On the QALoad Player main window, in the Run As: group, select the Process option.
- ! For streaming media playback, QALoad requires specific media player versions. For a list of supported versions, refer to "System Requirements" in the "Installing QALoad " chapter of the QALoad Installation and Configuration Guide.

### Syntax

```
DisableStatisticsRP();
```

### Return Value

### Parameters

None.


### Example

```
DisableStatisticsRP();
```

## DO\_AddHeader

Applies to HTTP and SSL requests. Indicates headers that are common to every request (`DO_Http` or `DO_Https` function calls) in a script.

QALoad takes all of the headers that are in every request in the script and places them at the beginning of the script (between `BEGIN_TRANSACTION` and the first request) using the `DO_AddHeader` command. During replay, `DO_AddHeader` tells QALoad to add the header with a given name and value to all requests in the script.

 Note: Cookie and Host headers are not included in the DO\_AddHeader function even if they are common to all of the requests.

### Syntax

```
DO_AddHeader (const char *name, const char *value);
```

### Return Value

### Parameters

Parameter	Description
Name	The name of the header.
Value	The value of the header.

### Example

If the following two requests occurred in the same script, the User-Agent header would be considered common:

```
DO_Http("GET http://yourserver.net/ HTTP/1.0\r\n"
"User-Agent: Mozilla/4.7 [en] (WinNT; I)\r\n"
"Host: yourserver.net\r\n"
"Accept: */*\r\n"
"Accept-Language: ja_JP\r\n"
"Accept-Charset: *\r\n\r\n");
DO_Http("GET http://anotherserver.net/ HTTP/1.0\r\n"
"User-Agent: Mozilla/4.7 [en] (WinNT; I)\r\n"
"Host: anotherserver.net\r\n"
"Accept: image/jpeg, */*\r\n"
"Accept-Language: en\r\n"
"Accept-Charset: iso-8859-1,*,utf-8\r\n\r\n");
```

Note that both User-Agent and Mozilla/4.7 [en] (WinNT; I) must be the same in order for them to be considered common. Using the above example, the resulting script will look like this:

```
DO_AddHeader("User-Agent", "Mozilla/4.7 [en] (WinNT; I)");
DO_Http("GET http://yourserver.net/ HTTP/1.0\r\n"
"Host: yourserver.net\r\n"
"Accept: */*\r\n"
"Accept-Language: ja_JP\r\n"
"Accept-Charset: *\r\n\r\n");
DO_Http("GET http://anotherserver.net/ HTTP/1.0\r\n"
"Host: anotherserver.net\r\n"
"Accept: image/jpeg, */*\r\n"
"Accept-Language: en\r\n"
"Accept-Charset: iso-8859-1,*,utf-8\r\n\r\n");
```

Note that the User-Agent header was removed from the DO\_Http() calls. The DO\_AddHeader() call tells QALoad to add the header with a given name and value to all requests in the script.

## DO\_AdditionalSubRequest

Applies to HTTP and SSL requests. DO\_AdditionalSubRequest manually adds a sub-request for the next DO\_Http or DO\_Https request. The request is specified as a URL.

### Syntax

```
int DO_AdditionalSubRequest ( const char * szSubRequest );
```

### Return Value

Returns the number of items in the pre-loaded sub-request list.

### Parameters

Parameter	Description
szSubRequest	URL to add as a sub-request of the next DO_Http or DO_Https request.

### Example

```
...
...
DO_AdditionalSubRequest ( "http://company.com/images/bar.gif" );
...
...
```

### DO\_AllowTrafficFrom

Applies to HTTP and SSL requests. If DO\_AllowTrafficFrom is present in a script, then sub-requested URLs only occur if the sub-request's URL contains one of the sub-strings in the 'substrings' list.

For example, if substrings is "www.host.com, images; .js", then the following URLs could be sub-requested.

```
http://www.host.com/top-frame.html : URL has a substring "www.host.com"
http://img.host.com/images/fist.png : URL has a sub-string "images"
http://scripts.host.com/scripts/menu.js : URL has a sub-string ".js"
```

And the following URL could not be sub-requested:

```
http://x.host.com/no-reason-to-request/page.html : No substring found
```

### Syntax

```
DO_AllowTrafficFrom ( const char * substrings )
```

### Return Value

### Parameters

Parameter	Description
substrings	Semicolon separated list of sub-strings.

### Example

```
DO_AllowTrafficFrom ( "www.host.com; images; .js" );
```

### DO\_AttachFile

Applies to HTTP and SSL requests. Specifies files that should be loaded into memory at the beginning of a script run. This is used in Post transactions that include binary files.

### Syntax

```
DO_AttachFile(const char *label, const char *filename);
```

### Return Value

## Parameters

Parameter	Description
label	The variable that is replaced by the file contents in the request at run-time.
filename	The relative filename for the file to attach.

## Example

```

...
...
DO_AttachFile("FILE_1", "mee-1.jpg");
...
...
BEGIN_TRANSACTION();
...
...
DO_Http("POST {*action_statement0} HTTP/1.0\r\n"
"Content-Disposition: frm-data; name=\"phylename\"; filename="
"\"F:\\temp\\mee-1.jpg\"\\r\n"
"Content-Type: image/jpeg\r\n\r\n{*FILE_1}\\r\n"
"-----7d02d1b240910--");
...
...

```

## DO\_AutomaticSubRequests

Applies to HTTP requests. Indicates whether subrequests will be downloaded during replay.

This command relates to the Automatically Process HTTP SubRequests check box on the QALoad Script Development Workbench Convert Options wizard. When this option is selected, DO\_AutomaticSubRequests(TRUE); is written to the script when it is converted from a capture file and subrequests are not included in the script. During replay, QALoad handles subrequests like a browser.

When it is not selected, DO\_AutomaticSubRequests(FALSE); is written to the script when it is converted from a capture file. Each DO\_Http request evaluates the Web page, determines if it contains any subrequests (requests that call for images, style sheets, or XML DTD's), and downloads these items. All subrequests in the capture file are converted into the resulting script and executed during replay.

By default, the Automatically Process HTTP SubRequests check box is selected. DO\_AutomaticSubRequests is placed at the beginning of a script, between the BEGIN\_TRANSACTION command and the first request.

## Syntax

```
int DO_AutomaticSubRequests (BOOL bFlag);
```

## Return Value

0 if bFlag is set to FALSE.

1 if bFlag is set to TRUE.

## Parameters

Parameter	Description
bflag	A flag indicating if the Automatically Process HTTP SubRequests option is enabled (TRUE or FALSE).

## Examples

Example 1:

## Language Reference Commands

The following example is valid when `bflag` is `TRUE`:

 **Note:** Request 3 (`logo.gif`) is not present when `SubRequest` is `TRUE`.

```
...
...
BEGIN_TRANSACTION();
...
...
DO_AutomaticSubRequests(TRUE);
...
...
/* Request: 1 */

DO_Http("GET http://company.com/ HTTP/1.0\r\n"
"Accept: image/gif, image/x-xbitmap, */*\r\n"
"Host: company.com\r\n"
"Cookie: HTMLA=FONTSIZE=LARGE; SITESERVER=ID=" "4b5b75c9dda4ab9751bce9a95f74ec62\r\n\r\n");
...
...

/* Request: 2 */

DO_Http("GET http://company.com/index.htm HTTP/1.0\r\n"
"Accept: image/gif, image/x-xbitmap, */*\r\n"
"Referer: http://company.com/\r\n"
"Host: company.com\r\n"
"Cookie: HTMLA=FONTSIZE=LARGE; SITESERVER=ID=" "4b5b75c9dda4ab9751bce9a95f74ec62\r\n\r\n");
...
...
END_TRANSACTION();
...
...
```

### Example 2:

The following example is valid when `bflag` is `FALSE`:

```
...
...
BEGIN_TRANSACTION();
...
...
DO_AutomaticSubRequests(FALSE);
...
...

/* Request: 1 */

DO_Http("GET http://company.com/ HTTP/1.0\r\n"
"Accept: image/gif, image/x-xbitmap, */*\r\n"
"Host: company.com\r\n"
"Cookie: HTMLA=FONTSIZE=LARGE; SITESERVER=ID=" "4b5b75c9dda4ab9751bce9a95f74ec62\r\n\r\n");
...
...

/* Request: 2 */

DO_Http("GET http://company.com/index.htm HTTP/1.0\r\n"
"Accept: image/gif, image/x-xbitmap, */*\r\n"
"Referer: http://company.com/\r\n"
"Host: company.com\r\n"
"Cookie: HTMLA=FONTSIZE=LARGE; SITESERVER=ID=" "4b5b75c9dda4ab9751bce9a95f74ec62\r\n\r\n");
...
...

/* Request: 3 */
```



```

DO_Http("GET http://company.com/logo.gif HTTP/1.0\r\n"
"Accept: */*\r\n"
"Referer:http://company.com/index.htm\r\n"
"Host: company.com\r\n"
"Cookie: HTMLA=FONTSIZE=LARGE; SITESERVER=ID=" "4b5b75c9dda4ab9751bce9a95f74ec62\r\n\r\n");
...
...
END_TRANSACTION();
...
...
/

```

## DO\_BasicAuthorization

Specifies the username and password to gain access to a password protected WWW host, directory, or file.

The password may be encrypted using QALoad's "~encr~" encryption. Username and password are inserted automatically as necessary during conversion. Note that you can variablize the username and password to emulate different users accessing the resources.

### Syntax

```
DO_BasicAuthorization(const char *username, const char *password);
```

### Return Value

### Parameters

Parameter	Description
username	A valid username for the resource you're attempting to access.
password	The associated password.

### Example

```

DO_HttpVersion("Auto");
DO_SLEEP(2);

/* Request: 1 */

DO_BasicAuthorization("smith", "~encr~0E636502080E");
BeginCheckpoint(" http://iris/redline - chkpt: 1");
DO_Http("GET http://iris/redline HTTP/1.1\r\n"
"Accept: image/gif, image/x-xbitmap, image/jpeg, image/pjpeg, "
"application/vnd.ms-excel, application/msword, "
"application/vnd.ms-powerpoint, */*\r\n"
"Accept-Language: en-us\r\n"
"Accept-Encoding: gzip, deflate\r\n"
"User-Agent: Mozilla/4.0 (compatible; MSIE 5.01; Windows NT; CPWR)\r\n"
"Host: iris\r\n\r\n"
);

```

## DO\_BlankOutOfRangeData

Applies to HTTP and SSL requests. If DO\_BlankOutOfRangeData is enabled, then characters in the HTTP response body that interface with text searching or the HTML parser are changed to spaces.

 Note: Currently, the only character blanked by DO\_BlankOutOfRangeData is the NUL character (ASCII value 0).

### Syntax

```
DO_BlankOutOfRangeData ( BOOL flag );
```

### Return Value

### Parameters

Parameter	Description
flag	Flag indicating if out of range blanking is to be done or not.

### Example

```
DO_BlankOutOfRangeData ( TRUE );
```

## DO\_BlockTrafficFrom

Applies to HTTP and SSL requests. If DO\_BlockTrafficFrom is present in a script, then sub-requested URLs only occur if the sub-request's URL does not contain one of the sub-strings in the 'substrings' list.

For example, if sub-strings list is "pop-up; imgsrv", then the following URLs would not be sub-requested:

```
http://www.host.com/pop-up/ad.html : URL has a substring "pop-up"  
http://imgsrv.host.com/images/fist.png : URL has a sub-string "imgsrv"
```

And the following URL could be sub-requested:

```
http://www.host.com/no-reason-to-block/page.html : No substring found
```

### Syntax

```
DO_BlockTrafficFrom( const char * substrings )
```

### Return Value

### Parameters

Parameter	Description
substrings	Semicolon separated list of sub-strings.

### Example

```
DO_BlockTrafficFrom ( "pop-up; imgsrv" );
```

## DO\_Cache

Applies to HTTP and SSL requests. Turns on cache emulation, which caches anything with a content type beginning with "image/".

DO\_Cache is related to the Cache option on the WWW Advanced options dialog box. If that option is selected, DO\_Cache (TRUE); is written into the script during the convert process, and requested images are cached.

### Syntax

```
DO_Cache(BOOL flag);
```

### Return Value

Parameters

Parameter	Description
flag	TRUE (on) or FALSE (off).

Example

```
DO_InitHttp(s_info);
DO_Cache(); /* Enable cache */
```

DO\_Clear

Applies to HTTP and SSL requests. Used to clear out certain items, such as the cache or cookies. Types can be ordered together to clear both.

Prototypes

```
DO_Clear ( WWWClearEnum type );
```

Return Value

Parameters

Parameter	Description												
type	<p><i>WWWClearEnum</i></p> <p>The type of clear to do. Valid types are listed in the following tables:</p> <p>Values for Meta type</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>ALL</td> <td>Clear all internal settings.</td> </tr> <tr> <td>ALL_CGI_PARAMETERS</td> <td>Clear all Set CGI_PARAMETER parameters.</td> </tr> <tr> <td>ALL_COOKIES</td> <td>Clear all stored cookies. (Transaction type)</td> </tr> <tr> <td>ALL_HEADERS</td> <td>Clear all Set HEADER header attributes.</td> </tr> <tr> <td>ALL_VALUES</td> <td>Clear all DO_SetValue variables. (Transaction type)</td> </tr> </tbody> </table>	Value	Description	ALL	Clear all internal settings.	ALL_CGI_PARAMETERS	Clear all Set CGI_PARAMETER parameters.	ALL_COOKIES	Clear all stored cookies. (Transaction type)	ALL_HEADERS	Clear all Set HEADER header attributes.	ALL_VALUES	Clear all DO_SetValue variables. (Transaction type)
Value	Description												
ALL	Clear all internal settings.												
ALL_CGI_PARAMETERS	Clear all Set CGI_PARAMETER parameters.												
ALL_COOKIES	Clear all stored cookies. (Transaction type)												
ALL_HEADERS	Clear all Set HEADER header attributes.												
ALL_VALUES	Clear all DO_SetValue variables. (Transaction type)												

## Language Reference Commands

ATTACHED_FILES	Clear all files in the binary file list.
BASIC_AUTH_FLAG	Do not send the basic authorization until next challenge. (Transaction type)
BASIC_AUTHORIZATION	Clear the basic authorization user name and password.
BAUD_RATE_CALCULATIONS	Clear the accumulated modem emulation data. (Transaction type)
BLOCK_TRAFFIC_FROM	Clear the blocked traffic from list.
CACHE	Clear out any virtual browser cache. (Transaction type)
CERTIFICATE	Clear the client certificate.
CERTIFICATE_PASSWORD	Clear the client certificate password.
CONNECTION	Reset network connection. (Transaction type)
CONNECT_REQUEST_FOR_SSL_TUNNELING	Clear the set SSL connect string.
DEFAULT_CONTENT_TYPE	Clear the default content type.
DNS_CACHE	Clear any cached DNS

		lookups. (Transaction type)	
	INTERNAL_BUFFERS	Clear any internal buffers.	
	JAVASCRIPT_ENGINE	Clear the Javascript state.	
	NTLM_AUTHORIZATION	Clear the NTLM user name and password.	
	ONLY_ALLOW_TRAFFIC_FROM	Clear the allowed traffic from list.	
	ONLY_USE_SSL_CIPHER	Clear the only use SSL cipher string.	
	PROXY_AUTHORIZATION	Clear the proxy authorization user name and password.	
	PROXY_AUTH_FLAG	Do not send the basic authorization until next challenge. (Transaction type)	
	PROXY_SETTINGS	Clear all proxy settings.	
	RECEPTION_BAUD_RATE	Turn off reception baud rate emulation.	
	REFERER	Clear the referer so it is not sent with the next request. (Transaction type)	
	SIGNIFICANT_CONTENT_TYPES	Clear the significant content type list.	


SPOOFED_IP_ADDRESS	Clear any spoofed IP addresses.
TRANSACTION	Clear all temporary variables used in the transaction.
TRANSMISSION_BAUD_RATE	Turn off transmission baud rate emulation.

### Examples

```
DO_Clear ( JAVASCRIPT_ENGINE );
DO_Clear ( CACHE );
DO_Clear ( CONNECTION );
DO_Clear ( ALL_COOKIES );
DO_Clear ( TRANSACTION );
DO_Clear ( ALL );
```

### DO\_ClearCache

Applies to HTTP and SSL requests. Clears any cached images. Performed automatically by DO\_HttpCleanup.

 Note: This command is the same as DO\_Clear (CACHE).

#### Syntax

```
DO_ClearCache();
```

#### Return Value

#### Parameters

None.

### DO\_ClearDNSCache

Applies to HTTP and SSL requests. When DO\_Http or DO\_Https make an HTTP request, DO\_ClearDNSCache caches any DNS lookups that are performed. If that cache needs to be cleared to simulate browser, use DO\_ClearDNSCache.

 Note: This command is the same as DO\_Clear (DNS\_CACHE).

#### Syntax

```
DO_ClearDNSCache()
```

#### Return Value

#### Parameters

None.

## Example

```

...
...
/* Request: 1 */
DO_Http ("GET http://company.com/ HTTP/1.0\r\n\r\n" );
DO_ClearDNSCache();
/* Request: 2 */
/*
* Do a brand new DNS lookup of company.com
*/
DO_Http ("GET http://company.com/ HTTP/1.0\r\n\r\n" );
...
...

```

## DO\_ClearJavascript

Applies to HTTP and SSL requests. Clears any memory allocated by the JavaScript engine.

Performed automatically by DO\_HttpCleanup. DO\_ClearJavascript is the same as DO\_Clear (JAVASCRIPT\_ENGINE).

 Note: DO\_ClearJavascript is a deprecated command. Compuware recommends that you use DO\_SetJavascriptCleanupThreshold instead.

### Syntax

```
DO_ClearJavascript();
```

### Return Value

### Parameters

None.

### Example

```

...
DO_ClearJavascript();
END_TRANSACTION();
...

```

## DO\_DynamicCookieHandling

Applies to HTTP and SSL requests. Turns dynamic cookie handling on or off.

This command relates to the Enable Dynamic Cookie Handling option on the QALoad Script Development Workbench Convert Options wizard. When this option is selected, DO\_DynamicCookieHandling (TRUE); is written to the script and the script does not include cookie-related statements (DO\_GetCookieFromReplyEx, DO\_SetValue, etc.).

When the Enable Dynamic Cookie Handling option is not selected, the converted script includes the statement DO\_DynamicCookieHandling (FALSE); and includes all cookie-related information. By default, the Enable Dynamic Cookie Handling check box is selected.

### Syntax

```
int DO_DynamicCookieHandling(BOOL bFlag)
```

## Return Value

0 if bFlag is set to FALSE.

1 if bFlag is set to TRUE.

## Parameters

Parameter	Description
bFlag	Indicates whether dynamic cookie handling is turned on (TRUE) or off FALSE.

## Examples

## Example 1:

When the Enable Dynamic Cookie Handling option is not selected:

```

...
...
/* Declare Variables */
char *Cookie[1];
...
...
for(i=0;i<1;i++)
Cookie[i]=NULL;
...
...
BEGIN_TRANSACTION();
...
...
DO_DynamicCookieHandling(FALSE);
...
...
DO_GetCookieFromReplyEx("NUM", &Cookie[0], '*');
/* Request: 4 */
DO_SetValue("cookie000", Cookie[0]);
DO_Http("GET http://company.com/cgi-bin/cookiespipes.pl "
        "HTTP/1.0\r\n"
        "Accept: */*\r\n"
        "Host: company.com\r\n"
        "Cookie: HTMLA=FONTSIZE=LARGE; {*cookie000}; "
        "SITESERVER=ID=4b4ab9751bce9a95f74ec62\r\n\r\n");
...
...
for(i=0; i<1; i++)
{
free(Cookie[i]);
Cookie[i]=NULL;
}
END_TRANSACTION();
...
...

```

## Example 2:

When the Enable Dynamic Cookie Handling option is selected:

```

...
...
BEGIN_TRANSACTION();
...
...

```



```

DO_DynamicCookieHandling(TRUE);
...
...
DO_Http("GET http://company.com/cgi-bin/cookiespipes.pl "
        "HTTP/1.0\r\n"
        "Accept: */*\r\n"
        "Host: company.com\r\n"
        "Cookie: HTMLA=FONTSIZE=LARGE; SITESERVER=ID=" "4b4ab9751bce9a95f74ec62\r\n\r\n");
...
...
END_TRANSACTION();
...
...

```

## DO\_DynamicRedirectHandling

Applies to HTTP requests. Retrieves a redirected URL for use in the next request.

DO\_DynamicRedirectHandling is related to the Enable Dynamic Redirect Handling option on the QALoad Script Development Workbench Convert Options wizard. If that option is selected, DO\_DynamicRedirectHandling(TRUE) is written into the script during the convert process. The script then checks every response from a DO\_HTTP for a 301, 302, 303, or 307 message and performs the redirected request.

This line should appear only once in the script and at the beginning of the script.

### Syntax

```
int DO_DynamicRedirectHandling (BOOL bFlag)
```

### Return Value

0 if bFlag is set to FALSE.  
1 if bFlag is set to TRUE.

### Parameters

Parameter	Description
bFlag	Flag that indicates whether redirection should be handled.

### Examples

#### Example 1:

When Enable Dynamic Redirect Handling option is TRUE:

```

...
...
DO_DynamicRedirectHandling(TRUE);
...
...
/* Request: 4 To: Redirected Webpage */
DO_Http("GET http://examples.com/cgi-bin/dynredirect.exe "
        "HTTP/1.0\r\n"
        "Accept: image/gif, application/pdf, */*\r\n"
        "Referer: http://examples.com/index.htm\r\n"
        "Host: examples.com\r\n\r\n");
DO_Http("GET http://examples.com/nextrequest.htm"
        "HTTP/1.0\r\n"
        "Accept: image/gif, application/pdf, */*\r\n"
        "Referer: http://examples.com/redirect.htm\r\n"

```

## Language Reference Commands

```
    "Host: examples.com\r\n\r\n");  
...
```

### Example 2:


When Enable Dynamic Redirect Handling option is FALSE:

```
...  
...  
DO_DynamicRedirectHandling(FALSE);  
...  
...  
/* Request: 4 To: Redirected Webpage */  
  
DO_Http("GET http://examples.com/cgi-bin/dynredirect.exe "  
        "HTTP/1.0\r\n"  
        "Accept: image/gif, application/pdf, */*\r\n"  
        "Referer: http://examples.com/index.htm\r\n"  
        "Host: examples.com\r\n\r\n");  
  
DO_Http("GET http://examples.com/redirect.htm"  
        "HTTP/1.0\r\n"  
        "Accept: image/gif, application/pdf, */*\r\n"  
        "Referer: http://examples.com/cgi-bin/ dynredirect.exe\r\n"  
        "Host: examples.com\r\n\r\n");  
  
DO_Http("GET http://examples.com/nextrequest.htm"  
        "HTTP/1.0\r\n"  
        "Accept: image/gif, application/pdf, */*\r\n"  
        "Referer: http://examples.com/redirect.htm\r\n"  
        "Host: examples.com\r\n\r\n");  
...
```

## DO\_EnableJavascript

Applies to HTTP requests. Enables or disables the interpretation of Javascript.

By default, QALoad attempts to interpret Javascript detected during replay. If you disable this feature, you may be able to reduce the amount of CPU overhead during WWW replay. However, this may cause WWW replay to miss some sub-requests and cookies contained in Javascript on HTML pages. To disable Javascript interpretation, insert `DO_EnableJavascript(FALSE);` into your script.

 Note: The `DO_EnableJavascript` command must appear after the `DO_AutomaticSubRequests` command in the script.

### Syntax

```
DO_EnableJavascript(BOOL flag);
```

### Return Value

True = on

False = off

### Parameters

Parameter	Description
flag	Used to enable or disable the interpretation of Javascript.

### Example

```
...  
...  
DO_AutomaticSubRequests(TRUE);
```

```

...
...
DO_EnableJavascript(TRUE);
...
...

```

## DO\_EncodeString


Applies to HTTP and SSL requests. DO\_EncodeString takes in a string and URL-encodes the string to be suitable to use as a CGI parameter or in the body of a POST.

### Syntax

```
int DO_EncodeString( const char *szSource, char **pszDestination )
```

### Return Value

The difference between the string length of the destination and the string length of the source.

 **Caution:** The string buffer parameter variable should be explicitly initialized to NULL. Failure to do so results in a memory error in the script. Once the string buffer has been allocated, it can be reused within the same transaction loop without being explicitly freed. However, the buffer memory should be freed at the end of the transaction loop. Failure to free the memory buffer at the end of the transaction loop results in a memory leak.

### Parameters

Parameter	Description
szSource	String to URL encode.
pszDestination	Address of a string (char*) to hold the URL encoded string.

### Example

```

char* szEncoded= 0;
...
/* The value of szEncoded will be "a+string%21" */
DO_EncodeString( "a string!", &szEncoded );

```

## DO\_FreeHttp

Applies to HTTP and SSL requests. Clears memory used by the script.

This command is used at the end of every HTTP script. DO\_FreeHttp is automatically inserted during the convert process and should never need to be adjusted.

### Syntax

```
DO_FreeHttp( );
```

### Return Value

### Parameters

None.

Example

```
...
...
END_TRANSACTION();
DO_FreeHttp();
REPORT(SUCCESS);
```

DO\_GetAnchorByNumber

Applies to HTTP and SSL requests. Stores the value of an anchor from an HTML reply into a string that can be substituted into subsequent requests.

This command is used when an anchor is embedded in an HTML reply at a known location, but the anchor text may change. For example, a search engine returns a page with 10 anchors in response to a query, and the business logic for the transaction requires clicking on the third anchor regardless of the text for that anchor.

Syntax

```
int DO_GetAnchorByNumber( int anchorNumber, char **anchorValue );
```

Returns

- 1 if successful
- 0 if unsuccessful

Parameters

Parameter	Description
anchorNumber	A number which is the count of the anchor to be retrieved.
anchorValue	Address to a string where the anchor value is stored.

Example

```
...
char *AnchorByNumber= NULL;
...
BEGIN_TRANSACTION();
...
DO_GetAnchorByNumber(3, &AnchorByNumber);
...
DO_SetValue("AnchorByNumber", AnchorByNumber);
...
DO_Http("GET {*AnchorByNumber} HTTP/1.0\r\n"
        "Accept: */*\r\n"
        "Referer: http://company/cgi-bin/perl_9.pl\r\n"
        "Host: company\r\n"
        "Cookie: username=anu; c2_LastVisit=6\r\n\r\n");
...
if ( AnchorByNumber )
{
free(AnchorByNumber);
AnchorByNumber= NULL;
}
...
END_TRANSACTION();
```

## DO\_GetAnchorCount

Applies to HTTP and SSL requests. Returns the total number of the anchors on the page.

### Syntax

```
int DO_GetAnchorCount()
```

### Return Type

Integer

### Parameters

none


### Example

```
int n;
char *Anchor[1]= { NULL };
...
n= DO_GetAnchorCount();
DO_GetAnchorByNumber ( n/2, &Anchor[ 0 ] );
```

## DO\_GetAnchorHREF

Applies to HTTP and SSL requests. Stores the value of a named anchor off of an HTML reply into a string that can be substituted into subsequent requests.

This command is used when an anchor to a CGI request is embedded in a dynamic HTML reply (for instance, the results from a search engine query). The DO\_GetAnchorHREF function is automatically inserted by QALoad during conversion whenever this situation is encountered.

 Note: If you are adding commands, QALoad uses the following rules for matching the anchorName parameter to the <img> tag and anchor text. To modify this command in a script, take the syntax in the attribute (the value for the alt= or src= tags) and append it to either the "alt=" or "src=" (case sensitive) attribute.

! If there is an <img> tag in the source HTML, use the alt= attribute.

Example:

FOR: <a href="x.html">click</a>

USE: DO\_GetAnchorHREF ( "alt=look", Anchor [0] );

! If the <img> tag has no alt= attribute, use the src= attribute.

Example:

FOR: <a href="x.html">click</a>

USE: DO\_GetAnchorHREF ( "src=look.gif", Anchor [0] );

! If there is no <img> tag, use the anchor text between <a> and </a>.

Example:

FOR: <a href="x.html"> <b> click here </b> </a>

USE: DO\_GetAnchorHREF ( "click here", Anchor [0] );

The anchor text is made by removing all HTML tags and spaces. Words are extracted and put together separated by a single space.

### Syntax

```
int DO_GetAnchorHREF( const char *anchorName, char **anchorValue );
```

### Return Value

1 if successful.  
0 if unsuccessful.

### Parameters

Parameter	Description
anchorName	String constant specifying the name of the anchor to retrieve from the reply.
anchorValue	Address to a string where the anchor value is stored.

### Example

```

...
...
char *Anchor[1];
...
...
for(i=0;i<1;i++)
Anchor[i]=NULL;
...
...
BEGIN_TRANSACTION();
...
...
DO_GetAnchorHREF( "Resubmit", &Anchor[0]);
DO_SetValue("Anchor000", Anchor[0]);
DO_Http("GET {*Anchor000} HTTP/1.0\r\n"
        "Accept: */*\r\n"
        "Referer: http://company/cgi-bin/perl_9.pl\r\n"
        "Host: company\r\n"
        "Cookie: username=anu; c2_LastVisit=6\r\n\r\n");
...
...
for(i=0; i<1; i++)
{
free(Anchor[i]);
}
...
...
END_TRANSACTION();
...
...

```

### DO\_GetAnchorHREFEx

Applies to HTTP and SSL requests. Stores the value of a specific occurrence of a named anchor off an HTML reply into a string that can be substituted into subsequent requests.

This command is used when an anchor to a CGI request is embedded in a dynamic HTML reply, for example, the results from a search engine query, more than once. The which parameter specifies the occurrence of the anchor to retrieve. The DO\_GetAnchorHREFEx function is automatically inserted by QALoad during conversion whenever this situation is encountered.

If you are adding commands to match the anchorName parameter to the <img> tag and anchor text, see the note and examples for [DO\\_GetAnchorHREF](#).

### Syntax

```
int DO_GetAnchorHREFEx( const char *anchorName, int count, char **anchorValue );
```

## Return Value

1 if successful  
0 if unsuccessful

## Parameters

Parameter	Description
anchorName	String constant specifying the name of the anchor to retrieve from the reply.
count	Which occurrence of the anchor to retrieve.
anchorValue	Address to a string where the anchor value is stored.

## Example

```

...
...
char *Anchor[1];
...
...
for(i=0;i<1;i++)
Anchor[i]=NULL;
...
...
BEGIN_TRANSACTION();
...
...
DO_GetAnchorHREFEx( "Resubmit", &Anchor[0], 1 );
DO_SetValue("Anchor000", Anchor[0]);
DO_Http("GET {*Anchor000} HTTP/1.0\r\n"
        "Accept: */*\r\n"
        "Referer: http://company/cgi-bin/perl_9.pl\r\n"
        "Host: company\r\n"
        "Cookie: username=anu; c2_LastVisit=6\r\n\r\n");
...
...
for(i=0; i<1; i++)
{
free(Anchor[i]);
}
...
...
END_TRANSACTION();
...
...

```

## DO\_GetAnchorHREFn

Applies to HTTP and SSL requests. Stores the value of a specific occurrence of a named anchor off of an HTML reply into a string that can be substituted into subsequent requests.

This command is used when an anchor to a CGI request is embedded in a dynamic HTML reply, for instance, the results from a search engine query, more than once. The which parameter specifies the occurrence of the anchor to retrieve. The DO\_GetAnchorHREFn function is automatically inserted by QALoad during conversion whenever this situation is encountered.

If you are adding commands, to match the anchorName parameter to the <img> tag and anchor text, see the note and examples under [DO\\_GetAnchorHREF](#).

## Language Reference Commands

### Syntax

```
int DO_GetAnchorHREFn( const char *anchorName, char **anchorValue, int count );
```

### Return Value

1 if successful  
0 if unsuccessful

### Parameters

Parameter	Description
anchorName	String constant specifying the name of the anchor to retrieve from the reply.
anchorValue	Address to a string where the anchor value is stored.
count	The occurrence of the anchor to retrieve.

### Example

```
...
...
char *Anchor[1];
...
...
for(i=0;i<1;i++)
Anchor[i]=NULL;
...
...
BEGIN_TRANSACTION();
...
...
DO_GetAnchorHREFn( "Resubmit", &Anchor[0], 3);
DO_SetValue("Anchor000", Anchor[0]);
DO_Http("GET {*Anchor000} HTTP/1.0\r\n"
        "Accept: */*\r\n"
        "Referer: http://company/cgi-bin/perl_9.pl\r\n"
        "Host: company\r\n"
        "Cookie: username=anu; c2_LastVisit=6\r\n\r\n");
...
...
for(i=0; i<1; i++)
{
free(Anchor[i]);
}
...
...
END_TRANSACTION();
...
...
```

### DO\_GetCitrixICAFile

Saves a WWW reply when its body is an ICA file.

This function will save a WWW reply when its body is an ICA file. If the reply is an ICA file then the ICA file will be saved to the "QALoad\ BinaryFiles" directory with the following naming convention: "script name\_vuNN\_XX.ica", where NN is the "absolute virtual user number" and NN is the transaction number. This file location can then be used within Citrix CtxConnectICA() command.

### Syntax

```
int DO_GetCitrixICAFile (char ** szFileName);
```



### Return Value

Returns 1 if the function call was successful, else 0 if an error occurs.

### Parameters

Parameter	Description
szFileName	Address to a string that specifies the location of the ICA that was sent back as part of the server reply.

### Example

```

...
...
char *strICAFileName[1];
...
...
for(i=0;i<1;i++)
strICAFileName[i]=NULL;
...
...
BEGIN_TRANSACTION();
...
...
DO_Http("GET http://citrixserver/ica/notepad/ HTTP/1.0\r\n\r\n")
DO_GetCitrixICAFile(&strICAFileName[0]);
...
...
RR_printf("ICA file = %s",strICAFileName[0]);
...
CtxConnectICA(strICAFileName[0];
...
...
for(i=0; i<1; i++)
{
if(strICAFileName[i] != NULL)
unlink(strICAFileName[i]);
free(strICAFileName[i]);
strICAFileName[i]=NULL;
}
...

```

...

END\_TRANSACTION();

## DO\_GetClientMapHREF

Applies to HTTP and SSL requests. DO\_GetClientMapHREF is used to extract the href URL from a particular region of a client-side image map.

Client-side image maps are specified within an HTML document by the 'map' tag. Inside the 'map' tag, 'a' and 'area' tags are used to specify regions of the image map. The href attribute of the 'a' or 'area' tags specify the location of the URL to go to.

### Syntax

```
BOOL DO_GetClientMapHREF ( int nMapCount, int nRegionCount, char ** pszURL );
```

### Return Value

TRUE for successful  
FALSE for unsuccessful.

### Parameters

Parameter	Description
sMapCount	Count of 'map' tags inside the HTML. The map count can be wrapped in the MAP macro to make the script more readable.
nRegionCount	Count of 'a' and 'area' tags inside of the 'map' tag. The region count can be wrapped in the REGION macro to make the script more readable.
pszURL	Address of a string pointer to hold the href URL for the map and region.

### Example

```
char * ClientMapURL [1];
...
...
BEGIN_TRANSACTION();
...
...

/* Request: 1 */

DO_Http ("GET http://company.com/ HTTP/1.0\r\n\r\n" );
DO_GetClientMapHREF( MAP(1), REGION (1), &ClientMapURL [0] );

/* Request: 2 */

DO_SetValue ("ClientMap000", ClientMapURL [0] );
DO_Http ("GET {*ClientMap000} HTTP/1.1\r\n\r\n" );
...
...
```

## DO\_GetCookie

Applies to HTTP and SSL requests. Extracts a cookie from the QALoad internal cookie list.

The cookie is retrieved based on the name of the cookie. Wildcard patterns can be used to specify the cookie name in case the cookie name is dynamic. A count is also specified in case multiple cookies match the specified name.

 Note: DO\_GetCookie requires DO\_DynamicCookieHandling be set to TRUE

## Syntax

```
BOOL DO_GetCookie ( const char * szName, int nCount, char ** pszCookie
pszCookie );
```

## Return Value

TRUE for successful  
FALSE for unsuccessful

## Parameters

Parameter	Description
szName	Name of the cookie to get. Wildcard patterns, like '*' to match anything can be used.
nCount	Count of which occurrence to get.
pszCookie	Address of a string pointer to hold the cookie.

## Example

```
char * userid;
char * aspsessionid;
...
...
BEGIN_TRANSACTION();
...
...
/* Request: 1 */
DO_Http ( "GET http://company.com/HTTP/1.0\r\n\r\n" );
/*
 * Get a cookie named USER_ID
 */
DO_GetCookie ( "USER_ID", 1, &userid );
/*
 * Get the second ASPSESSIONID cookie. ASPSESSIONID
 * cookies always have extra characters on the end to make
 * them unique.
 *
 * An example ASPSESSIONID: ASPSESSIONIDQQGGQDO=EBOOONBBFH
 * BBELAJIMEFAKAP
 */
DO_GetCookie ( "ASPSESSIONID*", 2, &aspsessionid );
```

## DO\_GetCookieFromReplyEx

Applies to HTTP and SSL requests. Retrieves and stores the value of a cookie when a Set-Cookie: statement is encountered in a reply header.

A stored cookie can be used later in the script in a DO\_SetValue command to pass the cookie value on to subsequent requests. QALoad's Convert facility automatically inserts a DO\_GetCookieFromReplyEx into the script if it detects a Set-Cookie: header field.

Although this function is still valid, QALoad now includes an improved option to automatically provide the same functionality. See [DO\\_DynamicCookieHandling](#) for details.

### Syntax

```
DO_GetCookieFromReplyEx( const char *cookieName, char **cookieValue, char match );
```

### Return Value

None.

### Parameters

Parameter	Description
cookieName	String constant that specifies the name of the cookie to retrieve from the reply.
cookieValue	Address to a string where the cookie value is stored.
match	A wildcard character to use for regular expression matching before or after the cookie name. The default used by QALoad is the asterisk character (*).

### Example

```
...
...
/* Declare Variables */
char *Cookie[1];
...
...
for(i=0;i<1;i++)
Cookie[i]=NULL;
...
...
BEGIN_TRANSACTION();
...
...
DO_DynamicCookieHandling(FALSE);
...
...
DO_GetCookieFromReplyEx("NUM", &Cookie[0], '*');
DO_SetValue("cookie000", Cookie[0]);
DO_Http("GET http://company.com/cgi-bin/cookiespipes.pl "
        "HTTP/1.0\r\n"
        "Accept: */*\r\n"
        "Host: company.com\r\n"
        "Cookie: HTMMLA=FONTSIZE=LARGE; {*cookie000}; "
        "SITESERVER=ID=4b4ab9751bce9a95f74ec62\r\n\r\n");
...
...
for(i=0; i<1; i++)
{
free(Cookie[i]);
Cookie[i]=NULL;
END_TRANSACTION();
...
...

```

### DO\_GetCookiesForURL

Applies to HTTP and SSL requests. DO\_GetCookiesForURL sends a message to the QALoad internal cookie storage requesting a list of cookies for this URL. The cookies are returned in a semicolon-separated list of cookies. Each cookie in the returned cookie list is put into the “name=value” form. The returned cookie list is suitable to be used as a cookie header for an HTTP request.

 Note: DO\_GetCookiesForURL requires DO\_DynamicCookieHandling be set to TRUE.

### Syntax

```
BOOL DO_GetCookiesForURL ( const char * szURL, char ** pszCookie );
```

### Return Value

TRUE for successful

FALSE for unsuccessful

### Parameters

Parameter	Description
szURL	The requested URL
pszCookies	Address of a string pointer to hold the cookies.

### Example

```
char * cookielist= NULL;
...
...
BEGIN_TRANSACTION();
...
...
/* Request: 1 */
/*
 * In this request two cookies will be set. CookieA will have the value of ValueA and
 * CookieB will have the value of ValueB.
 *
 * Set-Cookie: CookieA=ValueA; domain=.company.com; path=/;
 * Set-Cookie: CookieB=ValueB; domain=.company.com; path=/;
 */
DO_Http ( "GET http://www.company1.com/ HTTP/1.0\r\n\r\n" );
/*
 * Get all cookies set for http://www.company1.com/. After this call cookielist will have
 * the value "CookieA=ValueA; CookieB=ValueB.
 */
DO_GetCookiesForURL ( "http://www.company1.com/", &cookielist );
/*
 * Now make a request to company 2 with all the cookies from www.company1.com to
 * www.company2.com.
 */
DO_SetValue ( "CompanyCookies", cookielist );
DO_Http ( "GET http://www.company2.com/ HTTP/1.0\r\n\r\n"
         "Cookie: {*CompanyCookies}\r\n\r\n" );
```

## DO\_GetFormActionStatement

Applies to HTTP and SSL requests. Gets the ACTION tag from a requested form.

This feature is useful when a form dynamically changes what is stored in the ACTION tag.

### Syntax

```
int DO_GetFormActionStatement( int nFormnum, char **ActionURL );
```

### Return Value

1 for successful  
0 for unsuccessful

### Parameters

Parameter	Description
nFormnum	Specifies which form on a response to retrieve the ACTION tag from.
ActionURL	Address of the string where the ACTION tag will be stored.

### Example

```
...
...
char *ActionURL[1];
...
...
for(i=0;i<1;i++)
ActionURL[i]=NULL;
...
...
BEGIN_TRANSACTION();
...
...
DO_GetFormActionStatement(Form (1), &ActionURL[0]);
DO_SetValue("action_statement0", ActionURL[0]);
DO_Http("POST {*action_statement0} HTTP/1.0\r\n"
        "Content-Type: multipart/form-data; boundary="
        "-----7d04c2740364\r\n"
        "Host: company\r\n"
        "Content-Length: {*content-length}\r\n"
        "Cookie: username=anu; c2_LastVisit="
        "Mon%20Mar%2013%0; c2_NumVisits=\r\n"
        "Content-Disposition: form-data; name=\"entry \r\n\r\n\r\n"
        "-----7d04c2740364\r\n\r\n");
...
...
for(i=0; i<1; i++)
{
free(ActionURL[i]);
}
END_TRANSACTION();
...
...
```

## DO\_GetFormValueByName

Applies to HTTP and SSL requests. Retrieves the value embedded in a form for the specified field.

Subsequently, this value can be used in a call to the `DO_SetValue` command to pass it along to the CGI script associated with this form. `DO_GetFormValueByName` is generally seen when hidden fields are encountered in a form. QALoad's Convert facility automatically generates these commands for hidden fields.

### Syntax

```
GetFormValueByName( int form_number, const char *field_type, const char *field_name, int
count, char **value );
```

### Parameters

Parameter	Description
form_number	Integer specifying which form to search in an HTML document.
field_type	Type of field to search.
field_name	Name of the field to search.
count	If more than one field has the same name, a number specifying each field.
value	Address to a string where the result value will be stored.

### Example

```
...
...
char *Field[2];
...
...
for(i=0;i<2;i++)
Field[i]=NULL;
...
...
BEGIN_TRANSACTION();
...
...
DO_GetFormValueByName(FORM (1), "hidden", "hidden", 1, &Field[0]);
DO_GetFormValueByName(FORM (1), "hidden", "hidden1", 1, &Field[1]);
...
...
DO_SetValue("hidden", Field[0]);
DO_SetValue("hidden1", Field[1]);
...
...
BeginCheckpoint(); /* *FORM* */
DO_Http("POST {*action_statement0} HTTP/1.0\r\n"
        "Content-Type: application/x-www-form-urlencoded\r\n"
        "Host: company\r\n"
        "Content-Length: {*content-length}\r\n\r\n"
        "{name }&{hidden}&{hidden1}&{submit}");
...
...
DO_HttpCleanup();
for(i=0; i<2; i++)
{
free(Field[i]);
}
...
...
END_TRANSACTION();
...
...
...
```

## DO\_GetHeaderFromReply

Applies to HTTP and SSL requests. Retrieves the value of a header in the reply resulting from a DO\_HTTP command.

### Syntax

```
int DO_GetHeaderFromReply ( char *header, const char *output_buffer, int nLength )
```

### Return Value

1 for success  
0 for unsuccessful

### Parameters

Parameter	Description
header	A header to look for in the reply.
output_buffer	A string to store the result. Memory should already be allocated for it.
nLength	The length of space available in the output buffer.

### Example

```
char OutputBuf[256];
...
...
BEGIN_TRANSACTION();
...
...
DO_Http("GET http://company.com/ HTTP/1.0\r\n"
        "Accept: image/gif, image/x-xbitmap, */*\r\n"
        "Host: company.com\r\n"
        "Cookie: HTMLA=FONTSIZE=LARGE; SITESERVER=ID="
        "4b5b75c9dda4ab9751bce9a95f74ec62\r\n\r\n");
DO_GetHeaderFromReply("Content-Length:", OutputBuf, 255);
...
...
```

## DO\_GetLastHttpError

Applies to HTTP and SSL requests. Retrieves the integer indicating the error code of the last HTTP request sent with DO\_Http.

Errors greater than 399 include the "Page not found" 404 error.

### Syntax

```
int DO_GetLastHttpError();
```

### Return Value

Returns the error code, or 0 if unsuccessful.

### Parameters

None.

### Example

```
int error;
char errorString[50];
...
...
```



```

BEGIN_TRANSACTION();
...
...
/* Request: 1 */
DO_Http("GET http://company.com/ HTTP/1.0\r\n"
        "Accept: */*\r\n"
        "Host: company.com\r\n\r\n");
if ((error = DO_GetLastHttpError()) > 399)
{
    sprintf (errorString, "Error in response: %d\n", error);
    WWW_FATAL_ERROR ("DO_Http", errorString);
}
...
...

```

## DO\_GetRedirectedURL

Applies to HTTP requests. Modifies the parameter passed in for use in the next request.

This function is still supported, however, [DO\\_DynamicRedirectHandling](#) is preferred.

### Syntax

```
int DO_GetRedirectedURL (char **URL)
```

### Return Value

1 for successful  
0 for unsuccessful

### Parameters

Parameter	Description
URL	An address to a string.

### Example

```

DO_Http(http_statement);

/* RedirectedURL[0]="http://company/cgi-bin/pm3D.htm"*/
DO_GetRedirectedURL(&RedirectURL[0]);

/* Request: 10 * From: QALoad WWW Capture Examples */
DO_SetValue("redirect_statement0", RedirectURL[0]);
DO_Http("GET {*redirect_statement0} HTTP/1.0\r\n"
        "Accept: */*\r\n"
        "Referer: http://company/index.htm\r\n"
        "Accept-Language: en-us\r\n"
        "Accept-Encoding: gzip, deflate\r\n"
        "Host: company\r\n\r\n");

```

## DO\_GetReplyBuffer

Applies to HTTP and SSL requests. `DO_GetReplyBuffer` returns the HTTP response from the last `DO_Http` request.

### Syntax

```
Const char * DO_GetReplyBuffer()
```

## Language Reference Commands

### Return Value

The last HTTP reply or NULL if unsuccessful.

### Parameters

None.

### Example

```
const char * data;
...
...
BEGIN_TRANSACTION();
...
...

/* Request: 1 */

DO_Http("GET http://company.com/ HTTP/1.0\r\n\r\n" );
data = strstr(DO_GetReplyBuffer(), "data_key" );
if ( data == NULL )
{
  WWW_FATAL_ERROR ("DO_Http", "Data_key was missing in reply" );
}
...
...
```

## DO\_GetReplyBufferLength

Applies to HTTP and SSL requests. DO\_GetReplyBuffer returns the length of the HTTP response from the last DO\_Http request.

### Syntax

```
int DO_GetReplyBufferLength()
```

### Return Value

The length of the last HTTP reply or 0 if there is no response found.

### Parameters

None.

### Example

```
int bufLength;
...
...
BEGIN_TRANSACTION();
...
...

/* Request: 1 */

DO_Http("GET http://company.com/ HTTP/1.0\r\n\r\n" );
bufLength = DO_GetReplyBufferLength();
...
...
```

## DO\_GetUniqueString

Applies to HTTP and SSL requests. Used to parse the most recent HTTP server reply to get the contents of a string that occurs between the left and right input strings.

## Syntax

```
char *DO_GetUniqueString( const char *left, const char *right );
```

## Return Value

The string (null-terminated) of characters between the left and right search strings provided as input. NULL If either the left or right search strings are not found.

DO\_GetUniqueString allocates enough space in the parameter passed in as the string buffer to hold the string (including the NULL). Please remember to free any memory after using the returned string. Any memory created with this command that is not explicitly freed results in a memory leak.

 **Note:** If the string buffer parameter has a non-NULL value when passed to this function, the memory is leaked.

## Parameters

Parameter	Description
left	A string containing the left search string.
right	A string containing the right search string.

## Example

```
char *p;
char temp[1000];
...
...
DO_Http("GET HTTP://www.yahoo.com HTTP/1.0\r\n"
        "Referer: HTTP://company/index.htm\r\n"
        "Proxy-Connection: Keep-Alive\r\n"
        "User-Agent: Mozilla/3.01 WinNT;I)\r\n"
        "Host: www.yahoo.com\r\n"
        "Accept:*/*\r\n");
p = DO_GetUniqueString( "text to the left side of the string",
                       "text to the right side of the string" );
if (p != NULL )
{
    strcpy( temp, p );
    free( p );
}
RR_printf( "String value = %s", temp );
```

## DO\_GetUniqueStringEx


Applies to HTTP and SSL requests. Used to parse a null-terminated input string (search) to get the contents of a string that occurs between the left and right input strings.

## Syntax

```
char *DO_GetUniqueStringEx( const char *search, const char *left, const char *right );
```

## Return Value

The string (null-terminated) of characters between the left and right search strings provided as input. NULL if either the left or right search strings are not found.

 **Note:** DO\_GetUniqueStringEx allocates enough space to hold the string (including the NULL). Any memory created with the use of malloc results in a memory leak. Please remember to free any memory after the usage of the returned string.

### Parameters

Parameter	Description
search	A string to be searched.
left	A string containing the left search string.
right	A string containing the right search string.

### Example

```

char *p;
char temp[1000];
...
...
strcpy( temp, "Here is the search string." );
p = DO_GetUniqueStringEx( temp, "the", "string" );

if ( p != NULL )
{
    RR_printf( "String value = %s", p );
    free( p );
}
else
{
    RR_printf( "String not found" );
}

```

### DO\_Http

Applies to HTTP requests. Executes an HTTP request in the script.

DO\_Http sends the request to the server. Any responses to the request are then processed by DO\_Http and returned to the script. DO\_Http returns text replies to the script.

### Syntax

```
char *DO_Http( const char *http_statement );
```

### Return Value

Character string containing the response from the server.

### Parameters

Parameter	Description
http_statement	String containing a valid HTTP request to be sent to a server.

### Example

```

...
...
DO_Http( "GET HTTP://www.yahoo.com HTTP/1.0\r\n"
        "Referer: HTTP://company/index.htm\r\n"
        "Proxy-Connection: Keep-Alive\r\n"
        "User-Agent: Mozilla/3.01 WinNT;I)\r\n"
        "Host: www.yahoo.com\r\n"
        "Accept: */*\r\n" );
...
...

```

## DO\_HttpCleanup

Applies to HTTP and SSL requests. Performs all necessary cleanup operations when a script exits or the user terminates the script.

 **Note:** This command is the same as DO\_Clear (TRANSACTION).

### Syntax

```
DO_HttpCleanup( );
```

### Return Value

### Parameters

None.

### Example

```
...
...
DO_Http("GET HTTP://www.yahoo.com HTTP/1.0\r\n"
        "Referer: HTTP://company/index.htm\r\n"
        "Proxy-Connection: Keep-Alive\r\n"
        "User-Agent: Mozilla/3.01 WinNT;I)\r\n"
        "Host: www.yahoo.com\r\n"
        "Accept: */*\r\n");
...
...
DO_HttpCleanup();
...
...
END_TRANSACTION();
...
...
```

## DO\_Https

Applies to SSL requests. Makes a secured request to the server specified by the http\_statement.

This command returns a string containing the HTML response from the secured server.

### Syntax

```
DO_Https ( const char *http_statement );
```

### Return Value

Character: String containing the response from the secured server.

### Parameters

Parameter	Description
http_statement	A string containing the URL of the secured server and any headers to be sent.

### Example

```
...
...
DO_Https("GET HTTPS://www.yahoo.com HTTP/1.0\r\n"
        "Referer: HTTP://company/index.htm\r\n"
        "Proxy-Connection: Keep-Alive\r\n");
```

## Language Reference Commands

```
"User-Agent: Mozilla/3.01 WinNT;I)\r\n"
"Host: www.yahoo.com\r\n"
"Accept: */*\r\n");
...
...
```

### DO\_HttpVersion

Applies to HTTP and SSL requests. Specifies the version to use in the requests sent during playback.

This affects whether or not the replies may come back chunked. Only HTTP 1.1 requests receive chunked replies.

DO\_HttpVersion is related to the HTTP Version Detection option on the WWW Advanced dialog box. From the Convert Options wizard, access the WWW Advanced dialog box by clicking the Advanced button. The default setting is Auto.

#### Syntax

```
DO_HttpVersion(WWWHTTPVersionEnum version);
```

#### Parameters

Parameter	Description								
version	<p><i>WWWHTTPVersionEnum</i></p> <p>The HTTP version. If specified as Auto, the version used for each request is determined from the request. Valid values are:</p> <table><thead><tr><th>Value</th><th>Description</th></tr></thead><tbody><tr><td>"1.0"</td><td>HTTP version 1.0</td></tr><tr><td>"1.1"</td><td>HTTP version 1.1</td></tr><tr><td>"AUTO"</td><td>HTTP version is set in DO_Http and DO_Https</td></tr></tbody></table>	Value	Description	"1.0"	HTTP version 1.0	"1.1"	HTTP version 1.1	"AUTO"	HTTP version is set in DO_Http and DO_Https
Value	Description								
"1.0"	HTTP version 1.0								
"1.1"	HTTP version 1.1								
"AUTO"	HTTP version is set in DO_Http and DO_Https								

#### Example

```
DO_HttpVersion("Auto");
```

### DO\_InitHttp

Applies to HTTP and SSL requests. Also applies to Visual Scripting. Sets all necessary internal variables needed to load test an HTTP script.

Use this command at the beginning of every HTTP script, but never more than once in a script.

 **Note:** This function should be written exactly as shown below.

#### Syntax

```
DO_InitHttp(PLAYER_INFO *sInfo);
```

#### Return Value

#### Parameters

Parameter	Description
-----------	-------------

sInfo	A pointer to a PLAYER_INFO memory structure.
-------	--

### Example

```

...
...
int rrobot_script(s_info)
PLAYER_INFO *s_info;
{
...
...
DO_InitHttp(s_info);
...
...
BEGIN_TRANSACTION();
...
...
}

```

### DO\_IPSpooFEnable

Applies to HTTP and SSL requests. Enables each virtual user to appear to the web server as being sourced from a different network interface card.

This command is placed after the DO\_InitHttp command. It is useful for those applications where the server keys off the originating IP address. To utilize this feature, the Player system must be configured with multiple static IP addresses. In addition, a local datapool file containing a list of valid IP addresses must be available to the Player. The Player tab on the QALoad Conductor Options dialog box provides an option for creating this local datapool file for NT-based Players.

The datapool file name defaults to using the datapool file pointed to by the qaload\_ipspooF environment variable. This variable is automatically set when QALoad is installed on an NT-based system. Users of the UNIX-based Players must add this variable manually. The parameter to this command can be used to override the contents of the environment variable.

### Syntax

```
Const char *DO_IPSpooFEnable(const char *filename);
```

### Return Value

A string containing the IP address.

### Parameters

Parameter	Description
Filename	String containing a fully qualified path name. This file contains a list of IP addresses to use. Set to "" to use the filename specified in the qaload_ipspooF environment variable.

### Example

```

...
...
DO_IPSpooFEnable( "c:\\qaload\\ myipspooF.dat" );
BEGIN_TRANSACTION();
...
...


```

## DO\_NTLMAuthorization

Applies to HTTP requests. Provides user ID and password (plain text or encrypted) information for Integrated Windows Authentication.

DO\_NTLMAuthorization is related to the Integrated Windows Authentication (formerly NTLM) option on the QALoad Script Development Workbench Record Advanced Options. When you select that option and enter user ID and password information, DO\_NTLMAuthorization(string, string) is written to your script. QALoad attempts to use the user ID and password you entered to access the site. If the information is not accepted, QALoad reports the error and aborts.

At test time, when QALoad encounters an Integrated Windows Authentication controlled site, it uses the Integrated Windows Authentication user ID and password that are provided to access that site.

 **Note:** Integrated Windows Authentication user names and passwords can be variablized by machine, but not by user.

### Syntax

```
DO_NTLMAuthorization(const char *name, const char *password);
```

### Return Value

### Parameters

Parameter	Description
name	A valid user ID for the Integrated Windows Authentication-enabled site.
password	A valid password corresponding to the user ID.

### Examples

#### Example 1:

```
...
...
BEGIN_TRANSACTION();
...
...
DO_NTLMAuthorization("user-id", "~encr~2038520348AKJAS");
...
...
END_TRANSACTION();
...
...
```

 **Note:** String must be enclosed in quotation marks (""), unless NULL is used.

#### Example 2:

When the user ID, password, and domain are provided:

```
DO_NTLMAuthorization("domain\\user_id", "~encr~506C205A545D");
```

#### Example 3:

When the domain is not provided:

```
DO_NTLMAuthorization("user_id", "~encr~506C205A545D");
```

#### Example 4:

When NULL is used and access is provided:

```
DO_NTLMAuthorization(NULL, NULL);
```



 Note: NULL is not enclosed in quotes.

## DO\_ProxyAuthorization

Provides the username and password to access a password protected proxy server.

The password may be encrypted using QALoad's "~encr~" encryption. The username and password are inserted automatically as necessary during conversion. Note that you can variablize the username and password to emulate different users accessing the resources.

### Syntax

```
DO_ProxyAuthorization(const char *username, const char *password);
```

### Return Value

### Parameters

Parameter	Description
username	A valid user name for the resource you're attempting to access.
password	The associated password.

### Example

```
DO_HttpVersion("Auto");
DO_SLEEP(2);

/* Request: 1 */

DO_ProxyAuthorization("smith", "~encr~0E636502080E");

BeginCheckpoint(" http://iris/redline - chkpt: 1");

DO_Http("GET http://iris/redline HTTP/1.1\r\n"
"Accept: image/gif, image/x-xbitmap, image/jpeg, image/pjpeg, "
"application/vnd.ms-excel, application/msword, "
"application/vnd.ms-powerpoint, */*\r\n"
"Accept-Language: en-us\r\n"
"Accept-Encoding: gzip, deflate\r\n"
"User-Agent: Mozilla/4.0 (compatible; MSIE 5.01; Windows NT; CPWR)\r\n"
"Host: iris\r\n\r\n"
);
```

## DO\_ProxyExceptions

Applies to HTTP and SSL requests. Tells QALoad not to use the proxy server for hosts in the proxy exceptions list, so you can replay requests both inside and outside of the firewall in the same script.

This command is written to the script when the option Automatically configure proxy options and launch browser is selected on the QALoad Script Development Workbench Record Options wizard.

DO\_ProxyExceptions is written to the script between BEGIN\_TRANSACTION and the first request.

### Syntax

```
int DO_ProxyExceptions(const char *list);
```

### Return Value

-1 if the list is NULL.  
0 if successful.

## Parameters

Parameter	Description
list	List of proxy addresses in exceptions list. Note that addresses are separated by commas in the script.

## Example

```

...
...
BEGIN_TRANSACTION();
...
...
DO_UseProxy ("internet.company.com:80" );
DO_SSLUseProxy ("internet.company.com:90" );
DO_ProxyExceptions("company.sample.com, "company2.company.com" );
...
...

```

## DO\_ProxyHttpVersion()

Applies to HTTP and SSL requests. Specifies the version to use in proxy requests sent during playback. This affects whether or not the replies come back chunked. Only HTTP 1.1 requests receive chunked replies.

Do\_ProxyHttpVersion is related to the Proxy HTTP Version option on the General page of the [WWW Convert Options](#) dialog box. The default setting is 1.0.

## Syntax

```
DO_ProxyHttpVersion (const char *version)
```

## Return Value

## Parameters

Parameter	Description
version	The HTTP version ("1.0" or "1.1").

## Example

```
DO_ProxyHttpVersion("1.0");
```

## DO\_SaveReplyType

Applies to HTTP and SSL requests. Specifies types of replies to save.

Normally, only replies returned from the server whose type begin with "text/" are saved. Use DO\_SaveReplyType to specify which type(s) to save. You can specify multiple types if you separate them with a semi-colon (;).

In a reply, the type is specified in the "Content-Type:" tag. You access the reply by saving a pointer returned from the DO\_Http command:

```

char *p;
...
p = DO_Http("GET http://www.nosuch.com/...");

```

## Syntax

```
DO_SaveReplyType(const char *types);
```

## Return Value

## Parameters

Parameter	Description
types	Reply types to save (for example, "text;image/gif" saves replies specified as text or image/gif in the replies' "Content-Type" tag).


## Example

```
...
...
DO_SaveReplyType("text;image/gif");
BEGIN_TRANSACTION();
...
...
```

## DO\_SetAssumedContentType

Applies to HTTP and SSL requests. Sets the default content type if the web server doesn't send a content-type header.

If any reply from a web server doesn't contain a content-type header, then QALoad assumes the content-type is application/octet-stream. application/octet-stream is not processed by QALoad and the body of such a reply is not available. To override the default assumed content-type, use this function to set a new content type.

 **Note:** According to the HTTP specification, returning a response without a content-type is undefined behavior and may indicate a problem on the server.

Setting the assumed content type to text/html allows the reply to be treated as an HTML document.

Once you have set the assumed content type, it does not change until the next call to DO\_SetAssumedContentType.

This command corresponds to the Assumed Content-Type field on the QALoad Script Development Workbench Record Options wizard.

## Syntax

```
DO_SetAssumedContentType(const char *ContentType);
```

## Return Value

## Parameters

Parameter	Description
ContentType	The mime type that is used as the new default content type if the web server doesn't send a content type header.

## Example

```
DO_SetAssumedContentType("text/html");
```

## DO\_SetBaudRate

Applies to HTTP and SSL requests. Causes a virtual user to delay transmission and reception of network traffic to emulate a given modem speed. Returns the baud rate the virtual user will use.

### Syntax

```
int DO_SetBaudRate(int nBaud)
```

### Return Value

Returns the baud rate the virtual user will use.

### Parameters

Parameter	Description
nBaud	The rate the virtual user will use. If nBaud is set to 0, modem emulation is shut off.

### Example

```
...
...
BEGIN_TRANSACTION();
DO_SetBaudRate(28800);
...
...
```

## DO\_SetBaudRateEx

Applies to HTTP and SSL requests. Causes a virtual user to delay transmission and reception of network traffic to emulate a given modem speed. The transmission rate and the reception rate are set as separate values.

### Syntax

```
int DO_SetBaudRateEx (int nTransmissionRate, int nReceptionRate)
```

### Return Value

Returns the transmission rate the virtual user will use.

### Parameters

Parameter	Description
nTransmissionRate	The transmission rate the virtual user will use. If nTransmissionRate is set to 0, modem transmission emulation is shut off.
nReceptionRate	The reception rate the virtual user will use. If nReceptionRate is set to 0, modem reception emulation is shut off.

### Example

```
...
...
BEGIN_TRANSACTION();
DO_SetBaudRateEx(28800, 36600);
...
...
```

## DO\_SetCookie

Applies to HTTP and SSL requests. DO\_SetCookie adds a cookie to the current transaction.

The path of the cookie is "/". The domain of the cookie is the same as the next DO\_Http or DO\_Https request. If you wish to set a particular domain or path, use DO\_SetCookieEx.

Once a cookie is set, it remains for the rest of the transaction. To remove the cookie, use DO\_SetCookieEx with the name of the cookie to remove and an expiration value of -1.

DO\_SetCookie requires DO\_DynamicCookieHandling to be set to TRUE.

### Syntax

```
BOOL DO_SetCookie ( const char * szName, const char * szValue );
```

### Return Value

TRUE for successful  
FALSE for unsuccessful

### Parameters

Parameter	Description
szName	Name of the cookie to set.
szValue	Value of the cookie to set.

### Example

```
...
...
BEGIN_TRANSACTION();
...
...
DO_SetCookie ( "cookie1", "desired value" );
/* Request: 1 */
/*
 * This request will have "cookie1" sent with this request
 */
DO_Http ( "GET http://company.com/ HTTP/1.0\r\n\r\n" );
...
...
```

## DO\_SetCookieEx

Applies to HTTP and SSL requests. DO\_SetCookie adds a cookie to the current transaction.

Once a cookie is set, it remains for the rest of the transaction. To remove the cookie, use DO\_SetCookieEx with the name of the cookie to remove and a max age of -1.

DO\_SetCookie requires DO\_DynamicCookieHandling to be set to TRUE.

### Syntax

```
BOOL DO_SetCookieEx ( const char * szName, const char * szValue,
                     const char * szDomain, const char * szPath,
                     int nMaxAge, BOOL bSecure );
```

### Return Value

TRUE for successful  
FALSE for unsuccessful

## Parameters

Parameter	Description
szName	Name of the cookie to set.
szValue	Value of the cookie to set.
szDomain	Domain of the cookie. The domain of the cookie controls what hosts the cookie is sent to.
szPath	The path of the cookie. The path of the cookie controls when a cookie is sent to a host based on the path of the URL.
nMaxAge	Time to live of the cookie. Use a value of 0 for a session cookie and -1 for an expired cookie.
bSecure	Boolean flag (TRUE or FALSE). If the value is TRUE, then the cookie only is sent with SSL request. If the value is FALSE, then the cookie is sent with HTTP and SSL requests.

## Example

```

...
...
BEGIN_TRANSACTION();
...
...
DO_SetCookieEx ( "cookie1", "desired value", ".company.com", "/", 1000, FALSE );

/* Request: 1 */
/*
 * This request will have "cookie1" sent with this request
 */
DO_Http ( "GET http://company.com/ HTTP/1.0\r\n\r\n" );
...
...

```

## DO\_SetJavascriptCleanupThreshold

Applies to HTTP and SSL requests. Periodically QALoad destroys its internal JavaScript model and recreates it.

DO\_SetJavascriptCleanupThreshold sets a count of the number of times JavaScript parsing is done before destroying and recreating the model. By default, the count is 300.

Cleaning up JavaScript takes CPU time, and the Javascript model takes up more memory the longer the same model is used. To reduce CPU usage, set the count higher. To reduce the memory footprint, set the count lower.

## Syntax

```
DO_SetJavascriptCleanupThreshold(int nThreshold)
```

## Return Value

## Parameters

Parameter	Description
-----------	-------------

nThreshold	Number of JavaScript evaluations to make before cleaning up the JavaScript engine.
------------	--

### Example

```
...
...
DO_SetJavaScriptCleanupThreshold(200);
...
...
```

## DO\_SetJavaScriptLevel

Applies to HTTP requests. Allows user to control the level of JavaScript execution for convert and replay.

### Syntax

```
DO_SetJavaScriptLevel (WWWJavascriptExecutionLevelEnum level );
```

### Return Value

### Parameters

Parameter	Description								
level	<p><i>WWWSetJavaScriptLevelEnum</i></p> <p>JavaScript execution level user sets in the WWW Advanced convert dialog. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>FULL</td> <td>Create/execute scripts that parse through and handle JavaScript.</td> </tr> <tr> <td>LIMITED</td> <td>Create/execute scripts that handle the JavaScript to the same level as QALoad 5.2.</td> </tr> <tr> <td>NONE</td> <td>Create/execute scripts that disregard all JavaScript.</td> </tr> </tbody> </table>	Value	Description	FULL	Create/execute scripts that parse through and handle JavaScript.	LIMITED	Create/execute scripts that handle the JavaScript to the same level as QALoad 5.2.	NONE	Create/execute scripts that disregard all JavaScript.
Value	Description								
FULL	Create/execute scripts that parse through and handle JavaScript.								
LIMITED	Create/execute scripts that handle the JavaScript to the same level as QALoad 5.2.								
NONE	Create/execute scripts that disregard all JavaScript.								

### Examples

```
DO_SetJavaScriptLevel ( FULL );
DO_SetJavaScriptLevel ( LIMITED );
DO_SetJavaScriptLevel ( NONE );
```

## DO\_SetMaxBrowserThreads

Applies to HTTP and SSL requests. Specifies the number of concurrent connections to make for playback.

This command relates to the Max Concurrent Connections option on the WWW Advanced options dialog box. The value you enter in that field is inserted in the script.

## Language Reference Commands

### Syntax

```
DO_SetMaxBrowserThreads(int count);
```

### Return Value

### Parameters

Parameter	Description
count	The number of connections to make. QALoad accepts 1-4. The default is 2.

### Example

```
BEGIN_TRANSACTION();  
DO_SetMaxBrowserThreads(2);
```

## DO\_SetMaximumRetries

Applies to HTTP and SSL requests. Sets the maximum number of times a virtual user should attempt to retrieve a graphic or page that failed.

Similar to the behavior of Netscape and Internet Explorer.

### Syntax

```
DO_SetMaximumRetries(int nValue)
```

### Return Value

### Parameters

Parameter	Description
nValue	The default is 4.

### Example

```
...  
...  
BEGIN_TRANSACTION();  
DO_SetMaximumRetries(5);  
...  
...
```

## DO\_SetPostDelay

Applies to HTTP requests. Sets how many seconds QALoad should wait for a reply from a server after the header has been sent for a POST request.

DO\_SetPostDelay sets will send the header and body of a POST request all at once if set to zero, or it will wait up to the specified number of seconds for the server to respond before sending the body.

### Syntax

```
void DO_SetPostDelay( long delay );
```

### Return Value

None



### Parameters

Parameter	Description
delay	Number of seconds to delay between sending the header and body of a POST request.

### Example

### DO\_SetRefreshTimeout

Specifies how long to wait for a meta refresh or an HTTP refresh header.

The HTML meta tag can set a number of seconds before a refresh. When that number of seconds has expired, then the browser loads the URL specified in the meta refresh.

QALoad's WWW replay only refreshes the page if the number of seconds specified in the refresh is less than or equal to the timeout value set by DO\_SetRefreshTimeout. If the refresh is set too large, then QALoad's WWW replay can get stuck in an infinite loop.

### Syntax

```
int DO_SetRefreshTimeout(int nTimeout);
```

### Parameters

Parameter	Description
nTimeout	How many seconds to wait for a refresh, the default is 0.

### DO\_SetRetryWait

Applies to HTTP and SSL requests. Sets the delay between retries in seconds.

### Syntax

```
DO_SetRetryWait(int nValue)
```

### Return Value

### Parameters

Parameter	Description
nValue	Delay between retries, in seconds. Default is 1.

### Example

```
DO_SetRetryWait(6);
```

## DO\_SetTimeout

Applies to HTTP and SSL requests. Specifies how long to wait for a reply from the server. If a reply is not received within the specified time, the virtual user fails with a fatal error.

DO\_SetTimeout allows you to more closely emulate browser behavior when requests go unanswered due to server or network problems. Normally a browser would wait until it receives a reply or the user cancels the request by clicking the Stop button.

This command relates to the Server Response Timeout option on the WWW Advanced options dialog box. The range of values is 5 to 65535. The default is 120 seconds.

### Syntax

```
DO_SetTimeout(int timeout);
```

### Return Value

### Parameters

Parameter	Description
timeout	The number of seconds to wait. Range of values is 5 to 65535. The default is 120.

### Example

```
DO_SetTimeout(120); /* Maximum time to wait for an HTTP Reply */
```

## DO\_UseEntityList

Applies to HTTP and SSL requests. Decodes non-ASCII character entities.

### Syntax

```
void DO_UseEntityList ( ENTITY_LIST );
```

### Return Value

### Parameters

Parameter	Description
ENTITY_LIST	User-defined Entity list.

### Example

For examples and more information about this command, see [HTML character entities and numeric references](#).

## DO\_UseNumericReferenceList

Applies to HTTP and SSL requests. Decodes non-ASCII numeric references.

## Syntax

```
void DO_UseNumericReferenceList ( NUMERIC_REFERENCE_LIST ) ;
```

## Return Value

## Parameters

Parameter	Description
NUMERIC_REFERENCE_LIST	User-defined Numeric Reference list.

## Example

For examples and more information about this command, see [HTML character entities and numeric references](#).

## DO\_UsePersistentConnections

Applies to HTTP and SSL requests. Turns the use of persistent connections on or off.

It always terminates the current persistent connection if one is present. This allows persistent connections to be reset in transaction loops to better simulate a real user test.

## Syntax

```
void DO_UsePersistentConnections ( BOOL bEnable )
```

## Return Value

None

## Parameters

Parameter	Description
bEnable	A flag indicating if the Use Persistent Connections option should be enabled (1=TRUE, 0=FALSE).


## Example

```
...
...
BEGIN_TRANSACTION();
DO_UsePersistentConnections(1);
...
...
```

## DO\_UseProxy

Applies to HTTP and SSL requests. Specifies a proxy server to use during testing.

If you select the Use a proxy server option on the QALoad Script Development Workbench's Record Options wizard before you record, a DO\_UseProxy command is inserted at the beginning of your script. If you change your proxy server while recording, QALoad's Record facility detects the modification and inserts another DO\_UseProxy() into the script.

 Note: When called with a proxy server that is not found on the network, DO\_UseProxy aborts even when you select "Continue executing and ignore the error" in the Error Handling Options dialog box. See [Anticipating Error Conditions](#) for more information on setting error handling options.

### Syntax

```
int DO_UseProxy( const char *proxy );
```

### Return Value

Always returns 0

### Parameters

Parameter	Description
proxy	String containing the proxy server and port separated by a colon.

### Example

```
...
...
BEGIN_TRANSACTION();
...
...
DO_UseProxy ( "internet:80" );
DO_SSLUseProxy ( "internet.company.com:90" );
DO_ProxyExceptions( "company.sample.com, "company2.company.com" );
...
...
```

## DO\_UseProxyAutomaticConfiguration

Applies to HTTP and SSL requests. Downloads the proxy automatic configuration (PAC) script at the specified URL.

The rest of the transaction uses the PAC script to determine which proxy, if any, to connect to hosts.

### Syntax

```
BOOL DO_UseProxyAutomaticConfiguration ( const char * szUrl );
```

### Return Value

TRUE = successful  
FALSE = unsuccessful

### Parameters

Parameter	Description
szUrl	URL where the proxy automatic configuration script is located.

### Example

```
...
...
BEGIN_TRANSACTION();
DO_UseProxyAutomaticConfiguration( "http://proxy config.host.com/" );
...
...
/*Request: 1*/
/*
*The PAC script downloaded from http://proxyconfig.host.com/
*determine what proxy, if any, to use to connect to
*company.com
```

```
*/
DO_Http ( "GET http://company.com/ HTTP/1.0\r\n\r\n" );
...
...
```

## DO\_VerifyDocTitle

Applies to HTTP and SSL requests. Compares the parameters and match type passed in the parameters against the HTML page title specified in the response received from the HTTP request.

### Syntax

```
int DO_VerifyDocTitle ( const char *szTitle, WWWVerifyDocTitleComparisonTypeEnum nType ) ;
```

### Return Value

Integer value

1 = match found. Indicated by the Player debug window.

0 = match not found. The function calls WWW\_FATAL\_ERROR, which either aborts the test or continues, based upon the ABORT\_ON\_ERROR flag.

### Parameters

Parameter	Description								
szTitle	A character string specifying a title to search for in the HTTP response. This is generated by Convert using the entire document title, the title prefix, or the title suffix, as specified on the QALoad Script Development Workbench Convert Options wizard.								
nType	<p><i>WWWVerifyDocTitleComparisonTypeEnum</i></p> <p>Type corresponding to the comparison options available on the QALoad Script Development Workbench Convert Options wizard. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>TITLE</td> <td>Verify title</td> </tr> <tr> <td>PREFIX</td> <td>Verify title prefix</td> </tr> <tr> <td>SUFFIX</td> <td>Verify title suffix</td> </tr> </tbody> </table>	Value	Description	TITLE	Verify title	PREFIX	Verify title prefix	SUFFIX	Verify title suffix
Value	Description								
TITLE	Verify title								
PREFIX	Verify title prefix								
SUFFIX	Verify title suffix								

### Example

```
DO_Http ( http_statement ) ;
DO_VerifyDocTitle ( "Welcome to Compuware" , TITLE ) ;
```

## DO\_WWWFree

Applies to HTTP and SSL requests. Clears memory used by the script.

This command is used at the end of every HTTP script. DO\_WWWFree is automatically inserted during the convert process and should never need to be adjusted.

### Syntax

```
DO_WWWFree( ) ;
```

Return Value

Parameters

None.

Example

```
...
...
END_TRANSACTION();
DO_WWWFree();
REPORT(SUCCESS);
```

DO\_WWWInitialize

Applies to HTTP and SSL requests. Sets all necessary internal variables needed to load test a WWW script. Use this command at the beginning of every WWW script, but never more than once in a script.

 **Note:** This function should be written exactly as shown below.

Syntax

```
DO_WWWInitialize(PLAYER_INFO *sInfo, WWWConvertModeEnum convertMode);
```

Return Value

Parameters

Parameters	Description						
sInfo	A pointer to a PLAYER_INFO memory structure.						
convertMode	<p><i>WWWConvertModeEnum</i></p> <p>Convert mode options. Valid values include:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>HTML_MODE</td> <td>The script will be run in HTML mode.</td> </tr> <tr> <td>HTTP_MODE</td> <td>The script will be run in HTTP mode.</td> </tr> </tbody> </table>	Value	Description	HTML_MODE	The script will be run in HTML mode.	HTTP_MODE	The script will be run in HTTP mode.
Value	Description						
HTML_MODE	The script will be run in HTML mode.						
HTTP_MODE	The script will be run in HTTP mode.						

Example

```
...
...
int rhobot_script(s_info)
PLAYER_INFO *s_info;
{
...
...
DO_WWWInitialize(s_info, HTML_MODE);
...
...
BEGIN_TRANSACTION();
...
}
```


```
...
}
```

## DownloadMediaFromASX

Applies to Windows Media Player streaming media.

Dynamically parses an ASX file from the previous response and initiates and waits for completion of the specified Windows Media resources download.

DownloadMediaFromASX is a deprecated function. Use a combination of the Click\_On function with the PlayMedia function instead.

 **Note:** For streaming media playback, QALoad requires specific media player versions. For a list of supported versions, refer to "System Requirements" in the "Installing QALoad" chapter of the QALoad Installation and Configuration Guide.

### Syntax

```
DownloadMediaFromASX( int secDuration );
```

### Return Value

### Parameters

Parameter	Description
secDuration	Specifies the number of seconds of media to download. Specifying 0 means read the entire media.

### Example

```
Do_Http("GET http://host/test.asx HTTP/1.0\r\n"
        "Accept: image/gif, image/x-xbitmap, image/jpeg, image/"
        "pjpeg,application/vnd.ms-excel, application/"
        "vnd.ms-powerpoint, msword, */*\r\n"
        "Accept-Language: en-us\r\n"
        "User-Agent: Mozilla/4.0 (compatible; MSIE 6.0; Windows"
        "NT 5.0)\r\n\r\n" );

// Play the media file(s) specified in the ASX file for 50 seconds.
DownloadMediaFromASX(50);
```

## DownloadMediaRP

Applies to Real Networks Streaming Media. Initiates and waits for completion of the specified multi-media resource download.

DownloadMediaRP is a deprecated function. Use a combination of the Click\_On function with the PlayMedia function instead.

### Notes:


- ! Enable streaming media download by selecting the Streaming Media check box on the WWW Advanced Universal Convert Options dialog box in the QALoad Script Development Workbench.
- ! Real Networks streaming media is only supported in process mode. On the QALoad Player main window, in the Run As: group, select the Process option.
- ! For streaming media playback, QALoad requires specific media player versions. For a list of supported versions, refer to "System Requirements" in the "Installing QALoad" chapter of the QALoad Installation and Configuration Guide.

### Syntax

```
DownloadMediaRP( char *URL, int timeout );
```

### Return Value

### Parameters

Parameter	Description
URL	Specifies the location (in URL format) of the streaming media file.
timeout	Specifies the number of seconds of media to play. Specify 0 (the default in the script) to play the entire media transaction. Specify another number, such as a value of 10, to have the timeout buffer the media and play the clip for 10 seconds.  <b>Note:</b> This timeout refers to clip time. The elapsed time of a Real Networks media transaction may be longer than the timeout.


### Example

```
DownloadMediaRP("http://host:8099/ramgen/realvideo.rm", 0);
```

## DownloadMediaWMP

Applies to Windows Media Player streaming media. Initiates and waits for completion of the specified Windows Media resource download.

DownloadMediaWMP is a deprecated function. Use a combination of the [Click\\_On](#) function with the [PlayMedia](#) function instead.

 **Note:** For streaming media playback, QALoad requires specific media player versions. For a list of supported versions, refer to "System Requirements" in the "Installing QALoad " chapter of the QALoad Installation and Configuration Guide.

### Syntax

```
DownloadMediaWMP( char *reqURL, int secDuration );
```

### Return Value

### Parameters

Parameter	Description
reqURL	Specifies the location (in URL format) of the streaming media file.
secDuration	Specifies the number of seconds of media to download. Specify 0 to read the entire media file.

### Example

```
// Requests welcome2.asf from qacmedia over TCP ("mmst://")
// Play the file for 10 seconds
DownloadMediaWMP("mmst://qacmedia/welcome2.asf", 10 );
```



## EnableStatisticsRP

Applies to Real Networks Streaming Media. Enables capture of media player performance statistics during a load test.

Compuware recommends that this function is called in the initial section of a Web script, before the SYNCHRONIZE() call. Although it can be called at any point in the script, this command must appear in the script prior to any DownloadRPMedia call.

### Notes:

- ! Exercise caution when using this feature. Real Networks streaming media uses extra system resources and may degrade performance or skew test results.
- ! By default, capturing statistics is not enabled.
- ! Real Networks streaming media is only supported in process mode. On the QALoad Player main window, in the Run As: group, select the Process option.
- ! For streaming media playback, QALoad requires specific media player versions. For a list of supported versions, refer to "System Requirements" in the "Installing QALoad " chapter of the QALoad Installation and Configuration Guide.

### Syntax

```
EnableStatisticsRP( WWWRPStatsMaskEnum flags, int interval, BOOL traceOutput );
```

### Return Value

### Parameters

Parameter	Description																						
flags	<p><i>WWWRPStatsMaskEnum</i></p> <p>The flag values in the following table can be combined using a logical OR. Flag values include:</p> <p>Values for Meta flags</p> <table border="1"> <thead> <tr> <th>Type</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>QAL_WWW_RN_STAT_ALL_LEVELS</td> <td>All statistic levels.</td> </tr> <tr> <td>QAL_WWW_RN_STAT_PLAYER</td> <td>Player level statistics.</td> </tr> <tr> <td>QAL_WWW_RN_STAT_SOURCE</td> <td>Source level statistics.</td> </tr> <tr> <td>QAL_WWW_RN_STAT_STREAM</td> <td>Stream level statistics.</td> </tr> <tr> <td>QAL_WWW_RN_STAT_ALL</td> <td>Enable all levels, all counters.</td> </tr> <tr> <td>QAL_WWW_RN_STAT_PLAYER_ALL</td> <td>All Media Player level statistics.</td> </tr> <tr> <td>QAL_WWW_RN_STAT_SOURCE_ALL</td> <td>All source level statistics.</td> </tr> <tr> <td>QAL_WWW_RN_STAT_STREAM_ALL</td> <td>All stream level statistics.</td> </tr> <tr> <td>QAL_WWW_RN_STAT_ALL_COUNTERS</td> <td>All counters.</td> </tr> <tr> <td>QAL_WWW_RN_STAT_NORMAL_PKTS</td> <td>Packets not lost, late, etc.</td> </tr> </tbody> </table>	Type	Description	QAL_WWW_RN_STAT_ALL_LEVELS	All statistic levels.	QAL_WWW_RN_STAT_PLAYER	Player level statistics.	QAL_WWW_RN_STAT_SOURCE	Source level statistics.	QAL_WWW_RN_STAT_STREAM	Stream level statistics.	QAL_WWW_RN_STAT_ALL	Enable all levels, all counters.	QAL_WWW_RN_STAT_PLAYER_ALL	All Media Player level statistics.	QAL_WWW_RN_STAT_SOURCE_ALL	All source level statistics.	QAL_WWW_RN_STAT_STREAM_ALL	All stream level statistics.	QAL_WWW_RN_STAT_ALL_COUNTERS	All counters.	QAL_WWW_RN_STAT_NORMAL_PKTS	Packets not lost, late, etc.
Type	Description																						
QAL_WWW_RN_STAT_ALL_LEVELS	All statistic levels.																						
QAL_WWW_RN_STAT_PLAYER	Player level statistics.																						
QAL_WWW_RN_STAT_SOURCE	Source level statistics.																						
QAL_WWW_RN_STAT_STREAM	Stream level statistics.																						
QAL_WWW_RN_STAT_ALL	Enable all levels, all counters.																						
QAL_WWW_RN_STAT_PLAYER_ALL	All Media Player level statistics.																						
QAL_WWW_RN_STAT_SOURCE_ALL	All source level statistics.																						
QAL_WWW_RN_STAT_STREAM_ALL	All stream level statistics.																						
QAL_WWW_RN_STAT_ALL_COUNTERS	All counters.																						
QAL_WWW_RN_STAT_NORMAL_PKTS	Packets not lost, late, etc.																						

## Language Reference Commands

	<p>QAL_WWW_RN_STAT_RECOVERED_PKTS   Packets recovered.</p> <p>QAL_WWW_RN_STAT_RECEIVED_PKTS   Packets received.</p> <p>QAL_WWW_RN_STAT_LOST_PKTS       Packets currently lost.</p> <p>QAL_WWW_RN_STAT_LATE_PKTS       Late packets.</p> <p>QAL_WWW_RN_STAT_CLIP_BANDWIDTH   Bandwidth at which the clip was encoded.</p> <p>QAL_WWW_RN_STAT_AVE_BANDWIDTH   Average bandwidth so far.</p> <p>QAL_WWW_RN_STAT_CUR_BANDWIDTH   Current bandwidth.</p>
interval	Report every <i>n</i> th stat received.
traceOutput	TRUE means send enabled stats to QALoad Player window (if QALoad Player window output is enabled).

### Example

```
// Records, current bandwidth, average bandwidth, and the clip
// bandwidth at the Player (media player) level as often as
// the statistics are updated.
```

```
EnableStatisticsRP( QAL_WWW_RN_STAT_PLAYER |
                   QAL_WWW_RN_STAT_AVE_BANDWIDTH |
                   QAL_WWW_RN_STAT_CLIP_BANDWIDTH |
                   QAL_WWW_RN_STAT_CUR_BANDWIDTH,
                   0, TRUE );
```

### ExtractString

Applies to Visual Scripting. Retrieves data from the virtual browser.

Will extract a text string from within the responses that came back from the last request. This command replaces the old method of extracting a string using the Get command.

#### Syntax

```
string ExtractString ( int nOccurrence, string strPrecede, string strFollow, int nSearchType );
```

#### Return Value

Returns the extracted string. If the extracted string is not found then an appropriate exception will be thrown and caught which will produce an error message specifying why the string was not found.

#### Parameters

Parameter	Description				
nOccurrence	<p>WWWExtractStringNEnum</p> <p>This field specifies which occurrence of the search strings to find before extracting the text between them. Below are the various string formats you can use to specify the occurrence.</p> <table border="1"> <thead> <tr> <th>Type</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td> </td> <td> </td> </tr> </tbody> </table>	Type	Description		
Type	Description				

	N	This will find the Nth occurrence of the search strings within the responses.						
	EXTRACT_LAST	This will find the Last occurrence of the search strings within the responses.						
	EXTRACT_LAST - N	This will find the (Last-Nth) occurrence of the search strings within the responses.						
	EXTRACT_RANDOM	This will calculate a random number between 1 and Last and find this occurrence of the search strings within the responses.						
strPrecede	The Left search string which will precede the text which is to be extracted.							
strFollow	The Right search string which will follow the text which is to be extracted.							
nSearchType	<p>WWWExtractStringSearchtypeEnum</p> <p>Valid values are:</p> <table border="1"> <thead> <tr> <th>Specifier</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>INCLUDE_REDIRS_AND_ADDSUBS</td> <td>Search includes not only the main page, its frames and subrequests but also Redirects and Additional Subrequests. This is the only search method for HTTP scripts.</td> </tr> <tr> <td>NO_REDIRS_AND_ADDSUBS</td> <td>Search only includes the main page, its frames, and its subrequests. This is the default value for HTML scripts.</td> </tr> </tbody> </table>		Specifier	Description	INCLUDE_REDIRS_AND_ADDSUBS	Search includes not only the main page, its frames and subrequests but also Redirects and Additional Subrequests. This is the only search method for HTTP scripts.	NO_REDIRS_AND_ADDSUBS	Search only includes the main page, its frames, and its subrequests. This is the default value for HTML scripts.
Specifier	Description							
INCLUDE_REDIRS_AND_ADDSUBS	Search includes not only the main page, its frames and subrequests but also Redirects and Additional Subrequests. This is the only search method for HTTP scripts.							
NO_REDIRS_AND_ADDSUBS	Search only includes the main page, its frames, and its subrequests. This is the default value for HTML scripts.							

**Example**

The following are examples of using the ExtractString command

```

CLoadString myString = "";
myString = ExtractString (1, "SessionID=\"", "\"", INCLUDE_REDIRS_AND_ADDSUBS);
myString = ExtractString (3, "abc", "def", NO_REDIRS_AND_ADDSUBS);
myString = ExtractString (EXTRACT_LAST, "abc", "def", NO_REDIRS_AND_ADDSUBS);
myString = ExtractString (EXTRACT_LAST - 2, "abc", "def", NO_REDIRS_AND_ADDSUBS);
myString = ExtractString (EXTRACT_RANDOM, "abc", "def", NO_REDIRS_AND_ADDSUBS);
    
```

**Fill\_In**

Applies to Visual Scripting. Used to represent how the user filled in fields on a form before clicking on a submit button.

**Versions**

Versions for Fill\_In are:

```

boolean Fill_In ( WWWControlEnum control_type, string description, string value );
    
```

## Language Reference Commands

boolean [Fill\\_In](#) ( WWWControlEnum control\_type, WWWFillInSpecifierEnum specifier, string description, string value );

boolean [Fill\\_In](#) ( WWWControlEnum control\_type, integer count, WWWFillInSpecifierEnum specifier, string description, string value );

boolean [Fill\\_In](#) ( WWWControlEnum control\_type, integer count, string value );

### Get

Applies to Visual Scripting. Retrieves data from the virtual browser.

#### Versions

Versions for Get are:

page\_id [Get](#) ( WWWGetTypeEnum type );

page\_id [Get](#) ( WWWGetTypeEnum type, string description );

page\_id [Get](#) ( WWWGetTypeEnum type, string description, integer count );

page\_id [Get](#) ( WWWGetTypeEnum type, WWWGetSpecifierEnum specifier, string description );

page\_id [Get](#) ( WWWGetTypeEnum type, WWWGetSpecifierEnum specifier, string description, integer count );

page\_id [Get](#) ( WWWGetTypeEnum type, integer count );

integer [Get](#) ( WWWGetTypeEnum type, WWWGetSpecifierEnum specifier );

string [Get](#) ( WWWGetTypeEnum type, WWWGetSpecifierEnum specifier, string left, string right );

string [Get](#) ( WWWGetTypeEnum type, WWWGetSpecifierEnum specifier, integer count, string left, string right );

string [Get](#) ( WWWGetTypeEnum type, WWWGetSpecifierEnum specifier, string xpath-string );

### GetSiebelValue

Retrieves the value of a Siebel record from the Siebel library and saves it in a Local Variable.

A call to [SiebelUpdatePage](#) before the last request is mandatory to get the value of the Siebel record.

#### Syntax

```
GetSiebelValues(const char* pszSiebelUniqueID);
```

#### Return Value

CLoadString

#### Parameters

Parameter	Description
pszSiebelUniqueID	Unique Record ID of the Siebel parameter whose value is to be retrieved.

#### Example

```
CLoadString var = GetSiebelValue(" S_BC0_RC1_F01" );
```

## ModifyEncoding

ModifyEncoding is used in Visual scripts to convert strings to UTF8, EUCJP or to the language used by the script.

### Syntax

```
char* Modify_Encoding(EncodingLangEnum encodingID, const char* strInput)
```

### Return Value

A char pointer to the encoded string if successful; NULL if not successful.

### Parameters

Parameter	Description								
encodingID	<p><i>EncodingTypeEnum</i></p> <p>Counter data type. Valid values are:</p> <table border="1"> <thead> <tr> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>UTF8</td> <td>UTF8 encoding.</td> </tr> <tr> <td>EUCJP</td> <td>EUCJP encoding.</td> </tr> <tr> <td>SCRIPT_LANGUAGE</td> <td>Script language encoding.</td> </tr> </tbody> </table>	Value	Description	UTF8	UTF8 encoding.	EUCJP	EUCJP encoding.	SCRIPT_LANGUAGE	Script language encoding.
Value	Description								
UTF8	UTF8 encoding.								
EUCJP	EUCJP encoding.								
SCRIPT_LANGUAGE	Script language encoding.								
strInput	The input string.								

### Example

```
Fill_In(TEXT_BOX,NAME_ATTRIBUTE, "q", ModifyEncoding(SCRIPT_LANGUAGE,"Sample text to be converted to UTF-8"));
```

## Navigate\_To

Applies to Visual Scripting. Reads a URL typed in the Web browser's address field and constructs a request to navigate to the URL.

### Versions


Versions of Navigate\_To are:

```
boolean Navigate_To ( string URL );
```

```
boolean Navigate_To ( string URL, WWWNavigateEncodingEnum encoding);
```

## PlayMedia

Applies to Real Networks and Windows streaming media. Initiates and plays back the streaming media file that was stored in a previous call to the [Click\\_On](#) function.

 Notes: Real Networks streaming media is only supported in process mode. On the QALoad Player main window, in the Run As: group, select the Process option. For streaming media playback, QALoad requires specific media player versions. For a list of supported versions, refer to "System Requirements" in the "Installing QALoad" chapter of the QALoad Installation and Configuration Guide.


## Language Reference Commands

### Syntax

```
PlayMedia( int timeout );
```

### Return Value

### Parameters

Parameter	Description
timeout	The maximum amount of time to play back the requested streaming media file. A value of 0 indicates that the entire file should be played.  Note: This timeout refers to clip time. The elapsed time of a Real Networks media transaction will likely be longer than the timeout.

### Example

```
//Play the file for 10 seconds  
PlayMedia(10);
```

### Post\_To

Applies to Visual Scripting. Reads a URL typed in the Web browser's address field as well as the encoding type. It then constructs a request to send a post to the URL.

### Versions

Versions of Post\_To are:

```
boolean Post_To ( string URL );
```

```
boolean Post_To ( string URL, WWWPostContentTypeEnum content-type );
```

```
boolean Post_To ( stringURL, WWWPostContentEncodingEnum encoding );
```

### RandNumString

Applies to Visual Scripting. Generates a random number from minimum to maximum.

### Syntax

```
string RandNumString ( int minimum, int maximum );
```

### Return Value

Returns the generated random number as a string.

### Parameters

Parameter	Description
minimum	The lower bound of the random number.
maximum	The upper bound of the random number.

### Examples

```
RandNumString ( 20, 500 );
```

## Region

Applies to Visual Scripting. Marks the `region_number` parameter as an image map region.

### Syntax

```
string Region ( int region_number );
```

### Return Value

Returns the region number as a string.

### Parameters

Parameter	Description
<code>region_number</code>	The region number.

### Examples

```
// Region returns the string passed into it. It is a label to make
// clicking on a client side image map easier to read.
Click_On(IMAGE, 1, SRC_ATTRIBUTE, "http://host.com/client-map.jpg", Region("2"));

// does the same as
Click_On(IMAGE, 1, SRC_ATTRIBUTE, "http://host.com/client-map.jpg", "2");
```

## RESTART\_TRANSACTION\_BOTTOM

Applies to Visual Scripting. Used to define a point at the end of the transaction for anything that needs to be deallocated or uninitialized.

When transaction restarting occurs for a failed transaction, QALoad first executes any code starting after the call to `RESTART_TRANSACTION_BOTTOM` allowing you to clean up important information and prevent memory leaks before retrying the transaction.

### Syntax

```
RESTART_TRANSACTION_BOTTOM() ;
```

### Return Value

### Parameters

None.

### Example

```
BEGIN_TRANSACTION();
RESTART_TRANSACTION_TOP();
TRANSACTION CODE...
RESTART_TRANSACTION_BOTTOM();
DO_HttpCleanup();
DO_SomeOtherMiddlewareCleanup();
END_TRANSACTION();
```

## RESTART\_TRANSACTION\_TOP

Used to define a point at the beginning of the transaction loop that QALoad can use to rewind the transaction.

`Restart_Transaction_Top` is used if the transaction fails and Restart Transaction error handling has been selected in the QALoad Conductor.

## Language Reference Commands

### Syntax

```
RESTART_TRANSACTION_TOP() ;
```

### Return Value

### Parameters

None.

### Example

```
BEGIN_TRANSACTION() ;  
RESTART_TRANSACTION_TOP() ;  
TRANSACTION CODE...  
RESTART_TRANSACTION_BOTTOM() ;  
DO_HttpCleanup() ;  
DO_SomeOtherMiddlewareCleanup() ;  
END_TRANSACTION() ;
```

### Set

Applies to Visual Scripting. Assigns values to the Virtual Browser, Proxy, and other parts of the QALoad replay. This command sets the properties and attributes of the script.

 **Note:** For Visual Scripting, this command replaces the following EasyScript for WWW commands:

```
DO_AddHeader  
DO_AttachFile  
DO_BasicAuthorization  
DO_Cache  
DO_HttpVersion  
DO_IPSpoofEnable  
DO_NTLMAuthorization  
DO_ProxyAuthorization  
DO_ProxyEceptions  
DO_SaveReplyType  
DO_SetAssumedContentType  
DO_SetBaudRate  
DO_SetBaudRateEX  
DO_SetJavascriptCleanupThreshold  
DO_SetMaxBrowserThreads  
DO_SetMaximumRetries  
DO_SetRetryWait  
DO_SetSSLConnectString  
DO_SSLReuseSession  
DO_SSLUseCipher  
DO_SSLUseClientCert  
DO_SSLUseProxy  
DO_SetTimeout  
DO_UsePersistentConnections  
DO_UseProxy
```

### Versions

Versions of **Set** are:

```
boolean Set ( WWWSetDurationEnum  
             duration, WWWSetOptionBoolEnum  
             bool_option, boolean  
             boolean );
```



```

boolean Set ( WWWSetDurationEnum
    duration, WWWSetCachingOptionsEnum
    cache_option, WWWSetCachingValuesEnum
    cache_value );

boolean Set ( WWWSetDurationEnum duration,
    WWWSetOptionIntegerEnum int_option,
    integer integer );

boolean Set ( WWWSetDurationEnum
    duration, WWWSetProxyOptionsEnum
    proxy_option, WWWSetProxyModeValueEnum
    proxy_mode_value );

boolean Set ( WWWSetDurationEnum duration,
    WWWSetOptionTextEnum string1_option, string
    string );

boolean Set ( WWWSetDurationEnum duration,
    WWWSetOptionText2Enum string2_option, string
    string1, string string2 );

boolean Set ( WWWSetDurationEnum
    duration, WWWSetOptionText3Enum
    string3_option, string
    string1, string
    string2, string
    string3 );

boolean Set ( WWWSetDurationEnum
    duration, WWWSetOptionNumericReferenceEnum int_option,
    NUMERIC_REFERENCE_LIST myReferences );

boolean Set ( WWWSetDurationEnum
    duration, WWWSetOptionEntityListEnum int_option,
    ENTITY_LIST myEntities );

boolean Set ( WWWSetDurationEnum
    duration, WWWSetOptionBoolEnum bool_option,
    WWWSetJavaScriptLevelEnum js_level );

```

## ShowMediaRP

Applies to Real Networks Streaming Media. Displays the media during a load test.

Audio and video can be controlled separately. If video is enabled, a dialog box displays the video. For audio, the sound from the media will play through the sound device.

### Notes:

- ! Exercise caution when using this feature. Use the audio display for one virtual user only. If enabling audio on two virtual users, audio from the two streams contends for the audio device. By default, audio and video do not display. Displaying the media for audio or video uses extra system resources and may degrade performance and skew test results.
- ! Real Networks streaming media is only supported in process mode. On the QALoad Player main window, in the Run As: group, select the Process option.
- ! Real Networks streaming media is only supported on a stand-alone QALoad Player or if the QALoad Player and QALoad Conductor are on the same machine.
- ! For streaming media playback, QALoad requires specific media player versions. For a list of supported versions, refer to "System Requirements" in the "Installing QALoad" chapter of the QALoad Installation and Configuration Guide.

### Syntax

```
ShowMediaRP( BOOL showAudio, BOOL showVideo );
```

### Return Value

### Parameters

Parameter	Description
showAudio	Display and play audio.
showVideo	Display video.

### Example

```
ShowMediaRP( FALSE, TRUE );  
// Display video, but leave audio muted
```

## SiebelInitialize

Initializes the Siebel correlation library and treats the current script file as a Siebel file. If the Siebel correlation library dll (ssdtcorr.dll) is not present in the BinaryFiles folder under the QALoad directory, it throws an error in the TRACE window and exits the playback.

### Syntax

```
SiebelInitialize()
```

### Return Value

void

### Parameters

None.

### Example

```
SiebelInitialize()
```

## SiebelUpdatePage

Feeds the current response (response from last request) to the Siebel library. This tells the Siebel library to extract the Siebel parameter values from the response.

### Syntax

```
SiebelUpdatePage()
```

### Return Value

void

### Parameters

None.

### Example

```
SiebelUpdatePage()
```

## Verify

Applies to Visual Scripting. Used to verify expected text against an element of the page just requested.

### Versions

Versions of Verify are:

```
boolean Verify ( WWWVerificationSpecifierEnum type, string expected );
```

```
boolean Verify ( WWWVerificationTypeEnum type, WWWVerificationSpecifierEnum specifier, string expected );
```

```
boolean Verify ( WWWVerificationTypeEnum type, int count, WWWVerificationSpecifierEnum specifier, const char* description, Verify_Size size, string expected );
```

## WWW\_FATAL\_ERROR

Applies to HTTP and SSL requests. Also applies to Visual Scripting. WWW\_FATAL\_ERROR aborts or restarts a virtual user in the event of an error during replay.

This command handles error conditions in a script that invalidates the transaction. WWW\_FATAL\_ERROR is called internally by all script commands to report error conditions.

If Abort Transaction is selected in the Error Handling column of the QALoad Conductor Script Assignment tab, then WWW\_FATAL\_ERROR aborts the virtual user after generating a debug log and notifying the QALoad Conductor that it is aborting.

If Restart Transaction is selected in the Error Handling column, then WWW\_FATAL\_ERROR restarts the transaction from the restart point (DO\_SetTransactionStart or RESTART\_TRANSACTION\_TOP) after generating a debug log and notifying the QALoad Conductor about the restart.

If Continue Transaction is selected in the Abort on Error Handling column, then the virtual user continues as if no error had occurred. This may cause a virtual user middleware exception if WWW\_FATAL\_ERROR was called because the transaction is in an unstable state.

### Syntax

```
WWW_FATAL_ERROR ( const char *short_desc, const char *long_desc ) ;
```

## Return Value

## Parameters

Parameter	Description
short_desc	A string containing a one-word description of the error. This is often the name of the function where an error was encountered.
long_desc	A longer description of the error.

## Example

```
WWW_FATAL_ERROR ( "My Func", "An error has occurred" );
```

## X\_Coord

Applies to Visual Scripting. Marks the x\_value parameter as an x-coordinate value.

## Syntax

```
X_Coord( string x_value );
```

## Return Value

Returns the x-coordinate value.

## Parameters

Parameter	Description
x_value	The x-coordinate value.

## Example

```
// X_Coord and Y_Coord return the string passed into them. They are a
// label to make clicking on a server side imagemap easier to read.
Click_On(IMAGE, 1, SRC_ATTRIBUTE, "http://host.com/server-map.jpg", X_Coord("25"),
Y_Coord("60"));
// does the same as
Click_On(IMAGE, 1, SRC_ATTRIBUTE, "http://host.com/server-map.jpg", "25", "60");
```

## XmlRequest

Applies to Visual Scripting. The XmlRequest function takes in the HTTP action and a URL and constructs a request to navigate to the URL.

If the method is "GET", XmlRequest makes a request for the URL expecting to get an XML reply. If the method is "POST", XmlRequest finishes an XML message and posts the message to the URL, expecting to get an XML reply.

XmlRequest is a direct replacement for Navigate\_To and Post\_To when the HTTP reply contains XML.

## Syntax

```
boolean XMLRequest ( string method, string URL );
```

### Return Value

True if the requested page is successfully retrieved.

False if the requested page is not successfully retrieved.

### Parameters

Parameter	Description
method	HTTP request method ("GET" or "POST")
URL	A URL containing the location of the page to be requested.

### Examples

```
XmlRequest ( "GET", "http://msoapsampleserver/
MSSoapSamples/Echo/Service/Rpc/IsapiCpp/Echo.wsdl" );
XmlRequest ( "POST",
"http://MSSoapSampleServer:80/MSSoapSamples/Echo/Service/Rpc/IsapiCpp/Echo.wsdl" );
```

### Y\_Coord

Applies to Visual Scripting. Marks the `y_value` parameter as a y-coordinate value.

### Syntax

```
Y_Coord( string y_value );
```

### Return Value

Returns the y-coordinate value.

### Parameters

Parameter	Description
<code>y_value</code>	The y-coordinate value.

### Example

```
// X_Coord and Y_Coord return the string passed into them. They are a
// label to make clicking on a server side imagemap easier to read.
Click_On(IMAGE, 1, SRC_ATTRIBUTE, "http://host.com/server-map.jpg", X_Coord("25"),
Y_Coord("60"));

// does the same as
Click_On(IMAGE, 1, SRC_ATTRIBUTE, "http://host.com/server-map.jpg", "25", "60");
```



# Index

## A

AddrByte ..... 244

Attach ..... 277

## B

BEGIN\_CHECKPOINT ..... 4, 163

BEGIN\_TRANSACTION ..... 163

BEGIN\_UENTITY ..... 218

BeginBlock ..... 18

BeginCheckpoint ..... 4, 163

## C

Citrix

    commands ..... 16

CitrixInit ..... 19

CitrixUninit ..... 19

Clear ..... 278

Click, Citrix command ..... 20

Click\_On ..... 280

CLOSE\_ALL\_DATA\_POOLS ..... 4, 164

CLOSE\_DATA\_POOL ..... 5, 164

commands

    Citrix ..... 16

    common ..... 160

    ODBC ..... 45

    Oracle Forms Server ..... 89

    QALoad ..... 160

    SAP ..... 190

    SSL ..... 207

    TestPartner ..... 212

    UNIFACE ..... 216

    Winsock ..... 241

    WWW ..... 270

COUNTER\_VALUE ..... 5, 164

Ctx\_Error\_Handler ..... 19

CtxClick ..... 20

CtxConnectICA ..... 21

CtxConnectPubApp ..... 21

CtxConnectServer ..... 22

CtxDisconnect ..... 22

CtxDoubleClick ..... 23

CtxFullBitmapExists ..... 23

CtxKeyDown ..... 23

CtxKeyUp ..... 24

CtxMouseDown ..... 24

CtxMouseMove ..... 26

CtxMouseUp ..... 26

CtxPartialBitmapExists ..... 27

CtxPoint ..... 27

CtxScreenEventExists ..... 28

CtxSetCitrixPort ..... 28

CtxSetConnectTimeout ..... 29

CtxSetDisconnectTimeout ..... 29

CtxSetEnableCounters ..... 30

CtxSetEnableWildcardMatching ..... 31

CtxSetGracefulDisconnect ..... 31

CtxSetOutputMode ..... 31

CtxSetWaitPointTimeout ..... 32

CtxSetWindowMatchTitle ..... 32

CtxSetWindowRetries ..... 33

CtxSetWindowTimeout ..... 33

CtxSetWindowTitle ..... 34

CtxSetWindowVerification ..... 35

CtxType ..... 35

CtxTypeChar ..... 35

CtxTypeVK ..... 36

CtxWaitForCaptionChange ..... 37

CtxWaitForFullBitmap ..... 37

## Language Reference Commands

CtxWaitForPartialBitmap .....	38	DO_EnableJavascript .....	294
CtxWaitForScreenUpdate .....	38	DO_EncodeString.....	295
CtxWaitForWindowActivate.....	38	Do_ExtractString.....	169
CtxWaitForWindowCreate .....	39	DO_FreeHttp .....	295
CtxWaitforWindowDestroy .....	39	DO_FreeODBC .....	49
CtxWaitForWindowLglIconChange .....	40	DO_GetAnchorByNumber .....	296
CtxWaitForWindowMinimize .....	40	DO_GetAnchorCount .....	297
CtxWaitForWindowMove.....	41	DO_GetAnchorHREF .....	297
CtxWaitForWindowResize.....	41	DO_GetAnchorHREFEx .....	298
CtxWaitForWindowSmIconChange.....	42	DO_GetAnchorHREFn .....	299
CtxWaitforWindowStyleChange.....	43	DO_GetCitrixICAFile.....	300
CtxWindowEventExists.....	43	DO_GetClientMapHREF .....	302
<b>D</b>		DO_GetCookie.....	302
datapool		DO_GetCookieFromReplyEx .....	303
substituting a string .....	15, 189	DO_GetCookiesForURL .....	304
DATE_TIME.....	165	DO_GetFormActionStatement.....	306
DefaultCheckpointsOn .....	166	DO_GetFormValueByName.....	306
DEFINE_COUNTER.....	5, 166	DO_GetHeaderFromReply .....	308
DEFINE_TRANS_TYPE.....	167	DO_GetLastHttpError .....	308
DisableStatisticsRP .....	280	DO_GetRedirectedURL .....	309
Disconnect, Citrix command .....	22	DO_GetReplyBuffer .....	309
DO_AbortOnError .....	168	DO_GetReplyBufferLength .....	310
DO_AddHeader .....	280	DO_GetUniqueString.....	310
DO_AdditionalSubRequest.....	281	DO_GetUniqueStringEx.....	311
DO_AllowTrafficFrom .....	282	DO_Http .....	312
DO_AttachFile.....	282	DO_HttpCleanup.....	313
DO_AutomaticSubRequests .....	283	DO_Https.....	208, 313
DO_BasicAuthorization .....	285	DO_HTTPVersion.....	314
DO_BlankOutOfRangeData .....	285	DO_InitHttp.....	314
DO_BlockTrafficFrom .....	286	DO_initODBC .....	49
DO_Cache.....	286	DO_IPSpoofofEnable.....	315
DO_Clear.....	287	DO_LoadMem .....	50
DO_ClearCache.....	290	DO_Logfile_URB .....	219
DO_ClearDNSCache .....	290	DO_MSLEEP.....	7, 170
DO_ClearJavascript .....	291	DO_NTLMAuthorization .....	316
DO_DynamicCookieHandling.....	291	DO_ProxyAuthorization .....	317
DO_DynamicRedirectHandling.....	293	DO_ProxyExceptions.....	317



DO_ProxyHttpVersion .....	318	DO_SQLFetch .....	64
DO_SaveReplyType .....	318	DO_SQLFreeConnect .....	64
DO_SetAssumedContentType.....	319	DO_SQLFreeHandle .....	65
DO_SetBaudRate .....	320	DO_SQLFreeStmt .....	66
DO_SetBaudRateEx .....	320	DO_SQLGetCursorName .....	66
DO_SetCookie .....	321	DO_SQLGetData .....	67
DO_SetCookieEx .....	321	DO_SQLGetDescField .....	68
DO_SetJavascriptCleanupThreshold .....	322	DO_SQLGetDescRec .....	68
Do_SetJavaScriptLevel .....	323	DO_SQLGetEnvAttr .....	69
DO_SetMaxBrowserThreads.....	323	DO_SQLGetTypeInfo .....	70
DO_SetMaximumRetries.....	324	DO_SQLNumResultCols .....	71
DO_SetPostDelay .....	324	DO_SQLParamData.....	72
DO_SetRefreshTimeout .....	325	DO_SQLPrepare .....	72
DO_SetRetryWait .....	325	DO_SQLPutData .....	73
DO_SetSSLConnectString.....	208	DO_SQLRetrieveParamValue.....	73
DO_SetTimeout .....	326	DO_SQLRowCount .....	74
DO_SetTransactionCleanup.....	170	DO_SQLSetConnectAttr .....	74
DO_SetTransactionStart .....	171	DO_SQLSetConnectOption .....	75
DO_SetValue .....	171	DO_SQLSetCursorName .....	77
DO_SLEEP .....	7, 172	DO_SQLSetDescField .....	78
DO_SQLAllocConnect .....	50	DO_SQLSetDescRec .....	78
DO_SQLAllocHandle.....	51	DO_SQLSetEnvAttr .....	79
DO_SQLAllocStmt .....	52	DO_SQLSetPos.....	80
DO_SQLBindCol .....	52	DO_SQLSetStmtAttr.....	81
DO_SQLBindParameter .....	54	DO_SQLSetStmtOption .....	81
DO_SQLCancel.....	56	DO_SQLSpecialColumns .....	84
DO_SQLCloseCursor .....	57	DO_SQLStatistics.....	86
DO_SQLColAttribute .....	57	DO_SQLTables.....	87
DO_SQLColumns.....	58	DO_SQLTransact.....	87
DO_SQLConnect .....	59	DO_SSLReuseSession.....	209
DO_SQLCopyDesc .....	60	DO_SSLUseCipher.....	210
DO_SQLDescribeCol .....	61	DO_SSLUseClientCert.....	211
DO_SQLDisconnect .....	61	DO_SSLUseClientCertPass.....	211
DO_SQLDriverConnect.....	62	DO_SSLUseProxy .....	212
DO_SQLEndTran .....	62	DO_substr .....	88
DO_SQLExecDirect .....	63	DO_URB_AsciiToHex .....	219
DO_SQLExecute.....	63	DO_URB_Init .....	220

## Language Reference Commands

DO_URB_setoprretry .....	220	DO_UseProxy .....	327
DO_URB_ubin2uf .....	220	DO_UseProxyAutomaticConfiguration .....	328
DO_URB_udbl2uf .....	221	DO_VerifyDocTitle .....	329
DO_URB_ucreate .....	221	DO_WSK_Accept .....	245
DO_URB_udelete .....	222	DO_WSK_Bind .....	245
DO_URB_uentcreo .....	223	DO_WSK_Closesocket .....	246
DO_URB_uentoccs .....	223	DO_WSK_Connect .....	246
DO_URB_uentseto .....	224	DO_WSK_Expect .....	246
DO_URB_ufreeh .....	224	DO_WSK_ExpectAny .....	247
DO_URB_uinstdel .....	225	DO_WSK_ExpectAnyExpr .....	248
DO_URB_uinstnew .....	225	DO_WSK_ExpectExpr .....	248
DO_URB_uinstopr .....	226	DO_WSK_GetSocket .....	249
DO_URB_ulist2uf .....	226	DO_WSK_Getsockname .....	249
DO_URB_ulistdel .....	227	DO_WSK_HexDecode .....	250
DO_URB_ulistfree .....	228	DO_WSK_Init .....	250
DO_URB_ulistget .....	228	DO_WSK_Ioctlsocket .....	250
DO_URB_ulistnew .....	229	DO_WSK_IsReadable .....	251
DO_URB_ulistput .....	230	DO_WSK_IsWritable .....	252
DO_URB_ulistputlist .....	231	DO_WSK_IsWriteable .....	252
DO_URB_ulistputx .....	231	DO_WSK_Listen .....	252
DO_URB_ulong2uf .....	232	DO_WSK_Quiet .....	253
DO_URB_unifree .....	232	DO_WSK_Read .....	253
DO_URB_uniname .....	233	DO_WSK_Recv .....	253
DO_URB_uopract .....	234	DO_WSK_Recvfrom .....	254
DO_URB_uoprprms .....	234	DO_WSK_Reorder .....	255
DO_URB_uprmdir .....	235	DO_WSK_Select .....	255
DO_URB_uprmgeth .....	235	DO_WSK_Send .....	256
DO_URB_uprmtype .....	236	DO_WSK_SendAll .....	257
DO_URB_ustr2uf .....	236	DO_WSK_Sendto .....	257
DO_URB_uuf2bin .....	237	DO_WSK_Setsockopt .....	258
DO_URB_uuf2dbl .....	238	DO_WSK_Shutdown .....	259
DO_URB_uuf2list .....	238	DO_WSK_Socket .....	259
DO_URB_uuf2long .....	239	DO_WSK_Write .....	260
DO_URB_uuf2str .....	239	DO_WWWFree .....	329
DO_UseEntityList .....	326	DO_WWWInitialize .....	330
DO_UseNumericReferenceList .....	326	DoubleClick, Citrix command .....	23
DO_UsePersistentConnections .....	327	DownloadMediaFromASX .....	331

DownloadMediaRP .....	331	KeyUp .....	24
DownloadMediaWMP.....	332	<b>L</b>	
<b>E</b>		LoByte .....	263
EnableStatisticsRP .....	333	Log .....	264
END_CHECKPOINT .....	8, 174	LOG_ERROR.....	178
END_TRANSACTION .....	173	<b>M</b>	
END_UENTITY .....	240	Modify_Encoding common .....	179
EndBlock .....	44	ModifyEncoding .....	337
EndCheckpoint .....	8, 174	MouseDown .....	24
EscapeStr .....	260	MouseMove.....	26
EXIT.....	174	MouseUp.....	26
ExtractString.....	334	MyByteOrder.....	264
<b>F</b>		<b>N</b>	
Fill_In .....	335	Navigate_To .....	337
<b>G</b>		<b>O</b>	
Get .....	336	OctalToChar .....	179
GET_ABSOLUTE_VUNUM .....	8, 174	ODBC	
Get_Data .....	9, 175	commands.....	45
GET_DATA_FIELD .....	9, 175	ofsActivateListItem .....	95
GET_DATAPOOLS_DIR.....	176	ofsActivateTreeItem .....	96
GET_HOME_DIR.....	176	ofsActivateWindow .....	97
GET_LOGFILES_DIR.....	176	ofsClickButton .....	97
GET_RELATIVE_VUNUM.....	9, 177	ofsClickTextFieldItem .....	98
GET_SCRIPTS_DIR .....	177	ofsClosePopList .....	99
GET_TIMINGFILES_DIR.....	178	ofsCloseWindow .....	100
GET_TOTAL_TRANSACTIONS.....	10	ofsCollapseTreeItem .....	101
GET_TRANSACTION_NUMBER.....	10	ofsColorAdd .....	101
GetBindColumnData .....	89	ofsConnectToSocket .....	102
GetLocalAddr .....	261	ofsDeActivateWindow .....	103
GetLocalPort .....	262	ofsDefineTreeNode .....	104
GetRemoteAddr.....	262	ofsDefineTreeNodeOffset .....	105
GetRemotePort .....	262	ofsDelconifyWindow .....	106
GetSiebelValue .....	336	ofsDeSelectItem .....	106
<b>H</b>		ofsDeselectTreeEvent .....	107
HiByte.....	263	ofsEdit .....	108
<b>K</b>		ofsExpandTreeItem .....	109
KeyDown.....	23	ofsFindLOVValue .....	110

## Language Reference Commands

ofsFocus.....	111	ofsSetICXTicket.....	134
ofsGetServerData.....	111	ofsSetInitialVersion.....	135
ofsHideWindow.....	112	ofsSetJavaContainerArgName.....	136
ofsHTTPConnectToFormsServlet.....	113	ofsSetJavaContainerArgValue.....	136
ofsHTTPConnectToListenerServlet.....	113	ofsSetJavaContainerEvent.....	137
ofsHTTPDisconnect.....	114	ofsSetLogonDatabase.....	138
ofsHTTPInitialFormsConnect.....	114	ofsSetLogonPassWord.....	138
ofsHTTPSetHdrProperty.....	114	ofsSetLogonUserName.....	139
ofsHTTPSetListenerServletParms.....	115	ofsSetNoRequiredVAList.....	140
ofsIconifyWindow.....	115	ofsSetPropertyBoolean.....	140
ofsIndexKey.....	116	ofsSetPropertyByte.....	141
ofsIndexSKey.....	117	ofsSetPropertyByteArray.....	142
ofsInitSessionCmdLine.....	117	ofsSetPropertyCharacter.....	142
ofsInitSessionTimeZone.....	118	ofsSetPropertyDate.....	143
ofsListItemValue.....	119	ofsSetPropertyFloat.....	144
ofsLoadValue.....	119	ofsSetPropertyInteger.....	145
ofsLOVRequestRow.....	120	ofsSetPropertyPoint.....	145
ofsLOVSelection.....	121	ofsSetPropertyRectangle.....	146
ofsMenuParamDlgOK.....	122	ofsSetPropertyString.....	147
ofsOpenWindow.....	122	ofsSetPropertyStringArray.....	147
ofsRemoveFocus.....	123	ofsSetPropertyVoid.....	148
ofsScroll.....	124	ofsSetRequiredVAList.....	149
ofsScrollSize.....	124	ofsSetRunOptions.....	150
ofsSelectItem.....	125	ofsSetScaleInfo.....	151
ofsSelectMenuItem.....	126	ofsSetScreenResolution.....	152
ofsSelectTreeEvent.....	127	ofsSetSelection.....	152
ofsSendRecv.....	127	ofsSetServerFailedMsg.....	153
ofsServerSideDisconnect.....	128	ofsSetServletMode.....	154
ofsSetColorDepth.....	128	ofsSetValue.....	155
ofsSetCursorPosition.....	129	ofsSetWindowLocation.....	154
ofsSetDisplaySize.....	129	ofsSetWindowSize.....	156
ofsSetErrorDialogTitle.....	130	ofsShowWindow.....	156
ofsSetExpectedServerMsg.....	131	ofsSocketDisconnect.....	157
ofsSetFontName.....	131	ofsStartSubMessage.....	157
ofsSetFontSize.....	132	ofsTabControlTopPage.....	158
ofsSetFontStyle.....	133	ofsUnsetPropertyBoolean.....	159
ofsSetFontWeight.....	133	ofsWindowCreated.....	159

- OPEN\_DATA\_POOL ..... 10, 180
- Oracle Forms Server
  - commands ..... 89
- P**
- password-protected directory ..... 285
- PlayMedia ..... 337
- Point ..... 27
- Post\_To ..... 338
- Q**
- QALoad
  - commands ..... 160
- R**
- RandNumString ..... 338
- RANDOM\_NUMBER ..... 181
- RANDOM\_STRING ..... 181
- READ\_DATA\_RECORD ..... 11, 182
- Region ..... 339
- Response ..... 265
- ResponseLength ..... 265
- RESTART\_TRANSACTION\_BOTTOM ..... 339
- RESTART\_TRANSACTION\_TOP ..... 339
- restarting transactions
  - DO\_SetTransactionCleanup ..... 170
  - DO\_SetTransactionStart ..... 171
- RND\_DELAY ..... 11, 182
- RND\_DELAY\_RANGE ..... 12, 183
- RR\_FailedMsg ..... 183
- RR\_GetDebugFlag ..... 184
- RR\_printf ..... 12, 184
- S**
- SAP
  - commands ..... 190
  - SAPGuiApplication ..... 191
  - SAPGuiCheckScreen ..... 192
  - SAPGuiCheckStatusBar ..... 193
  - SAPGuiCmd0 ..... 193
  - SAPGuiCmd1 ..... 194
  - SAPGuiCmd1Coll ..... 195
  - SAPGuiCmd1Elmnt ..... 195
  - SAPGuiCmd1Sub ..... 196
  - SAPGuiCmd1Sub1 ..... 197
  - SAPGuiCmd2 ..... 198
  - SAPGuiCmd3 ..... 198
  - SAPGuiConnect ..... 199
  - SAPGuiContentCheck ..... 199
  - SAPGuiCreateColl ..... 200
  - SAPGuiDestroyColl ..... 201
  - SAPGuiGetControlText ..... 202
  - SAPGuiGetUniqueString ..... 203
  - SAPGuiPropIdStr ..... 203
  - SAPGuiPropIdStrExists ..... 204
  - SAPGuiPropIdStrExistsEnd ..... 204
  - SAPGuiSessionInfo ..... 205
  - SAPGuiSetCheckScreenWildcard ..... 206
  - SAPGuiVerCheckStr ..... 207
  - ScanExpr ..... 265
  - ScanFloat ..... 266
  - ScanInt ..... 267
  - ScanLenString ..... 267
  - ScanRewind ..... 268
  - ScanSkip ..... 268
  - ScanString ..... 268
  - SCRIPT\_MESSAGE ..... 14, 186
  - Set ..... 340
  - SET\_ABORT\_FUNCTION ..... 187
  - SET\_SCRIPT\_LANGUAGE ..... 187
  - SetCitrixPort ..... 28
  - SetConnectTimeout ..... 29
  - SetDisconnectTimeout ..... 29
  - SetDomainLoginInfo ..... 30
  - SetEnableCounters ..... 30
  - SetEnableWildcardMatching ..... 31
  - SetTimeout ..... 269
  - SetWaitPointTimeout ..... 32

## Language Reference Commands

SetWindowMatchName.....	32	Type .....	35
SetWindowMatchTitle .....	32	TypeChar .....	35
SetWindowRetries.....	33	TypeVK.....	36
SetWindowTimeout .....	33	<b>U</b>	
SetWindowVerification .....	35	UFIELD .....	240
ShowMediaRP .....	341	UnEscapeStr .....	270
SiebelInitialize.....	342	UNIFACE	
SiebelUpdatePage .....	343	commands.....	216
SkipExpr .....	269	<b>V</b>	
SLEEP.....	15, 188	VARDATA.....	15, 189
<b>SSL</b>		Verify .....	343
commands .....	207	<b>W</b>	
SYNCH .....	189	Winsock	
SYNCHRONIZE .....	188	commands.....	241
<b>T</b>		WWW	
technical support .....	iii	commands.....	270
TestPartner		WWW_FATAL_ERROR.....	343
commands .....	212	<b>X</b>	
TP_Init.....	213	X_Coord.....	344
TP_Uninit.....	213	XmlRequest.....	344
TPExecuteScript.....	214	<b>Y</b>	
TPExecuteVisualTest .....	215	Y_Coord .....	345
TPSetType.....	215		